


Nama : Giovanny Dani Saputra


NIM : L200170159

# Modul 11

1. Buat topologi seperti pada gambar.



## 2. Konfigurasi semua router a. Router Jarkom



The screenshot shows a web-based interface for configuring a network device. At the top, there's a title bar 'LAB JARKOM' and a tabbed menu with 'Physical', 'Config', 'CLI', and 'Attributes'. The 'CLI' tab is active, displaying the 'IOS Command Line Interface'. The interface shows the initial configuration steps for a router named 'JARKOM'. It starts with a system configuration dialog asking if the user wants to enter the initial configuration, which is answered 'no'. Then, the user enters 'en' to enter configuration mode. The configuration commands entered are: 'conf t' to enter configuration mode, 'hostname JARKOM' to set the router's name, 'int fa0/0' to select the first FastEthernet interface, 'ip address 172.16.0.1 255.255.255.0' to assign the IP address, and 'no shutdown' to enable the interface. The interface status changes to 'up'. The user then exits the configuration mode with 'exit'. The same steps are repeated for the second FastEthernet interface 'fa1/0' with IP address '172.15.0.1'. Finally, the user exits the configuration mode with 'exit'. The interface shows the final configuration and a prompt to press Ctrl+F6 to exit CLI focus.

```
LAB JARKOM
Physical Config CLI Attributes
IOS Command Line Interface

--- System Configuration Dialog ---
Would you like to enter the initial configuration dialog? [yes/no]: no

Press RETURN to get started!

Router>en
Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#hostname JARKOM
JARKOM(config)#int fa0/0
JARKOM(config-if)#ip address 172.16.0.1 255.255.255.0
JARKOM(config-if)#no shutdown

JARKOM(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up

JARKOM(config-if)#exit
JARKOM(config)#int fa1/0
JARKOM(config-if)#ip address 172.15.0.1 255.255.255.0
JARKOM(config-if)#no shutdown


JARKOM(config-if)#
%LINK-5-CHANGED: Interface FastEthernet1/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet1/0, changed state to up

JARKOM(config-if)#exit
JARKOM(config)#

Ctrl+F6 to exit CLI focus

☐ Top
```

## b. Router SI



```
LAB SI
Physical Config CLI Attributes
IOS Command Line Interface

Router>show speed serial(sync/async, network interface(s)
32K bytes of non-volatile configuration memory.
63488K bytes of ATA CompactFlash (Read/Write)

--- System Configuration Dialog ---

Would you like to enter the initial configuration dialog? [yes/no]: no

Press RETURN to get started!

Router>en
Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#hostname SistemInformasi
SistemInformasi(config)#int fa0/0
SistemInformasi(config-if)#ip address 172.17.0.1 255.255.255.0
SistemInformasi(config-if)#no shutdown

SistemInformasi(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up

SistemInformasi(config-if)#exit
SistemInformasi(config)#int fa1/0
SistemInformasi(config-if)#ip address 172.15.0.2 255.255.255.0
SistemInformasi(config-if)#no shutdown


SistemInformasi(config-if)#
%LINK-5-CHANGED: Interface FastEthernet1/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet1/0, changed state to up

SistemInformasi(config-if)#exit
SistemInformasi(config)#

Ctrl+F6 to exit CLI focus
```

### c. Router RPL



```
LAB RPL
Physical Config CLI Attributes
IOS Command Line Interface

Router>
32K bytes of non-volatile configuration memory.
63488K bytes of ATA CompactFlash (Read/Write)

--- System Configuration Dialog ---

Would you like to enter the initial configuration dialog? [yes/no]: no

Press RETURN to get started!

Router>en
Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#hostname RPL
RPL(config)#int fa0/0
RPL(config-if)#ip address 172.18.0.1 255.255.255.0
RPL(config-if)#no shutdown

RPL(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up


RPL(config-if)#exit
RPL(config)#int fa1/0
RPL(config-if)#ip address 172.15.0.3 255.255.255.0
RPL(config-if)#no shutdown

RPL(config-if)#
%LINK-5-CHANGED: Interface FastEthernet1/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet1/0, changed state to up

RPL(config-if)#exit
RPL(config)#

Ctrl+F6 to exit CLI focus
```

### d. Router UMS



3. Konfigurasi routing table pada 4 router
  - a. Router Jarkom

```

JARKOM(config)#router rip
JARKOM(config-router)#network 172.16.0.0
JARKOM(config-router)#network 172.16.0.0
^
% Invalid input detected at '^' marker.

JARKOM(config-router)#network 172.16.0.0
JARKOM(config-router)#network 172.17.0.0
JARKOM(config-router)#network 172.18.0.0
JARKOM(config-router)#network 172.19.0.0
JARKOM(config-router)#

```

- b. Router SI

```

SistemInformasi(config)#router rip
SistemInformasi(config-router)#network 172.16.0.0
SistemInformasi(config-router)#network 172.16.0.0
SistemInformasi(config-router)#network 172.17.0.0
SistemInformasi(config-router)#network 172.18.0.0
SistemInformasi(config-router)#network 172.19.0.0
SistemInformasi(config-router)#

Ctrl+F6 to exit CLI focus

```

c. Router RPL

```
RPL(config)#router rip
RPL(config-router)#network 172.15.0.0
RPL(config-router)#network 172.16.0.0
RPL(config-router)#network 172.17.0.0
RPL(config-router)#network 172.18.0.0
RPL(config-router)#network 172.19.0.0
RPL(config-router)#
```


Ctrl+F6 to exit CLI focus

d. Router UMS


```
UMS(config)#router rip
UMS(config-router)#network 172.15.0.0
UMS(config-router)#network 172.16.0.0
UMS(config-router)#network 172.17.0.0
UMS(config-router)#network 172.18.0.0
UMS(config-router)#network 172.19.0.0
UMS(config-router)#
```

4. Konfigurasi IP pada masing- masing PC


a. PC Jarkom



b. PC SI




c. PC RPL





d. PC UMS



2. Lakukan pengujian ICMP request(ping) untuk test koneksi a.  
PC UMS ke PC Jarkom

```
C:\>ping 172.16.0.2

Pinging 172.16.0.2 with 32 bytes of data:

Reply from 172.16.0.2: bytes=32 time=1ms TTL=126
Reply from 172.16.0.2: bytes=32 time=12ms TTL=126
Reply from 172.16.0.2: bytes=32 time=12ms TTL=126
Reply from 172.16.0.2: bytes=32 time=12ms TTL=126

Ping statistics for 172.16.0.2:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 1ms, Maximum = 12ms, Average = 9ms
```

b. PC UMS ke PC SI

```
C:\>ping 172.18.0.2

Pinging 172.18.0.2 with 32 bytes of data:

Reply from 172.18.0.2: bytes=32 time<1ms TTL=126
Reply from 172.18.0.2: bytes=32 time=15ms TTL=126
Reply from 172.18.0.2: bytes=32 time=19ms TTL=126
Reply from 172.18.0.2: bytes=32 time=12ms TTL=126

Ping statistics for 172.18.0.2:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 0ms, Maximum = 19ms, Average = 11ms

C:\>
```

c. PC UMS ke PC RPL



```
C:\>ping 172.17.0.2
```

```
Pinging 172.17.0.2 with 32 bytes of data:
```

```
Reply from 172.17.0.2: bytes=32 time<1ms TTL=126
```

```
Reply from 172.17.0.2: bytes=32 time=19ms TTL=126
```

```
Reply from 172.17.0.2: bytes=32 time=10ms TTL=126
```

```
Reply from 172.17.0.2: bytes=32 time=12ms TTL=126
```

```
Ping statistics for 172.17.0.2:
```

```
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
```

```
Approximate round trip times in milli-seconds:
```

```
    Minimum = 0ms, Maximum = 19ms, Average = 10ms
```