



Nama = Fredianto/L200170173/D


1. Buat topologi seperti pada gambar.



2. Konfigurasi semua router a. Router Jarkom



b. Router SI



LAB SI

Physical Config CLI Attributes

IOS Command Line Interface

```
32K bytes of non-volatile configuration memory.
63488K bytes of ATA CompactFlash (Read/Write)

--- System Configuration Dialog ---

Would you like to enter the initial configuration dialog? [yes/no]: no

Press RETURN to get started!

Router>en
Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#hostname SistemInformasi
SistemInformasi(config)#int fa0/0
SistemInformasi(config-if)#ip address 172.17.0.1 255.255.255.0
SistemInformasi(config-if)#no shutdown

SistemInformasi(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up

SistemInformasi(config-if)#exit
SistemInformasi(config)#int fal/0
SistemInformasi(config-if)#ip address 172.15.0.2 255.255.255.0
SistemInformasi(config-if)#no shutdown


SistemInformasi(config-if)#
%LINK-5-CHANGED: Interface FastEthernet1/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet1/0, changed state to up

SistemInformasi(config-if)#exit
SistemInformasi(config)#

Ctrl+F6 to exit CLI focus
```

c. Router RPL




The screenshot shows a window titled "LAB RPL" with tabs for "Physical", "Config", "CLI", and "Attributes". The "CLI" tab is active, displaying the "IOS Command Line Interface". The interface shows the following text:

```
32K bytes of non-volatile configuration memory.  
63488K bytes of ATA CompactFlash (Read/Write)  
  
--- System Configuration Dialog ---  
  
Would you like to enter the initial configuration dialog? [yes/no]: no  
  
Press RETURN to get started!  
  
Router>en  
Router#conf t  
Enter configuration commands, one per line. End with CNIL/Z.  
Router(config)#hostname RPL  
RPL(config)#int fa0/0  
RPL(config-if)#ip address 172.18.0.1 255.255.255.0  
RPL(config-if)#no shutdown  
  
RPL(config-if)#  
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up  
  
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up  
  
RPL(config-if)#exit  
RPL(config)#int fa1/0  
RPL(config-if)#ip address 172.15.0.3 255.255.255.0  
RPL(config-if)#no shutdown  
  
RPL(config-if)#  
%LINK-5-CHANGED: Interface FastEthernet1/0, changed state to up  
  
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet1/0, changed state to up  
  
RPL(config-if)#exit  
RPL(config)#
```

At the bottom of the CLI window, it says "Ctrl+F6 to exit CLI focus".

d. Router UMS



The screenshot shows a web-based configuration interface for a device named 'GATEWAY'. It has four tabs: 'Physical', 'Config', 'CLI', and 'Attributes'. The 'CLI' tab is active, displaying the 'IOS Command Line Interface'. The interface shows the output of several commands entered in the CLI. At the top, it displays system information: '32K bytes of non-volatile configuration memory' and '63488K bytes of ATA CompactFlash (Read/Write)'. Below this is a 'System Configuration Dialog' asking if the user wants to enter the initial configuration dialog, with the answer 'no'. The user is prompted to press RETURN to get started. The CLI shows the following commands and their outputs:

```
Router>en
Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#hostname UMS
UMS(config)#int fa0/0
UMS(config-if)#ip address 172.19.0.1 255.255.255.0
UMS(config-if)#no shutdown

UMS(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up

UMS(config-if)#exit
UMS(config)#int fal/0
UMS(config-if)#ip address 172.15.0.4 255.255.255.0
UMS(config-if)#no shutdown

UMS(config-if)#
%LINK-5-CHANGED: Interface FastEthernet1/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet1/0, changed state to up

UMS(config-if)#exit
UMS(config)#
```

At the bottom of the CLI window, it says 'Ctrl+F6 to exit CLI focus'. There is a 'Top' link at the bottom left of the interface.

3. Konfigurasi routing table pada 4 router

a. Router Jarkom

```
JARKOM(config)#router rip
JARKOM(config-router)#network 172.15.0.0
JARKOM(config-router)#networj 172.16.0.0
      ^
% Invalid input detected at '^' marker.

JARKOM(config-router)#network 172.16.0.0
JARKOM(config-router)#network 172.17.0.0
JARKOM(config-router)#network 172.18.0.0
JARKOM(config-router)#network 172.19.0.0
JARKOM(config-router)#
```

b. Router SI

```
SistemInformasi(config)#router rip
SistemInformasi(config-router)#network 172.15.0.0
SistemInformasi(config-router)#network 172.16.0.0
SistemInformasi(config-router)#network 172.17.0.0
SistemInformasi(config-router)#network 172.18.0.0
SistemInformasi(config-router)#network 172.19.0.0
SistemInformasi(config-router)#
```

Ctrl+F6 to exit CLI focus

c. Router RPL

```
RPL(config)#router rip
RPL(config-router)#network 172.15.0.0
RPL(config-router)#network 172.16.0.0
RPL(config-router)#network 172.17.0.0
RPL(config-router)#network 172.18.0.0
RPL(config-router)#network 172.19.0.0
RPL(config-router)#
```

Ctrl+F6 to exit CLI focus

d. Router UMS

```
UMS(config)#router rip
UMS(config-router)#network 172.15.0.0
UMS(config-router)#network 172.16.0.0
UMS(config-router)#network 172.17.0.0
UMS(config-router)#network 172.18.0.0
UMS(config-router)#network 172.19.0.0
UMS(config-router)#
```

4. Konfigurasi IP pada masing- masing PC


a. PC Jarkom

The screenshot shows the 'PC JARKOM' configuration window with the 'Config' tab selected. The 'IP Configuration' section is active, showing the following settings:


- IP Configuration:**
 - ☐ DHCP
 - ☒ Static
 - IP Address: 172.16.0.2
 - Subnet Mask: 255.255.255.0
 - Default Gateway: 172.16.0.1
 - DNS Server: 0.0.0.0
- IPv6 Configuration:**
 - ☐ DHCP
 - ☐ Auto Config
 - ☒ Static
 - IPv6 Address: (empty field) / (empty field)
 - Link Local Address: FE80::2D0:D3FF:FE30:5C09
 - IPv6 Gateway: (empty field)
 - IPv6 DNS Server: (empty field)

At the bottom left, there is a 'Top' button.


b. PC SI



c. PC RPL



d. PC UMS



2. Lakukan pengujian ICMP request(ping) untuk test koneksi a. PC UMS ke PC Jarkom

```
C:\>ping 172.16.0.2

Pinging 172.16.0.2 with 32 bytes of data:

Reply from 172.16.0.2: bytes=32 time=1ms TTL=126
Reply from 172.16.0.2: bytes=32 time=12ms TTL=126
Reply from 172.16.0.2: bytes=32 time=12ms TTL=126
Reply from 172.16.0.2: bytes=32 time=12ms TTL=126

Ping statistics for 172.16.0.2:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 1ms, Maximum = 12ms, Average = 9ms
```

- b. PC UMS ke PC SI

```
C:\>ping 172.18.0.2

Pinging 172.18.0.2 with 32 bytes of data:

Reply from 172.18.0.2: bytes=32 time<1ms TTL=126
Reply from 172.18.0.2: bytes=32 time=15ms TTL=126
Reply from 172.18.0.2: bytes=32 time=19ms TTL=126
Reply from 172.18.0.2: bytes=32 time=12ms TTL=126

Ping statistics for 172.18.0.2:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 0ms, Maximum = 19ms, Average = 11ms

C:\>
```

- c. PC UMS ke PC RPL

```
C:\>ping 172.17.0.2
```

```
Pinging 172.17.0.2 with 32 bytes of data:
```

```
Reply from 172.17.0.2: bytes=32 time<1ms TTL=126
```

```
Reply from 172.17.0.2: bytes=32 time=19ms TTL=126
```

```
Reply from 172.17.0.2: bytes=32 time=10ms TTL=126
```

```
Reply from 172.17.0.2: bytes=32 time=12ms TTL=126
```

```
Ping statistics for 172.17.0.2:
```

```
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
```

```
Approximate round trip times in milli-seconds:
```

```
    Minimum = 0ms, Maximum = 19ms, Average = 10ms
```