

## Latihan Praktikum Sistem Operasi Modul ke-3

Nama : Muhammad Ridwan NurFarizi

NIM : L200180020

Kelas : A

```
Bochs for Windows - Console
C:\>cd os

C:\OS>setpath

C:\OS>Path=C:\OS\Dev-Cpp\bin;C:\OS\Bochs-2.3.5;c:\OS\Perl;C:\Windows;C:\Windows\System32
C:\OS>cd lab



C:\OS\LAB>lab3
'lab3' is not recognized as an internal or external command,
operable program or batch file.

C:\OS\LAB>cd lab3

C:\OS\LAB\LAB3>type s.bat
..\..\bochs-2.3.5\bochsdbg -q -f bochsrc.bxrc

C:\OS\LAB\LAB3>s

C:\OS\LAB\LAB3>..\..\bochs-2.3.5\bochsdbg -q -f bochsrc.bxrc
0000000000i[APIC?] local apic in  initializing
=====
Bochs x86 Emulator 2.3.5
Build from CVS snapshot, on September 16, 2007
=====
0000000000i[      ] reading configuration from bochsrc.bxrc
0000000000i[      ] installing win32 module as the Bochs GUI
0000000000i[      ] using log file bochs.log
Next at t=0
(0) [0xffffffff] f000:fff0 (unk. ctxt): jmp far f000:e05b      ; ea5be00f0
<bochs:1> _
```



```
Bochs for Windows - Console
(0) [0x00007c00] 0000:7c00 (unk. ctxt): jmp .+0x003b (0x00007c3e) ; e93b00
<bochs:6> s
Next at t=2082129
(0) [0x00007c3e] 0000:7c3e (unk. ctxt): cli ; fa
<bochs:7> s
Next at t=2082130
(0) [0x00007c3f] 0000:7c3f (unk. ctxt): mov ax, 0x07c0 ; b8c007
<bochs:8> s
Next at t=2082131
(0) [0x00007c42] 0000:7c42 (unk. ctxt): mov ds, ax ; 8ed8
<bochs:9> s
Next at t=2082132
(0) [0x00007c44] 0000:7c44 (unk. ctxt): mov es, ax ; 8ec0
<bochs:10> s
Next at t=2082133
(0) [0x00007c46] 0000:7c46 (unk. ctxt): mov fs, ax ; 8ee0
<bochs:11> q
# In bx_win32_gui_c::exit(void)!

Bochs is exiting. Press ENTER when you're ready to close this window.

C:\OS\LAB\LAB3>s

C:\OS\LAB\LAB3>..\..\bochs-2.3.5\bochsdbg -q -f bochsrc.bxrc
00000000000i[APIC?] local apic in initializing
=====
Bochs x86 Emulator 2.3.5
Build from CVS snapshot, on September 16, 2007
=====
00000000000i[ ] reading configuration from bochsrc.bxrc
00000000000i[ ] installing win32 module as the Bochs GUI
00000000000i[ ] using log file bochs.log
Next at t=0
(0) [0xfffffff0] f000:fff0 (unk. ctxt): jmp far f000:e05b ; ea5be00f0
<bochs:1> vb 0x0100:0x0000
<bochs:2> _c
(10264512) Breakpoint 10285608, in 0100:0000 (0x00001000)
Next at t=2945013
(0) [0x00001000] 0100:0000 (unk. ctxt): mov ax, 0x0100 ; b00001
<bochs:3>
```

```
Bochs for Windows - Console
00000000000i[ ] reading configuration from bochsrc.bxrc
00000000000i[ ] installing win32 module as the Bochs GUI
00000000000i[ ] using log file bochs.log
Next at t=0
(0) [0xfffffff0] f000:fff0 (unk. ctxt): jmp far f000:e05b ; ea5be00f0
<bochs:1> vb 0x0100:0x0000
<bochs:2> _c
(10264512) Breakpoint 10285608, in 0100:0000 (0x00001000)
Next at t=2945013
(0) [0x00001000] 0100:0000 (unk. ctxt): mov ax, 0x0100 ; b00001
<bochs:3> _
Next at t=2945014
(0) [0x00001003] 0100:0003 (unk. ctxt): mov ds, ax ; 8ed8
<bochs:4> s
Next at t=2945015
(0) [0x00001005] 0100:0005 (unk. ctxt): mov es, ax ; 8ec0
<bochs:5> s
Next at t=2945016
(0) [0x00001007] 0100:0007 (unk. ctxt): cli ; fa
<bochs:6> s
Next at t=2945017
(0) [0x00001008] 0100:0008 (unk. ctxt): mov ss, ax ; 8ed0
<bochs:7> s
Next at t=2945018
(0) [0x0000100a] 0100:000a (unk. ctxt): mov sp, 0xffff ; bcffff
<bochs:8> s
Next at t=2945019
(0) [0x0000100d] 0100:000d (unk. ctxt): sti ; fb
<bochs:9> s
Next at t=2945020
(0) [0x0000100e] 0100:000e (unk. ctxt): push dx ; 52
<bochs:10> s
Next at t=2945021
(0) [0x0000100f] 0100:000f (unk. ctxt): push es ; 06
<bochs:11> s
Next at t=2945022
(0) [0x00001010] 0100:0010 (unk. ctxt): xor ax, ax ; 31c0
<bochs:12> s
Next at t=2945023
(0) [0x00001012] 0100:0012 (unk. ctxt): mov es, ax ; 8ec0
<bochs:13> _
```

