

```
Bochs for Windows - Console
Microsoft Windows [Version 10.0.15063]
(c) 2017 Microsoft Corporation. All rights reserved.

C:\Users\lenovo>cd..

C:\Users>cd..

C:\>cd os

C:\OS>setpath

C:\OS>Path=C:\OS\Dev-Cpp\bin;C:\OS\Bochs-2.3.5;c:\OS\Perl;C:\Windows;C:\Windows\System32
C:\OS>cd lab/lab3

C:\OS\LAB\LAB3>s

C:\OS\LAB\LAB3>...\bochs-2.3.5\bochsdbg -q -f bochsrc.bxrc
0000000000i[APIC?] local apic in  initializing
=====
Bochs x86 Emulator 2.3.5
Build from CVS snapshot, on September 16, 2007
=====
0000000000i[      ] reading configuration from bochsrc.bxrc
0000000000i[      ] installing win32 module as the Bochs GUI
0000000000i[      ] using log file bochs.log
Next at t=0
(0) [0xffffffff] f000:fff0 (unk. ctxt): jmp far f000:e05b      ; ea5be00f0
<bochs:1> r
rax: 0x00000000:00000000 rcx: 0x00000000:00000000
rdx: 0x00000000:0000f20 rbx: 0x00000000:00000000
```

```
Bochs for Windows - Console
<bochs:10> s
Next at t=2082132
(0) [0x00007c44] 0000:7c44 (unk. ctxt): mov es, ax      ; 8ec0
<bochs:11> s
Next at t=2082133
(0) [0x00007c46] 0000:7c46 (unk. ctxt): mov fs, ax      ; 8ee0
<bochs:12> q
# In bx_win32_gui_c::exit(void)!

Bochs is exiting. Press ENTER when you're ready to close this window.

C:\OS\LAB\LAB3>s

C:\OS\LAB\LAB3>...\bochs-2.3.5\bochsdbg -q -f bochsrc.bxrc
0000000000i[APIC?] local apic in  initializing
=====
Bochs x86 Emulator 2.3.5
Build from CVS snapshot, on September 16, 2007
=====
0000000000i[      ] reading configuration from bochsrc.bxrc
0000000000i[      ] installing win32 module as the Bochs GUI
0000000000i[      ] using log file bochs.log
Next at t=0
(0) [0xffffffff] f000:fff0 (unk. ctxt): jmp far f000:e05b      ; ea5be00f0
<bochs:1> vb 0x0100:0x0000
<bochs:2> c
(5295760) Breakpoint 10285624, in 0100:0000 (0x00001000)
Next at t=2945013
(0) [0x00001000] 0100:0000 (unk. ctxt): mov ax, 0x0100      ; b80001
```

```
Bochs for Windows - Console
<bochs:2> c
(5295760) Breakpoint 10285624, in 0100:0000 (0x00001000)
Next at t=2945013
(0) [0x00001000] 0100:0000 (unk. ctxt): mov ax, 0x0100 ; b80001
<bochs:3> s
Next at t=2945014
(0) [0x00001003] 0100:0003 (unk. ctxt): mov ds, ax ; 8ed8
<bochs:4> s
Next at t=2945015
(0) [0x00001005] 0100:0005 (unk. ctxt): mov es, ax ; 8ec0
<bochs:5> s
Next at t=2945016
(0) [0x00001007] 0100:0007 (unk. ctxt): cli ; fa
<bochs:6> s
Next at t=2945017
(0) [0x00001008] 0100:0008 (unk. ctxt): mov ss, ax ; 8ed0
<bochs:7> s
Next at t=2945018
(0) [0x0000100a] 0100:000a (unk. ctxt): mov sp, 0xffff ; bcffff
<bochs:8> s
Next at t=2945019
(0) [0x0000100d] 0100:000d (unk. ctxt): sti ; fb
<bochs:9> s
Next at t=2945020
(0) [0x0000100e] 0100:000e (unk. ctxt): push dx ; 52
<bochs:10> s
Next at t=2945021
(0) [0x0000100f] 0100:000f (unk. ctxt): push es ; 06
<bochs:11> s
Next at t=2945022
```

```
Bochs for Windows - Console
<bochs:11> s
Next at t=2945022
(0) [0x00001010] 0100:0010 (unk. ctxt): xor ax, ax ; 31c0
<bochs:12> s
Next at t=2945023
(0) [0x00001012] 0100:0012 (unk. ctxt): mov es, ax ; 8ec0
<bochs:13> s
Next at t=2945024
(0) [0x00001014] 0100:0014 (unk. ctxt): cli ; fa
<bochs:14> s
Next at t=2945025
(0) [0x00001015] 0100:0015 (unk. ctxt): mov word ptr es:0x84, 0x0030 ; 26c70684003000
<bochs:15> s
Next at t=2945026
(0) [0x0000101c] 0100:001c (unk. ctxt): mov word ptr es:0x86, cs ; 268c0e8600
<bochs:16> s
Next at t=2945027
(0) [0x00001021] 0100:0021 (unk. ctxt): sti ; fb
<bochs:17> s
Next at t=2945028
(0) [0x00001022] 0100:0022 (unk. ctxt): pop es ; 07
<bochs:18> s
Next at t=2945029
(0) [0x00001023] 0100:0023 (unk. ctxt): pop dx ; 5a
<bochs:19> s
Next at t=2945030
(0) [0x00001024] 0100:0024 (unk. ctxt): mov si, 0x01e8 ; bee801
<bochs:20> s
Next at t=2945031
(0) [0x00001027] 0100:0027 (unk. ctxt): mov al, 0x01 ; b001
```



