

## PIS03\_1

PIS03\_1

Physical Config CLI Attributes

IOS Command Line Interface

```
User Access Verification
Password:
Password:

PIS03_1>en
Password:
PIS03_1#show runn
Building configuration...

Current configuration : 1432 bytes
!
version 15.0
no service timestamps log datetime msec
no service timestamps debug datetime msec
no service password-encryption
!
hostname PIS03_1
!
enable secret 5 $1$mERr$6ft.YlcVqs09MNclUxIyr.
!
!
!
ip ssh version 2
ip domain-name PIS03_1.com
!
username PIS03_1 secret 5 $1$mERr$1jm.CBbctT6ppR/qlBpmE1
!
!
!
spanning-tree mode pvst
spanning-tree extend system-id
!
interface FastEthernet0/1
--More--
```

Ctrl+F6 to exit CLI focus

Copy Paste


PIS03\_1

Physical Config CLI Attributes

IOS Command Line Interface

```
!
interface GigabitEthernet0/1
!
interface GigabitEthernet0/2
!
interface Vlan1
 ip address 172.16.0.93 255.255.255.224
!
 ip default-gateway 172.16.0.94
!
 banner motd ^C***NO ENTRAR SIN AUTORIZACION***^C
!
!
!
line con 0
 password consoleCDMX
 logging synchronous
 login
!
line vty 0 4
 login local
 transport input ssh
line vty 5 15
 login local
 transport input ssh
!
!
!
end
```


## PISO4\_1



The screenshot shows a window titled 'PISO4\_1' with tabs for 'Physical', 'Config', 'CLI', and 'Attributes'. The 'CLI' tab is active, displaying the 'IOS Command Line Interface'. The terminal output shows the command 'show running' being executed, resulting in a display of the current configuration. The configuration includes system settings like version 15.0, service timestamps, and hostname 'PISO4\_1'. It also shows interface configurations for FastEthernet0/1 through 0/4, which are currently in a 'shutdown' state. The output is truncated with '--More--' at the bottom.

```
Password:
PISO4_1#show running
Building configuration...

Current configuration : 1432 bytes
!
version 15.0
no service timestamps log datetime msec
no service timestamps debug datetime msec
no service password-encryption
!
hostname PISO4_1
!
enable secret 5 $1$mERr76ft.Y1cVqs09MNC1UxIyr.
!
!
!
ip ssh version 2
ip domain-name PISO4_1.com
!
username PISO4_1 secret 5 $1$mERr71jm.GBbctT6ppR/qlBpmE1
!
!
!
spanning-tree mode pvst
spanning-tree extend system-id
!
interface FastEthernet0/1
!
interface FastEthernet0/2
!
interface FastEthernet0/3
!
interface FastEthernet0/4
!
--More--
```



The screenshot shows the same 'PISO4\_1' window with the 'CLI' tab active. The terminal output displays the configuration for GigabitEthernet0/1, GigabitEthernet0/2, and Vlan1. Vlan1 is configured with IP address 172.16.0.61 and a default gateway of 172.16.0.62. The configuration also includes a banner for MOTD, console settings (line con 0), and VTY settings (line vty 0 4 and line vty 5 15). The configuration ends with the 'end' command.

```
!
interface GigabitEthernet0/1
!
interface GigabitEthernet0/2
!
interface Vlan1
ip address 172.16.0.61 255.255.255.192
!
ip default-gateway 172.16.0.62
!
banner motd ^C***NO ENTRAR SIN AUTORIZACION***^C
!
!
!
line con 0
password consoleCDMX
logging synchronous
login
!
line vty 0 4
login local
transport input ssh
line vty 5 15
login local
transport input ssh
!
!
!
end
```

## PISO5\_1

PISO5\_1

Physical Config CLI Attributes

IOS Command Line Interface

```
PISO5_1>EN
Password:
PISO5_1#show runn
Building configuration...

Current configuration : 1434 bytes
!
version 15.0
no service timestamps log datetime msec
no service timestamps debug datetime msec
no service password-encryption
!
hostname PISO5_1
!
enable secret 5 $1$mERr$6ft.Y1cVqs09MNclUxIyr.
!
!
ip ssh version 2
ip domain-name PISO5_1.com
!
username PISO5_1 secret 5 $1$mERr$1jm.GBbctT6ppR/qlBpmE1
!
!
spanning-tree mode pvst
spanning-tree extend system-id
!
interface FastEthernet0/1
!
interface FastEthernet0/2
!
interface FastEthernet0/3
!
--More--
```

Ctrl+F6 to exit CLI focus

Copy Paste

PISO5\_1

Physical Config CLI Attributes

IOS Command Line Interface

```
!
interface FastEthernet0/23
!
interface FastEthernet0/24
!
interface GigabitEthernet0/1
!
interface GigabitEthernet0/2
!
interface Vlan1
 ip address 172.16.0.125 255.255.255.224
!
 ip default-gateway 172.16.0.126
!
 banner motd ^C***NO ENTRAR SIN AUTORIZACION***^C
!
!
line con 0
 password consoleCDMX
 logging synchronous
 login
!
line vty 0 4
 login local
 transport input ssh
line vty 5 15
 login local
 transport input ssh
!
!
!
```

## PISO1

DNS

Physical Config CLI Attributes

IOS Command Line Interface

```
DNS>en
Password:
DNS#show runni
Building configuration...

Current configuration : 841 bytes
!
version 12.1
no service timestamps log datetime msec
no service timestamps debug datetime msec
no service password-encryption
!
hostname DNS
!
enable secret 5 $1$mERr$6ft.YlcVqs09MMclUxIyr.
!
!
!
ip ssh version 2
ip domain-name DNS.com
!
username DNS secret 5 $1$mERr$1jm.GBbctI6ppR/qlBpmE1
!
!
!
spanning-tree mode pvst
spanning-tree extend system-id
!
interface FastEthernet0/1
!
interface FastEthernet1/1
!
interface FastEthernet2/1
!
--More--
```

DNS

Physical Config CLI Attributes

IOS Command Line Interface

```
interface FastEthernet2/1
!
interface FastEthernet3/1
!
interface FastEthernet4/1
!
interface FastEthernet5/1
!
interface Vlan1
 ip address 172.16.0.253 255.255.255.248
!
ip default-gateway 172.16.0.254
!
banner motd ^C***NO ENTRAR SIN AUTORIZACION***^C
!
!
!
line con 0
 password consoleCDMX
 logging synchronous
 login
!
line vty 0 4
 login local
 transport input ssh
line vty 5 15
 login local
 transport input ssh
!
```