


**9894**



Cisco Packet Tracer - C:\Users\usama\OneDrive\Desktop\Labtask 9694.pkt

File Edit Options View Tools Extensions Help

Logical Physical x: 109, y: 109

Time: 00:19:06

Scenario 0

Toggle PDU List Window

Usama-Router2

Physical Config CLI Attributes

IOS Command Line Interface

```

Router>enable
Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#hostname Usama
Usama(config)#interface serial 0/0/1
Usama(config-if)#ip address 12.100.0.2 255.255.255.252
Usama(config-if)#no shutdown
Usama(config-if)#
%LINK-5-CHANGED: Interface Serial0/0/1, changed state to up
Usama(config-if)#exit
Usama(config)#interface serial 0/1/0
Usama(config-if)#ip address 192.100.0.1 255.255.255.252
Usama(config-if)#clock rate 64000
Usama(config-if)#no shutdown
Usama(config-if)#
%LINK-5-CHANGED: Interface Serial0/1/0, changed state to down
Usama(config-if)#exit
Usama(config)#interface serial 0/0/0
Usama(config-if)#ip address 162.100.0.1 255.255.255.252
Usama(config-if)#clock rate 64000
Usama(config-if)#no shutdown
Usama(config-if)#
%LINK-5-CHANGED: Interface Serial0/0/0, changed state to down
Usama(config-if)#exit
Usama(config)#interface fa 0/0
Usama(config-if)#ip address 192.100.100.1 255.255.255.248
Usama(config-if)#no shutdown
Usama(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0,
changed state to up
Usama(config-if)#exit
Usama(config)#
Ctrl+F5 to exit CLI focus
  
```

Copy Paste

Time 12:29:30

Cisco Packet Tracer - C:\Users\usama\OneDrive\Desktop\Labtask 9694.pkt

File Edit Options View Tools Extensions Help

Logical Physical x: 97, y: 532

Time: 00:23:58

Scenario 0

Toggle PDU List Window

Usama-Router3

Physical Config CLI Attributes

IOS Command Line Interface

```

Router>enable
Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#hostname Usama
Usama(config)#interface serial 0/0/0
Usama(config-if)#ip address 52.100.0.1 255.255.255.252
Usama(config-if)#clock rate 64000
Usama(config-if)#no shutdown
Usama(config-if)#
%LINK-5-CHANGED: Interface Serial0/0/0, changed state to down
Usama(config-if)#exit
Usama(config)#interface serial 0/0/0
Usama(config-if)#ip address 32.100.0.1 255.255.255.252
Usama(config-if)#clock rate 64000
Usama(config-if)#no shutdown
Usama(config-if)#
%LINK-5-CHANGED: Interface Serial0/0/0, changed state to up
Usama(config-if)#exit
Usama(config)#interface serial 0/1/0
Usama(config-if)#ip address 192.100.0.2 255.255.255.252
Usama(config-if)#no shutdown
Usama(config-if)#
%LINK-5-CHANGED: Interface Serial0/1/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/1/0,
changed state to up
Usama(config-if)#exit
Usama(config)#interface fa 0/0
Usama(config-if)#ip address 192.100.100.1 255.255.255.248
Usama(config-if)#no shutdown
Usama(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0,
changed state to up
Usama(config-if)#exit
Usama(config)#
Ctrl+F5 to exit CLI focus
  
```

Copy Paste

Time 14:57:00

Cisco Packet Tracer - C:\Users\usama\OneDrive\Desktop\Labtask 9694.pkt

File Edit Options View Tools Extensions Help

Logical Physical x 140 y 697

Usama-Router4

Physical Config CLI Attributes

IOS Command Line Interface

```

Router>enable
Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#hostname Usama
Usama(config)#interface serial 0/1/1
Usama(config-if)#ip address 102.100.0.2 255.255.255.252
Usama(config-if)#no shutdown
Usama(config-if)#
%LINK-5-CHANGED: Interface Serial0/1/1, changed state to up
Usama(config-if)#exit
Usama(config)#interface serial 0/0/1
Usama(config-if)#ip
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/1/1, changed
state to
Usama(config-if)#ip address 52.100.0.2 255.255.255.252
Usama(config-if)#no shutdown
Usama(config-if)#
%LINK-5-CHANGED: Interface Serial0/0/1, changed state to up
Usama(config-if)#exit
Usama(config)#interface se
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/0/0, changed
state to up
Usama(config-if)#ip address 132.100.0.1 255.255.255.252
Usama(config-if)#clock rate 64000
Usama(config-if)#no shutdown
Usama(config-if)#
%LINK-5-CHANGED: Interface Serial0/0/0, changed state to up
Usama(config-if)#exit
Usama(config)#
Ctrl+Z to exit CLI focus
  
```

Time: 00:28:52

Scenario 0

Router PT

Toggle PDU List Window

Type here to search

ENG 9:24 PM 2/11/2021

Cisco Packet Tracer - C:\Users\usama\OneDrive\Desktop\Labtask 9694.pkt

File Edit Options View Tools Extensions Help

Logical Physical x 320 y 709

Usama-Router5

Physical Config CLI Attributes

IOS Command Line Interface

```

Press RETURN to get started!

Router>enable
Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#hostname Usama
Usama(config)#interface serial 0/0/1
Usama(config-if)#ip address 132.100.0.2 255.255.255.252
Usama(config-if)#no shutdown
Usama(config-if)#
%LINK-5-CHANGED: Interface Serial0/0/1, changed state to up
Usama(config-if)#exit
Usama(config)#interface fa 0/0
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/0/1,
changed state to up
Usama(config-if)#ip address 212.100.100.1 255.255.255.248
Usama(config-if)#no shutdown
Usama(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0,
changed state to up
Usama(config-if)#exit
Usama(config)#
Ctrl+Z to exit CLI focus
  
```

Time: 00:32:48

Scenario 0

Fire

Last Status	Source	Destin	Source	Destin	Source	Destin	Source	Destin
Successful	Usama-PC3	Usama-PC3	ICMP	0.000	N	0	(edit)	(delete)
Successful	Usama-PC10	Usama-PC3	ICMP	0.000	N	1	(edit)	(delete)
Successful	Usama-PC10	Usama-PC3	ICMP	0.000	N	2	(edit)	(delete)

Toggle PDU List Window

Type here to search

ENG 9:28 PM 2/11/2021

