

## **LAB TASK FLOATING & SUMMARY**


Name :- Usama Rehman

SID :- 9894

### **NETWORK DIAGRAM**



Logical Physical x 25, y 332



Rectangular Snip

Time: 00:27:13



829


Scenario 0

New

Delete

Toggle PDU List Window

Fire Last Status Source Destination Type Color Time(sec) Period

 Usama-Router1

Physical Config **CLI** Attributes

IOS Command Line Interface

```
Router>enable
Router#conf t
Enter configuration commands, one per line.  End with CNTL/Z.
Router(config)#hostname Usama
Usama(config)#interface serial 0/0/0
Usama(config-if)#ip address 121.100.100.1 255.255.255.252
Usama(config-if)#clock rate 64000
Usama(config-if)#no shutdown

%LINK-5-CHANGED: Interface Serial0/0/0, changed state to down
Usama(config-if)#
Usama(config-if)#exit
Usama(config)#interface serial 0/0/1
Usama(config-if)#ip address 21.100.100.2 255.255.255.252
Usama(config-if)#no shutdown

%LINK-5-CHANGED: Interface Serial0/0/1, changed state to down
Usama(config-if)#exit
Usama(config)#interface fa 0/0
Usama(config-if)#ip address 191.100.100.1 255.255.255.248
Usama(config-if)#no shutdown

Usama(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0,
changed state to up

Usama(config-if)#exit
Usama(config)#sc|
```

Ctrl+F6 to exit CLI focus

Copy Paste

☐ Top



Physical

Config

CLI

Attributes

## IOS Command Line Interface

Press RETURN to get started!

Router>enable

Router#conf t

Enter configuration commands, one per line. End with CNTL/Z.

Router(config)#hostname Usama

Usama(config)#interface serial 0/0/0

Usama(config-if)#ip address 81.100.100.100.1 255.255.255.252

^

% Invalid input detected at '^' marker.

Usama(config-if)#ip address 81.100.100.1 255.255.255.252

Usama(config-if)#clock rate 64000

Usama(config-if)#no shutdown

%LINK-5-CHANGED: Interface Serial0/0/0, changed state to down

Usama(config-if)#

Usama(config-if)#exit

Usama(config)#interface serial 0/0/1

Usama(config-if)#ip address 121.100.100.2 255.255.255.252

Usama(config-if)#no shutdown

Usama(config-if)#

%LINK-5-CHANGED: Interface Serial0/0/1, changed state to up

Usama(config-if)#exit

Usama(config)#

%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/0/1,  
changed state to up

Ctrl+F6 to exit CLI focus

Copy

Paste



Top



Physical

Config

CLI

Attributes

## IOS Command Line Interface

```
Router>enable
Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#hostname Usama
Usama(config)#interface serial 0/0/0
Usama(config-if)#ip address 41.100.100.1 255.255.255.252
Usama(config-if)#clock rate 64000
Usama(config-if)#no shutdown

%LINK-5-CHANGED: Interface Serial0/0/0, changed state to down
Usama(config-if)#exit
Usama(config)#interface serial 0/1/0
Usama(config-if)#ip address 61.100.100.100.2 255.255.255.252
      ^
% Invalid input detected at '^' marker.

Usama(config-if)#ip address 61.100.100.2 255.255.255.252
Usama(config-if)#no shutdown

%LINK-5-CHANGED: Interface Serial0/1/0, changed state to down
Usama(config-if)#exit
Usama(config)#interface serial 0/0/1
Usama(config-if)#ip address 81.100.100.2 255.255.255.252
Usama(config-if)#no shutdown

Usama(config-if)#
%LINK-5-CHANGED: Interface Serial0/0/1, changed state to up

Usama(config-if)#exit
Usama(config)#interfac
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/0/1,
changed stat
Usama(config)#interface serial 0/1/1
Usama(config-if)#ip address 21.100.100.1 255.255.255.252
Usama(config-if)#clock rate 64000
Usama(config-if)#no shutdown

Usama(config-if)#
%LINK-5-CHANGED: Interface Serial0/1/1, changed state to up

Usama(config-if)#exit
Usama(config)#
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/1/1,
changed state to up
```

Ctrl+F6 to exit CLI focus

Copy

Paste

☐ Top





Physical

Config

CLI

Attributes

## IOS Command Line Interface

```
Router>enable
Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#hostname Usama
Usama(config)#interface serial 0/0/0
Usama(config-if)#ip address 61.100.100.1 255.255.255.252
Usama(config-if)#clock rate 64000
Usama(config-if)#no shutdown

Usama(config-if)#
%LINK-5-CHANGED: Interface Serial0/0/0, changed state to up

Usama(config-if)#
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/0/0,
changed state to up

Usama(config-if)#exit
Usama(config)#interface serial 0/0/1
Usama(config-if)#ip address 41.100.100.2 255.255.255.252
Usama(config-if)#no shutdown

Usama(config-if)#
%LINK-5-CHANGED: Interface Serial0/0/1, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/0/1,
changed state to up

Usama(config-if)#exit
Usama(config)#interface fa 0/0
Usama(config-if)#ip address 211.100.100.1 255.255.255.248
Usama(config-if)#no shutdown

Usama(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0,
changed state to up

Usama(config-if)#exit
Usama(config)#
```

Ctrl+F6 to exit CLI focus

Copy

Paste



Top

## Routing

```
Usama(config)#ip route 41.100.100.0 255.255.255.252 21.100.100.1
5
Usama(config)#ip route 81.100.100.0 255.255.255.252 21.100.100.1
10
Usama(config)#ip route 211.100.100.0 255.255.255.248 21.100.100.1
10
Usama(config)#ip route 211.100.100.0 255.255.255.248 21.100.100.1
Usama(config)#exit
Usama#
%SYS-5-CONFIG_I: Configured from console by console
```

Ctrl+F6 to exit CLI focus

Copy

Paste

```
Usama(config)#ip route 191.100.100.0 255.255.255.248
121.100.100.1
Usama(config)#ip route 41.100.100.0 255.255.255.252 81.100.100.2
5
Usama(config)#ip route 61.100.100.0 255.255.255.252 81.100.100.2
10
Usama(config)#ip route 211.100.100.0 255.255.255.248 81.100.100.2
Usama(config)#exit
Usama#
%SYS-5-CONFIG_I: Configured from console by console
```

Ctrl+F6 to exit CLI focus

Copy

Paste

☐ Top

```
Usama(config)#ip route 191.100.100.0 255.255.255.248 21.100.100.2
Usama(config)#ip route 211.100.100.0 255.255.255.248 41.100.100.2
5
Usama(config)#ip route 211.100.100.0 255.255.255.248 41.100.100.2
10
Usama(config)#exit
Usama#
%SYS-5-CONFIG_I: Configured from console by console
```

Ctrl+F6 to exit CLI focus

Copy

Paste

☐ Top

```
Usama(config-if)#exit
Usama(config)#ip route 21.100.100.0 255.255.255.252 41.100.100.1
5
Usama(config)#ip route 21.100.100.0 255.255.255.252 61.100.100.2
10
Usama(config)#ip route 191.100.100.0 255.255.255.248 41.100.100.1
5
Usama(config)#ip route 191.100.100.0 255.255.255.248 61.100.100.2
10
Usama(config)#exit
Usama#
%SYS-5-CONFIG_I: Configured from console by console
```

Ctrl+F6 to exit CLI focus

Copy

Paste

☐ Top

**PC IPS**



UsamaPC3

PhysicalConfigDesktopProgrammingAttributes

IP Configuration X

InterfaceFastEthernet0

IP Configuration

☐ DHCP

☒ Static

IPv4 Address191.100.100.4

Subnet Mask255.255.255.248

Default Gateway191.100.100.1

DNS Server0.0.0.0

IPv6 Configuration

☐ Automatic

☒ Static

IPv6 Address /

Link Local AddressFE80::260:5CFF:FE44:94EC

Default Gateway

DNS Server

802.1X

☐ Use 802.1X Security

AuthenticationMD5

☐ Top

Usama-PC6

Physical
Config
Desktop
Programming
Attributes

IP Configuration

Interface
FastEthernet0

IP Configuration

☐ DHCP
☒ Static

IPv4 Address
211.100.100.4

Subnet Mask
255.255.255.248

Default Gateway
211.100.100.1

DNS Server
0.0.0.0

IPv6 Configuration

☐ Automatic
☒ Static

IPv6 Address
/

Link Local Address
FE80::20B:BEFF:FE23:45C9

Default Gateway

DNS Server

802.1X

☐ Use 802.1X Security

Authentication
MD5

☐ Top

## Message Sent & Received

Fire	Last Status	Source	Destination	Type	Color	Time(sec)	Periodic	Num	Edit	Delete
	Successful	UsamaPC3	Usama-PC6	ICMP		0.000	N	0	(edit)	(delete)
	Successful	Usama-PC2	Usama-PC5	ICMP		0.000	N	1	(edit)	(delete)
	Successful	Usama-PC1	Usama-PC4	ICMP		0.000	N	2	(edit)	(delete)