

For R1:

Router>en

Router#erase startup-config

Router#reload

No

Router>en

Router#conf t

Router(config)#hostname R1

Router(config)#no ip domain-lookup

Router(config)#enable secret class

Router(config)#exit

R1#show run

R1#conf t

R1(config)#banner motd &

!!!AUTHORIZED ACCESS ONLY!!!

&

R1(config)#line console 0

R1(config-line)#password cisco

R1(config-line)#login

R1(config-line)#exit

```
R1(config)#line vty 0 4
R1(config-line)#password cisco
R1(config-line)#login
R1(config-line)#exit
R1(config)#int f0/0
R1(config-if)#ip address 192.168.1.1 255.255.255.0
R1(config-if)#no shutdown
```

```
R1(config-if)#exit
R1(config)#int s0/0/0
R1(config-if)#ip address 192.168.2.1 255.255.255.0
R1(config-if)#no shutdown
```

```
R1(config-if)#clock rate 64000
R1(config-if)#no shutdown
R1(config-if)#exit
R1(config)#exit
```

```
R1#copy run start
```

For R2:

Router>en

Router#erase startup-config

Router#reload

No

Router>en

Router#conf t

Router(config)#hostname R2

R2(config)#no ip domain-lookup

R2(config)#enable secret class

R2(config)#exit

R2#show run

R2#conf t

R2(config)#banner motd &

!!!AUTHORIZED ACCESS ONLY!!!

&

R2(config)#line console 0

R2(config-line)#password cisco

R2(config-line)#login

R2(config-line)#exit

```
R2(config)#line vty 0 4
R2(config-line)#password cisco
R2(config-line)#login
R2(config-line)#exit
R2(config)#int s0/0/0
R2(config-if)#ip address 192.168.2.2 255.255.255.0
R2(config-if)#no shutdown
```

```
R2(config-if)#exit
R2(config)#int f0/0
R2(config-if)#ip address 192.168.3.1 255.255.255.0
R2(config-if)#no shutdown
```

```
R2(config-if)#exit
R2(config)#exit
```

```
R2#copy run start
```