

## Automatic Project Backup

Automatic Project Backup provides you the opportunity to backup your entire unity project to a directory or volume of your choice.

You can do this manually at any time by using the manual backup feature or even automatically by setting a time interval.

Several options help you to keep your backups structured.

From now on, if you have any problem with your original project files just load an easily created backup into Unity and continue your work.

In order to install Automatic Project Backup you have to purchase and download the Automatic Project Backup asset from the Unity Asset Store.

After the download is finished you are free to import the Automatic Project Backup asset into any project you like.

If you finished importing the asset, open the Automatic Project Backup window by choosing "Auto Project Backup" below the Unity menu item "Window".

Now you have access to the Automatic Project Backup controls. If you like to use the automatic backup feature please do not close this window. You can dock the Automatic Project Backup window as a tab or just leave it as a separate open window.

Controls description

### **Manual Backup**

Source:	The path to your original Unity project folder
Destination:	Enter your manual backup destination path or you use the change button to navigate to a certain folder or volume.
Increment:	Use separate options like time, date and numbers to keep your backups structured. Time and date are taken from system time and date and the numbers will increase automatically after every manual backup.
Example:	Preview of the chosen path and increment options
Big button:	Start manual backup

**Auto Backup** Enable or disable the automatic backup controls, if you disable here, a running backup interval will be disabled too.

Destination:	Enter your automatic backup destination path or you use the change button to navigate to a certain folder or volume.
Name Suffix:	Use this to mark your backup folders as Auto Backup Folders.
Number Backup:	Determines how many Auto Backup Folders will be created. For example: You enter 3. Three Auto Backup Folders will be created from folder one to folder three. If backup has written folder three it will continue after the next time interval with overwriting folder one. This prevents Auto Backup from flooding your hard disk with unlimited automatic backups.
Backup Every:	Set the time interval.
Enable/Disable:	Enable or disable the Auto Backup feature.

For further questions, suggestions, reports please feel free to contact [autobackup@monozoo.de](mailto:autobackup@monozoo.de) .