



Router0

Physical Config CLI Attributes

IOS Command Line Interface

```

cisco 2811 (MPC860) processor (revision 0x200) with 60416K/5120K bytes of
memory
Processor board ID JAD05190MTZ (4292891495)
2 FastEthernet interface(s)
DRAM configuration is 64 bits wide with parity disabled.
255K bytes of non-volatile configuration memory.
249856K bytes of ATA System CompactFlash 0 (Read/Write)

--- System Configuration Dialog ---

Would you like to enter the initial configuration dialog? [yes/no]:

Press RETURN to get started!

Router>en
Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#int fa0/0
Router(config-if)#ip ad 192.168.10.1 255.255.255.0
Router(config-if)#no sh

Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed
state to up

Router(config-if)#ex
Router(config)#ip dhcp pool VOICE
Router(dhcp-config)#network 192.168.10.0 255.255.255.0
Router(dhcp-config)#default-router 192.168.10.1
Router(dhcp-config)#option 150 ip 192.168.10.1
Router(dhcp-config)#ex
Router(config)#telephony-service
Router(config-telephony)#max-dn 5
Router(config-telephony)#max-ephones 5
Router(config-telephony)#ip source-address 192.168.10.1 port 2000
Router(config-telephony)#auto assign 1 to 5
Router(config-telephony)#ex
Router(config)#

```

Copy Paste

Switch0

Physical
Config
CLI
Attributes

IOS Command Line Interface

```

Hardware Board Revision Number : 0x01

Switch Ports Model          SW Version  SW Image
-----
*   1 26    WS-C2960-24TT-L    15.0(2)SE4    C2960-LANBASEK9-M

Cisco IOS Software, C2960 Software (C2960-LANBASEK9-M), Version 15.0(2)SE4, RELEASE
SOFTWARE (fc1)
Technical Support: http://www.cisco.com/techsupport
Copyright (c) 1986-2013 by Cisco Systems, Inc.
Compiled Wed 26-Jun-13 02:49 by mnguyen

Press RETURN to get started!

%LINK-5-CHANGED: Interface FastEthernet0/2, changed state to up
%LINK-5-CHANGED: Interface FastEthernet0/3, changed state to up
%LINK-5-CHANGED: Interface FastEthernet0/1, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/1, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/2, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/3, changed state to up

Switch>en
Switch#conf t
Enter configuration commands one per line. End with CNTL/Z

```

Copy
Paste

☐ Top



