

Bug report examples: Desktop application

Summary:

Delete option: Deleting an image from the main window deletes the image from source folder.

Issue type: Bug

Severity: Critical

Component: X

Affects Version: 2.0

Environment: Windows 10 PRO, 64 bits

Description:

Steps to reproduce:

1. Open X application
2. Navigate to File and click on "Folder" option from dropdown menu.
3. Import images as needed
4. Select imported image from the gallery window
5. Right click and select "Delete" from the options
6. Now open the source folder and pay attention.

Actual Result: Deleting images from the application gallery deletes the images from source folder. Kindly refer to the attachment section

Expected result: Deleting imported images from the application gallery should not delete the source image file

Summary:

Language: Application language is not changed to Deutsch when selecting “Deutsch” from Language option

Issue type: Bug

Severity: Major

Component: X

Affects Version: 2.0

Environment: Windows 10 PRO, 64 bits

Description:

Steps to reproduce:

1. Open X application
2. Click on “Options” button
3. From the dropdown menu of “Language”, select “Deutsch”
4. Close the application
5. Re-open the application and pay attention

Actual Result: Language of the application is not changed to German language after selecting “Deutsch” form the dropdown menu. Kindly refer to attachment section

Expected result: Changing the language to “Deutsch” from “Options” menu should change the application language to Deutsch

Summary:

Refresh: "Application has generated an exception that could not be handled" is displayed when holding the F5 button for five seconds

Issue type: Bug

Severity: Minor

Component: X

Affects Version: 2.0

Environment: Windows 10 PRO, 64 bits

Description:

Steps to reproduce:

1. Open X application
2. Click on "Options" button
3. From the dropdown menu of "Language", select "Deutsch"
4. Close the application
5. Re-open the application and pay attention

Actual Result: Language of the application is not changed to German language after selecting "Deutsch" form the dropdown menu

Expected result: Changing the language to "Deutsch" from "Options" menu should change the application language to Deutsch

Bug report examples: Mobile application

Summary: Text cursor is not displayed in Email Address input field of “Enter your information” page when trying to create an account

Issue type: Bug

Severity: Minor

Component: X

Affects Version: 1.0

Environment: Xiaomi Note 5 Pro, Android version 8

Description:

Steps to reproduce:

1. Open the “X” application
2. Click on Get Started
3. Enter your mobile phone number and click on “Continue” button
4. Navigate to the “Email Address” input field and tap on it

Actual Result: No text cursor is displayed in Email Address input field of “Enter your information” page.

Expected result: Text cursor should be present in Email Address input field when trying to tap on it or trying to input data