



# **What's new in Cloud Manager 3.5**

## **Cloud Manager 3.5**

Ben Cammett  
November 01, 2018

This PDF was generated from [https://docs.netapp.com/us-en/occm35/reference\\_new\\_occm.html](https://docs.netapp.com/us-en/occm35/reference_new_occm.html) on February 15, 2021. Always check docs.netapp.com for the latest.

# Table of Contents

- What's new in Cloud Manager 3.5 . . . . . 1
  - Cloud Manager 3.5.3 (2 Sept 2018). . . . . 1
  - Cloud Manager 3.5.2 (1 Aug 2018) . . . . . 1
  - Cloud Manager 3.5.1 (2 July 2018) . . . . . 3
  - Cloud Manager 3.5 (3 June 2018) . . . . . 5

# What's new in Cloud Manager 3.5

OnCommand Cloud Manager typically introduces a new release every month to bring you new features, enhancements, and bug fixes.

## Cloud Manager 3.5.3 (2 Sept 2018)

Cloud Manager 3.5.3 includes a few enhancements.

- [Creation of SVM management LIF for HA systems in multiple AZs](#)
- [Ability to break SMB/CIFS locks](#)

### Creation of SVM management LIF for HA systems in multiple AZs

When deploying Cloud Volumes ONTAP HA systems in multiple Availability Zones, you can now specify the floating IP address for an SVM management network interface (LIF). The SVM management LIF enables you to use SnapCenter or SnapDrive for Windows with the HA system.

#### Floating IPs

Cloud Volumes ONTAP HA uses floating IP addresses for storage failover between nodes when clients access NFS and CIFS data from within the VPC. You must specify IP addresses that are outside of the CIDR blocks for all VPCs in the selected AWS region.

Additional information ⓘ

Floating IP address for cluster management

192.168.10.2

Floating IP address 1 for NFS and CIFS data

192.168.10.3

Floating IP address 2 for NFS and CIFS data

192.168.10.4

Floating IP address for SVM management (Optional)

192.168.10.5

### Ability to break SMB/CIFS locks

In previous releases, upgrading or modifying the instance type and license type for a Cloud Volumes ONTAP HA system could fail if locks were present on SMB/CIFS files. Starting in this release, Cloud Manager can detect and break the locks before it proceeds with the operation. You simply need to confirm when prompted.

## Cloud Manager 3.5.2 (1 Aug 2018)

Cloud Manager 3.5.2 includes new features and enhancements.



Changes in this release require a new Azure permission for Cloud Manager. Read the changes below.

- [Support for WORM storage](#)
- [Support for the auto tiering policy with Cloud Volumes ONTAP Standard](#)
- [Cloud Manager deployment in Azure from NetApp Cloud Central](#)
- [Animation added to used capacity charts](#)
- [Locks on Azure disks](#)
- [Tags on AWS CloudFormation stacks](#)
- [Deprecation of Cloud Volumes ONTAP encryption in AWS](#)

## Support for WORM storage

You can now activate WORM storage on new Cloud Volumes ONTAP systems. Write once, read many (WORM) storage enables you to retain critical files in unmodified form for regulatory and governance purposes and to protect from malware attacks. WORM files are protected at the file level.

[Learn more about WORM storage.](#)

## Support for the auto tiering policy with Cloud Volumes ONTAP Standard

The *auto* volume tiering policy is now supported with the pay-as-you-go Standard license for Cloud Volumes ONTAP. You can select the auto tiering policy when creating, modifying, or replicating a volume. Data tiering enables automated tiering of cold data to low-cost object storage.



Auto is the default policy when creating new volumes for Cloud Volumes ONTAP Standard, Premium, and BYOL.

[Learn more about data tiering.](#)

## Cloud Manager deployment in Azure from NetApp Cloud Central

You can now deploy new Cloud Manager systems in Microsoft Azure directly from [NetApp Cloud Central](#). Cloud Central simplifies the deployment experience and provides a single location to view and manage multiple Cloud Manager systems. Providing your Azure credentials is secure and private because they are entered in an Azure pop-up window.

[Learn more about Cloud Central.](#)

## Animation added to used capacity charts

An animation now shows you the amount of used capacity when you view volumes or aggregates.



## Locks on Azure disks

Cloud Manager can now add locks to the Azure disks that it allocates to Cloud Volumes ONTAP. The locks help to ensure that the disks are not accidentally deleted. This change requires a new permission so Cloud Manager can add, delete, and query the locks:

"Microsoft.Authorization/locks/\*\*"

You should add this permission to the custom role that provides Cloud Manager with the required permissions.

## Tags on AWS CloudFormation stacks

Cloud Manager now adds user tags to the AWS CloudFormation stacks that it creates. The tags can help to ensure that the stacks are not deleted by automated processes.

## Deprecation of Cloud Volumes ONTAP encryption in AWS

Data-at-rest encryption of aggregates using external key managers is no longer supported when launching new Cloud Volumes ONTAP systems in AWS. Existing systems that use this feature are still supported; however, Cloud Volumes ONTAP encryption will be deprecated in the 9.5 release. NetApp will contact you to discuss how to upgrade those systems to the 9.5 release and how to implement a replacement encryption feature.

You can still enable data encryption on new systems by using the AWS Key Management Service (KMS).

## Cloud Manager 3.5.1 (2 July 2018)

Cloud Manager 3.5.1 includes new features and enhancements.

- [Support for pay-as-you-go in the AWS GovCloud \(US\) region](#)
- [Tiering levels for cold data](#)
- [Providing Azure permissions using a Managed Service Identity](#)
- [New used capacity charts](#)

## Support for pay-as-you-go in the AWS GovCloud (US) region

The pay-as-you-go version of Cloud Volumes ONTAP is now supported in the AWS GovCloud (US) region. This is in addition to supporting Cloud Volumes ONTAP BYOL in the GovCloud (US) region.

You can deploy Cloud Volumes ONTAP in the GovCloud (US) region just like any other region. Go to NetApp Cloud Central and launch Cloud Manager in GovCloud (US). Then launch Cloud Volumes ONTAP PAYGO or BYOL by creating a new working environment in Cloud Manager.

## Tiering levels for cold data

After you deploy Cloud Volumes ONTAP, you can change the Amazon S3 storage class or the Azure Blob storage tier in which you want to store cold data. Changing the tiering level can reduce your storage costs, if you do not plan to access the data. The access costs are higher if you do access the data, so you must take that into consideration before you change the tiering level.

The tiering level is system wide—it is not per volume. For details about changing the tiering level, see [Tiering cold data to low-cost object storage](#).

## AWS tiering levels

In AWS, Cloud Volumes ONTAP uses **Standard** as the default storage class for data tiering to Amazon S3. You can change the storage class to either **Standard-Infrequent Access** or **One Zone-Infrequent Access**. When you change the tiering level, cold data starts in the **Standard** storage class and moves to the storage

class that you selected, if the data is not accessed after 30 days. For details about S3 storage classes, refer to [AWS documentation](#).

### S3 Tiering Level

- ☐ **Standard** - For frequently accessed data stored across multiple Availability Zones.
- ☒ **Standard-Infrequent Access** - For infrequently accessed data stored across multiple Availability Zones.
- ☐ **One Zone-Infrequent Access** - For infrequently accessed data stored in a single Availability Zone.

## Azure tiering levels

In Azure, Cloud Volumes ONTAP uses the Azure **hot** storage tier as the default for data tiering to Blob storage. You can change to the Azure **cool** storage tier. When you change the tiering level, cold data starts in the **hot** storage tier and moves to the **cool** storage tier, if the data is not accessed after 30 days. For details about Azure Blob storage tiers, refer to [Azure documentation](#).

### Blob Tiering Level

- ☐ **Hot** - For frequently accessed data.
- ☒ **Cool** - For infrequently accessed data that will reside in the tier for at least 30 days.

## Providing Azure permissions using a Managed Service Identity

You can now provide Azure permissions to Cloud Manager by using a Managed Service Identity. A Managed Service Identity allows a Cloud Manager virtual machine in Azure to identify itself to Azure Active Directory without providing any credentials. This method is simpler than manually setting up an Azure service principal and providing the credentials to Cloud Manager.

To use a Managed Service Identity with Cloud Manager, follow [instructions for new Cloud Manager virtual machines](#) or [instructions for existing Cloud Manager virtual machines](#).




Managed Service Identities are not supported in the Azure US Gov regions and in the Germany regions. You must [grant Azure permissions to Cloud Manager using a service principal and credentials](#).

For more information about Managed Service Identities, refer to [Azure documentation](#).

## New used capacity charts

Cloud Manager now provides a graphical representation of used capacity when viewing volumes and aggregates.



## Cloud Manager 3.5 (3 June 2018)

Cloud Manager 3.5 includes new features and enhancements.

- [Support for Cloud Volumes ONTAP 9.4](#)
- [New permissions required for Cloud Volumes ONTAP 9.4](#)
- [Cloud Manager integration with NetApp Cloud Central](#)
- [Support for the m4.large instance type](#)
- [Marketplace image now based on RHEL 7.4](#)

### Support for Cloud Volumes ONTAP 9.4

You can now deploy new Cloud Volumes ONTAP 9.4 systems from Cloud Manager and upgrade your existing systems to the 9.4 release. Cloud Manager also provides support for [the new features introduced in Cloud Volumes ONTAP 9.4](#).

### New permissions required for Cloud Volumes ONTAP 9.4

Cloud Manager requires new permissions for key features in the Cloud Volumes ONTAP 9.4 release. To ensure that your Cloud Manager systems can deploy and manage Cloud Volumes ONTAP 9.4 systems, you must update your Cloud Manager policy by adding the following permissions:

- For AWS: "ec2:DescribeInstanceAttribute",

Cloud Manager uses this permission to verify that enhanced networking is enabled for supported instance types.

- For Azure: "Microsoft.Network/virtualNetworks/subnets/write",

Cloud Manager uses this permission to enable VNet service endpoints for data tiering.

You can find the entire list of required permissions in [the latest policies provided by NetApp](#).

## Cloud Manager integration with NetApp Cloud Central

When upgrading to Cloud Manager 3.5, NetApp will choose specific Cloud Manager systems to integrate with NetApp Cloud Central, if they are not already integrated. During this process, NetApp migrates all local user accounts in your Cloud Manager system to the centralized user authentication available in Cloud Central. After the upgrade is complete, you simply need to log in.

If you have questions, refer to [this FAQ](#).

## Support for the m4.large instance type

Cloud Manager is now supported with the m4.large EC2 instance type. m3.large is no longer supported.

For a list of supported Cloud Manager configurations, see [Cloud Manager host requirements](#).

## Marketplace image now based on RHEL 7.4

The operating system for the Cloud Manager marketplace image in AWS and Azure is now Red Hat Enterprise Linux 7.4.



## Copyright Information

Copyright © 2021 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system-without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP "AS IS" AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

## Trademark Information

NETAPP, the NETAPP logo, and the marks listed at <http://www.netapp.com/TM> are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.