

MOUNT.FUSE.CEPH – MOUNT CEPH-FUSE FROM /ETC/FSTAB.

SYNOPSIS

**mount.fuse.ceph** [-h] [-o OPTIONS [OPTIONS ...]] device [device ...] mountpoint [mountpoint ...]

DESCRIPTION

**mount.fuse.ceph** is a helper for mounting ceph-fuse from /etc/fstab.

To use mount.fuse.ceph, add an entry in /etc/fstab like:

DEVICE	PATH	TYPE	OPTIONS
none	/mnt/ceph	fuse.ceph	ceph.id=admin,_netdev,defaults 0 0
none	/mnt/ceph	fuse.ceph	ceph.name=client.admin,_netdev,defaults 0 0
none	/mnt/ceph	fuse.ceph	ceph.id=myuser,ceph.conf=/etc/ceph/foo.conf,_netdev,default

ceph-fuse options are specified in the OPTIONS column and must begin with ‘ceph.’ prefix. This way ceph related fs options will be passed to ceph-fuse and others will be ignored by ceph-fuse.

OPTIONS

**ceph.id=<username>**  
Specify that the ceph-fuse will authenticate as the given user.

**ceph.name=client.admin**  
Specify that the ceph-fuse will authenticate as client.admin

**ceph.conf=/etc/ceph/foo.conf**  
Sets ‘conf’ option to /etc/ceph/foo.conf via ceph-fuse command line.

Any valid ceph-fuse options can be passed this way.

ADDITIONAL INFO

The old format /etc/fstab entries are also supported:

DEVICE	PATH	TYPE	OPTIONS
id=admin	/mnt/ceph	fuse.ceph	defaults 0 0
id=myuser,conf=/etc/ceph/foo.conf	/mnt/ceph	fuse.ceph	defaults 0 0

AVAILABILITY

**mount.fuse.ceph** is part of Ceph, a massively scalable, open-source, distributed storage system. Please refer to the Ceph documentation at <http://ceph.com/docs> for more information.

SEE ALSO

[ceph-fuse\(8\)](#), [ceph\(8\)](#)