

Lab Report

---

## Your Performance

Your Score: 2 of 4 (50%)

Elapsed Time: 2 minutes 23 seconds

Pass Status: Not Passed

Required Score: 100%

## Task Summary

- ✓ Install the DHCP role
- ✓ Authorize CorpDHCP as a DHCP server
- ✗ Configure the DHCP scope [Hide Details](#)

- ✗ Scope name: Subnet1
  - ✗ Starting IP Address: 192.168.0.1
  - ✗ Ending IP Address: 192.168.0.254
  - ✗ Subnet mask: 255.255.255.0
  - ✗ Lease duration: 5 days

- ✗ Activate the DHCP scope

## Explanation

In this lab, you perform the following:

- Install the DHCP role.
- Authorize CorpDHCP as a DHCP server.
- Configure the DHCP scope as follows:
  - Name: **Subnet1**
  - Address range: **192.168.0.1** to **192.168.0.254**
  - Subnet mask: **255.255.255.0**
  - Length: **24**
  - Lease duration: **5 days**
- Activate the DHCP scope.

Complete this task as follows:

1. Install a DHCP role as follows:
  - a. From Hyper-V Manager, select **CORPSERVER**.
  - b. Maximize the window to view all virtual machines.
  - c. Right-click **CorpDCHP** and select **Connect**.
  - d. From Server Manager, select **Manage > Add Roles and Features**.
  - e. In the Add Roles and Features Wizard, click **Next**.
  - f. Make sure **Role-based or feature-based installation** is selected; then click **Next**.
  - g. Make sure **CorpDHCP.CorpNet.com** is selected in the Server Pool area; then click **Next**.
  - h. Select the **DHCP Server** role.
  - i. Select **Add Features**.
  - j. Click **Next**.
  - k. Click **Next** because no additional features are required for the DHCP Server.
    1. In the DHCP Server window, click **Next**.
  - m. Select **Install** to add the selected role.
2. Authorize CorpDHCP as a DHCP server as follows:
  1. In the center area, select **Complete DHCP configuration** to begin the DHCP Post-Install configuration wizard.
  2. In the DHCP Post-Install configuration wizard, click **Next**.
  3. Verify the **credentials**; then select **Commit**.

4. Click **Close** to close the DHCP Post-Install configuration wizard.
  5. Click **Close** to close the Add Roles and Features wizard.
3. Configure and activate a DHCP Scope as follows:
- a. From Server Manager, select **Tools > DHCP**.
  - b. Expand **CorpDHCP.CorpNet.com**.
  - c. Right-click **IPv4** and select **New Scope**.
  - d. In the New Scope wizard, click **Next**.
  - e. In the Name field, enter the *name* of the *scope*; then click **Next**.
  - f. Enter the *start IP address*.
  - g. Enter the *end IP address*.
  - h. Make sure the subnet is **255.255.255.0**.
  - i. Make sure the length is **24**; then click **Next**.
  - j. Click **Next** to ignore any exclusions and delays.
  - k. Enter **5** days as the lease duration; then click **Next**.
  - l. Select **No, I will configure these options later** to postpone configuring other DHCP options; then click **Next**.
  - m. Click **Finish** to close the wizard and create the scope.
4. Activate the DHCP scope as follows:
1. Expand **IPv4**.
  2. Right-click **Scope [192.168.0.1] Subnet1** and select **Activate**.