

Terminal

```
5 minute output rate 0 bits/sec, 0 packets/sec
 0 packets input, 0 bytes, 0 no buffer
Received 0 broadcasts, 0 runts, 0 giants, 0 throttles
0 input errors, 0 CRC, 0 frame, 0 overrun, 0 ignored, 0 abort
0 packets output, 0 bytes, 0 underruns
0 output errors, 0 collisions, 0 interface resets
0 output buffer failures, 0 output buffers swapped out
0 carrier transitions
DCD=up DSR=up DTR=up RTS=up CTS=up
Vlan1 is administratively down, line protocol is down
Hardware is CPU Interface, address is 0060.3eac.3cd2 (bia 0060.3eac.3cd2)
MTU 1500 bytes, BW 100000 Kbit, DLY 1000000 usec,
  reliability 255/255, txload 1/255, rxload 1/255
Encapsulation ARPA, loopback not set
ARP type: ARPA, ARP Timeout 04:00:00
Last input 21:40:21, output never, output hang never
Last clearing of "show interface" counters never
Input queue: 0/75/0/0 (size/max/drops/flushes); Total output drops: 0
Queueing strategy: fifo
Output queue: 0/40 (size/max)
5 minute input rate 0 bits/sec, 0 packets/sec
5 minute output rate 0 bits/sec, 0 packets/sec
 1682 packets input, 530955 bytes, 0 no buffer
Received 0 broadcasts (0 IP multicast)
 0 runts, 0 giants, 0 throttles
 0 input errors, 0 CRC, 0 frame, 0 overrun, 0 ignored
563859 packets output, 0 bytes, 0 underruns
 0 output errors, 23 interface resets
 0 output buffer failures, 0 output buffers swapped out

ISPRouter#show interface br
ISPRouter#show interface brief
```

```
%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/2, changed
state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/1, changed
state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/0, changed
state to up

%LINK-5-CHANGED: Interface Serial0/0/1, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/0/1, changed state to
up
Warning: Unauthorized Access is Prohibited!

User Access Verification

Password:

R1>enable
Password:
R1#conf t
Enter configuration commands, one per line.  End with CNTL/Z.
R1(config)#interface g0/1
R1(config-if)#ip address 172.16.1.126 255.255.255.192
R1(config-if)#ipv6 address 2001:db8:cafe:1::1/64
R1(config-if)#ipv6 address fe80::1
% Incomplete command.
R1(config-if)#ipv6 address fe80::1 link-local
R1(config-if)#
```

Terminal



Warning: Unauthorized Access is Prohibited!

User Access Verification

Password:

R1>enable

Password:

R1#conf t

Enter configuration commands, one per line. End with CNTL/Z.

R1(config)#interface g0/1

R1(config-if)#ip address 172.16.1.126 255.255.255.192

R1(config-if)#ipv6 address 2001:db8:cafe:1::1/64

R1(config-if)#ipv6 address fe80::1

% Incomplete command.

R1(config-if)#ipv6 address fe80::1 link-local

R1(config-if)#line console 0

R1(config-line)#tr

R1(config-line)#transport in

R1(config-line)#transport input s

R1(config-line)#transport input ssh

% Invalid input detected at '^' marker.

R1(config-line)#line vty 0 4

R1(config-line)#tr

R1(config-line)#transport i

R1(config-line)#transport input s

R1(config-line)#transport input ssh

R1(config-line)#exit

R1(config)#username Admin1 secret Admin1pa55

R1(config)#