


# CLAUDE\_LIKE\_NOPAIN EA v4.00 - KOMPLETNÝ VYVOJOVÝ DIAGRAM

Všetky funkcie a ich prepojenia | AUDCAD Grid Trading System



# DETAILNY POPIS PARAMETROV A LOGIKY

## VSTUPNE PARAMETRE

### GRID

InpAutoLot = true	Auto vypocet lotu
InpRiskPercent = 2.0	Risk na grid seriu
InpLotMultiplier = 1.3	Nasobitel lotov
InpGridStepPips = 25	Rozostup pozicii
InpMaxGridLevels = 7	Max pocet urovni
InpTotalTPPercent = 0.8	Cielovy profit %

### RISK

InpMaxDrawdownPct = 15	Max DD pre zatvorenie
InpMagicNumber = 2262642	ID nasich obchodov

### SIGNAL

InpRSIPeriod = 14	RSI perioda
InpRSIOverbought = 65	SELL zona
InpRSIOversold = 35	BUY zona
InpTimeframe = H1	Casovy ram

### CAS

InpStartHour = 0	Od hodiny
InpEndHour = 23	Do hodiny
InpTradeFriday = true	Piatok povoleny

## AKO TO FUNGUJE

### 1. SIGNAL

- RSI(14) na H1 timeframe
- RSI < 35 = BUY (prepredane)
- RSI > 65 = SELL (prekupene)
- Signal len ked nemame pozicie

### 2. GRID OTVORENIE

- Prvy obchod = Level 0
- Lot vypocitany podľa balance
- TP = +20 pips na kazdu poziciu
- SL = ziadny (grid recovery)

### 3. GRID ROZSIRENIE

- Cena ide proti nam o 25 pips
- Otvorime dalsiu poziciu
- Lot = predosly x 1.3
- Max 7 urovni (ochrana)

### 4. ZATVORENIE

- Celkovy profit >= 0.8% balance
- ALEBO drawdown >= 15%
- Zatvori VSETKY pozicie naraz
- Caka na novy RSI signal

## PRIKLAD GRID PRIEBEHU

