


This documents consists of 2 parts


- How to Install AspenOne
- How to Change the License server

1 How to Install AspenOne


Use Internet Explorer and go to the [software page of Aspen](#) on the intranet. Click (it is April 2019) 'Install Aspen 10'.



Click Run (and be patient)




Click Yes




Select “aspenOne Engineering”


Then Click on “Begin Install”



Click Run




Click on “Install Aspen One products “




Check “I accept the terms of this agreement” and click Next.

Make sure that all the prerequisite components are installed prior to installing Aspen.




If the above message appears (depending on your Windows version), exit the Aspen installer and install Microsoft .NET. Choose one of the following below:
[Click here](#) to install Microsoft .NET Framework version 4.6.2


A summary will inform you if any prerequisites are not met.




Choose the products to install and click Next




Verify your installation and click “Install now”



Be patient




Click Finish




Reboot your computer to finalize the installation, by **clicking** “Reboot Now”.

2 How to Change the License server


Use Internet Explorer and go to the [software page of Aspen](#) on the intranet. Click (it is April 2019) 'Install Aspen 10'.



Click Run (and be patient)




Click Yes




Select “aspenOne Engineering””


Then Click on “Begin Install”



Click ‘Upgrade or repair existing products.



Choose to accept the terms of the agreement and click Next.



Select the current server st-license, and then click Remove server.

aspenONE Installer

Specify licensing & security

Welcome

Software terms

Prerequisites

► **Licensing & security**

Product configuration

Summary

Progress

Please provide the licensing and Security server information below.

Licensing

AspenTech controls the use of aspenONE Products through the Software License Manager (SLM). This step allows you to set up the SLM information on this machine. SLM allows two types of licensing: Network and Standalone. Network licensing obtains the aspenONE Product licenses across a network connection from a network-license-server computer. Standalone licensing obtains licenses from the same computer on which the aspenONE Products are installed. For more information, please see the SLM Installation and Reference guide.

For network configurations, please provide a list of license servers for AspenTech products. Install will keep the server names and bucket numbers already configured on this machine. Additional buckets can be added through the SLM Configuration Wizard.

License server: ...

For a standalone license file that is local on this computer, browse to the location.

License file:

< Back Next > Cancel

Enter the name of the new license server in the field License server, and click Add Server.

aspenONE Installer

Specify licensing & security

Welcome

Software terms

Prerequisites

► **Licensing & security**

Product configuration

Summary

Progress

Please provide the licensing and Security server information below.

Licensing

AspenTech controls the use of aspenONE Products through the Software License Manager (SLM). This step allows you to set up the SLM information on this machine. SLM allows two types of licensing: Network and Standalone. Network licensing obtains the aspenONE Product licenses across a network connection from a network-license-server computer. Standalone licensing obtains licenses from the same computer on which the aspenONE Products are installed. For more information, please see the SLM Installation and Reference guide.

For network configurations, please provide a list of license servers for AspenTech products. Install will keep the server names and bucket numbers already configured on this machine. Additional buckets can be added through the SLM Configuration Wizard.


License server: ...

For a standalone license file that is local on this computer, browse to the location.


License file:


< Back Next > Cancel

Click Next




Click Install Now to start the installation of the 'repaired products' and the new license configuration. Be patient, even when only the license server changed a full installation process is being performed.





Click Finish



Reboot your computer to finalize the installation, by **clicking** “Reboot Now”.