

How To Check And Delete Your Windows 10 Activity History?

December 18, 2017



As you use Windows 10, you do Bing searches, control Cortana with your voice, browse the web using Microsoft Edge. All that information is collected by Microsoft to make the personalized for the users, they say. It's just like what [Google does for Google account users](#).

You can view some information collected by Windows 10 in the form of activity history. And thankfully, Redmond hasn't made it tedious and almost impossible to clear activity related to Windows 10.

Why I'm telling you about Windows 10 Activity History?


Other than keeping track of how you use your computer, the Windows 10 Activity history can be helpful in different ways. For instance, if you give your computer to your kids, you can know if they aren't breaking any of your rules.

Also, if you manage to lose your device someday, location updates in the activity history can be helpful. The location details displayed on the activity history page might not be accurate, still, it provides a rough idea of where your stolen device could be present.


How to view and delete your Windows 10 activity history?

You can delete your Windows 10 Activity history anywhere, anytime just by logging in to your Microsoft account. Follow the steps mentioned below:


1. On your computer, Go to Settings > Privacy. On the **General** screen, click **Manage my info that's stored in the cloud**. This will open a browser tab.



Alternatively, if you're on some other device, you can visit **accounts.microsoft.com** and log in using your Microsoft account credentials. Next, click the link called **Privacy**.



2. On the **Privacy Dashboard** web page, click **Activity history**.




3. The Activity history page separates the collected data with different filters including:
 - Voice – Your Cortana voice commands (and voice commands from apps that use Windows speech service)
 - Search – The searches you’ve made using Bing.
 - Browse – Your Microsoft Edge browsing history.
 - Locations – Your location history if the Location feature in Windows 10 is turned on.
4. Now, you can delete the items you want.

Please note that it isn’t possible to delete all Windows 10 Activity history at once. You need to choose a filter and then click “Clear activity” to remove all the items listed using that filter.


You can prevent your items from populating on your Windows 10 activity history page by disabling the respective features on your computer.

For your Voice history, you can visit **Settings > Privacy > Speech, inking, & typing**. There, enable the toggle button that says **Turn off speech services and typing suggestions**.





To disable location history, on your Windows 10 PC, open the Action Center and click the Location quick action button (Read this post for [more tips about using Action Center](#)).



The Privacy Dashboard also allows you to do other things such as viewing Cortana's notebook and edit your advertisement settings.

Also Read: [What Is Power Throttling In Windows 10? How To Enable It And Improve Battery Life?](#)



Aditya Tiwari

When he is not writing for Fossbytes, he is busy eating his daily cheat meal and finding content to binge watch.

Please feel free to suggest him some good stuff on Netflix. Reach out at aditya.tiwari@fossbytes.com

