

This file aims at presenting the 152 permissions of Android platform allowed for any kind of application developed for that operational system. Such permissions are often used by app developers to access Android resources and device actions. The information of each permission is displayed as follows:

PERMISSION\_NUMBER;PERMISSION\_NAME;PERMISSION\_DESCRIPTION

PERMISSION_NUMBER	PERMISSION_NAME	PERMISSION_DESCRIPTION
1	ACCESS_CHECKIN_PROPERTIES	Allows read/write access to the "properties" table in the checkin database, to change values that get uploaded.
2	ACCESS_COARSE_LOCATION	Allows an app to access approximate location derived from network location sources such as cell towers and Wi-Fi.
3	ACCESS_FINE_LOCATION	Allows an app to access precise location from location sources such as GPS, cell towers, and Wi-Fi.
4	ACCESS_LOCATION_EXTRA_COMMANDS	Allows an application to access extra location provider commands
5	ACCESS_mock_LOCATION	Allows an application to create mock location providers for testing
6	ACCESS_NETWORK_STATE	Allows applications to access information about networks
7	ACCESS_SURFACE_FLINGER	Allows an application to use SurfaceFlinger's low level features.
8	ACCESS_WIFI_STATE	Allows applications to access information about Wi-Fi networks
9	ACCOUNT_MANAGER	Allows applications to call into AccountAuthenticators.
10	ADD_VOICEMAIL	Allows an application to add voicemails into the system.
11	AUTHENTICATE_ACCOUNTS	Allows an application to act as an AccountAuthenticator for the AccountManager
12	BATTERY_STATS	Allows an application to collect battery statistics
13	BIND_ACCESSIBILITY_SERVICE	Must be required by an AccessibilityService, to ensure that only the system can bind to it.
14	BIND_APPWIDGET	Allows an application to tell the AppWidget service which application can access AppWidget's data.
15	BIND_CARRIER_MESSAGING_SERVICE	Must be required by a CarrierMessagingService.
16	BIND_DEVICE_ADMIN	Must be required by device administration receiver, to ensure that only the system can interact with it.
17	BIND_DREAM_SERVICE	Must be required by an DreamService, to ensure that only the system can bind to it.
18	BIND_INPUT_METHOD	Must be required by an InputMethodService, to ensure that only the system can bind to it.
19	BIND_NFC_SERVICE	Must be required by a HostApuService or OffHostApuService to ensure that only the system can bind to it.
20	BIND_NOTIFICATION_LISTENER_SERVICE	Must be required by an NotificationListenerService, to ensure that only the system can bind to it.
21	BIND_PRINT_SERVICE	Must be required by a PrintService, to ensure that only the system can bind to it.
22	BIND_REMOTEVIEWS	Must be required by a RemoteViewsService, to ensure that only the system can bind to it.
23	BIND_TEXT_SERVICE	Must be required by a TextService (e.g.
24	BIND_TV_INPUT	Must be required by a TvInputService to ensure that only the system can bind to it.
25	BIND_VOICE_INTERACTION	Must be required by a VoiceInteractionService, to ensure that only the system can bind to it.
26	BIND_VPN_SERVICE	Must be required by a VpnService, to ensure that only the system can bind to it.
27	BIND_WALLPAPER	Must be required by a WallpaperService, to ensure that only the system can bind to it.
28	BLUETOOTH	Allows applications to connect to paired bluetooth devices
29	BLUETOOTH_ADMIN	Allows applications to discover and pair bluetooth devices
30	BLUETOOTH_PRIVILEGED	Allows applications to pair bluetooth devices without user interaction, and to allow or disallow phonebook access or message access.
31	BODY_SENSORS	Allows an application to access data from sensors that the user uses to measure what is happening inside his/her body, such as heart rate.
32	BRICK	Required to be able to disable the device (very dangerous!).
33	BROADCAST_PACKAGE_REMOVED	Allows an application to broadcast a notification that an application package has been removed.
34	BROADCAST_SMS	Allows an application to broadcast an SMS receipt notification.
35	BROADCAST_STICKY	Allows an application to broadcast sticky intents.
36	BROADCAST_WAP_PUSH	Allows an application to broadcast a WAP PUSH receipt notification.
37	CALL_PHONE	Allows an application to initiate a phone call without going through the Dialer user interface for the user to confirm the call being placed.
38	CALL_PRIVILEGED	Allows an application to call any phone number, including emergency numbers, without going through the Dialer user interface for the user to confirm the call being placed.
39	CAMERA	Required to be able to access the camera device.
40	CAPTURE_AUDIO_OUTPUT	Allows an application to capture audio output.
41	CAPTURE_SECURE_VIDEO_OUTPUT	Allows an application to capture secure video output.
42	CAPTURE_VIDEO_OUTPUT	Allows an application to capture video output.
43	CHANGE_COMPONENT_ENABLED_STATE	Allows an application to change whether an application component (other than its own) is enabled or not.
44	CHANGE_CONFIGURATION	Allows an application to modify the current configuration, such as locale.
45	CHANGE_NETWORK_STATE	Allows applications to change network connectivity state
46	CHANGE_WIFI_MULTICAST_STATE	Allows applications to enter Wi-Fi Multicast mode
47	CHANGE_WIFI_STATE	Allows applications to change Wi-Fi connectivity state
48	CLEAR_APP_CACHE	Allows an application to clear the caches of all installed applications on the device.
49	CLEAR_APP_USER_DATA	Allows an application to clear user data.
50	CONTROL_LOCATION_UPDATES	Allows enabling/disabling location update notifications from the radio.
51	DELETE_CACHE_FILES	Allows an application to delete cache files.
52	DELETE_PACKAGES	Allows an application to delete packages.
53	DEVICE_POWER	Allows low-level access to power management.
54	DIAGNOSTIC	Allows applications to RW to diagnostic resources.
55	DISABLE_KEYGUARD	Allows applications to disable the keyguard
56	DUMP	Allows an application to retrieve state dump information from system services.
57	EXPAND_STATUS_BAR	Allows an application to expand or collapse the status bar.
58	FACTORY_TEST	Run as a manufacturer test application, running as the root user.
59	FLASHLIGHT	Allows access to the flashlight
60	FORCE_BACK	Allows an application to force a BACK operation on whatever is the top activity.
61	GET_ACCOUNTS	Allows access to the list of accounts in the Accounts Service
62	GET_PACKAGE_SIZE	Allows an application to find out the space used by any package.
63	GET_TASKS	This constant was deprecated in API level 21. No longer enforced.
64	GET_TOP_ACTIVITY_INFO	Allows an application to retrieve private information about the current top activity, such as any assist context it can provide.
65	GLOBAL_SEARCH	This permission can be used on content providers to allow the global search system to access their data.
66	HARDWARE_TEST	Allows access to hardware peripherals.
67	INJECT_EVENTS	Allows an application to inject user events (keys, touch, trackball) into the event stream and deliver them to ANY window.
68	INSTALL_LOCATION_PROVIDER	Allows an application to install a location provider into the Location Manager.
69	INSTALL_PACKAGES	Allows an application to install packages.
70	INSTALL_SHORTCUT	Allows an application to install a shortcut in Launcher

71	INTERNAL_SYSTEM_WINDOW	Allows an application to open windows that are for use by parts of the system user interface.
72	INTERNET	Allows applications to open network sockets.
73	KILL_BACKGROUND_PROCESSES	Allows an application to call killBackgroundProcesses(String).
74	LOCATION_HARDWARE	Allows an application to use location features in hardware, such as the geofencing api.
75	MANAGE_ACCOUNTS	Allows an application to manage the list of accounts in the AccountManager
76	MANAGE_APP_TOKENS	Allows an application to manage (create, destroy, Z-order) application tokens in the window manager.
77	MANAGE_DOCUMENTS	Allows an application to manage access to documents, usually as part of a document picker.
78	MASTER_CLEAR	Not for use by third-party applications.
79	MEDIA_CONTENT_CONTROL	Allows an application to know what content is playing and control its playback.
80	MODIFY_AUDIO_SETTINGS	Allows an application to modify global audio settings
81	MODIFY_PHONE_STATE	Allows modification of the telephony state - power on, mmi, etc.
82	MOUNT_FORMAT_FILESYSTEMS	Allows formatting file systems for removable storage.
83	MOUNT_UNMOUNT_FILESYSTEMS	Allows mounting and unmounting file systems for removable storage.
84	NFC	Allows applications to perform I/O operations over NFC
85	PERSISTENT_ACTIVITY	This constant was deprecated in API level 9. This functionality will be removed in the future; please do not use. Allow an application to make its activities persistent.
86	PROCESS_OUTGOING_CALLS	Allows an application to see the number being dialed during an outgoing call with the option to redirect the call to a different number or abort the call altogether.
87	READ_CALENDAR	Allows an application to read the user's calendar data.
88	READ_CALL_LOG	Allows an application to read the user's call log.
89	READ_CONTACTS	Allows an application to read the user's contacts data.
90	READ_EXTERNAL_STORAGE	Allows an application to read from external storage.
91	READ_FRAME_BUFFER	Allows an application to take screen shots and more generally get access to the frame buffer data.
92	READ_HISTORY_BOOKMARKS	Allows an application to read (but not write) the user's browsing history and bookmarks.
93	READ_INPUT_STATE	This constant was deprecated in API level 16. The API that used this permission has been removed.
94	READ_LOGS	Allows an application to read the low-level system log files.
95	READ_PHONE_STATE	Allows read only access to phone state.
96	READ_PROFILE	Allows an application to read the user's personal profile data.
97	READ_SMS	Allows an application to read SMS messages.
98	READ_SOCIAL_STREAM	This constant was deprecated in API level 21. This functionality will be unsupported in the future; cursors returned will be empty. Please do not use.
99	READ_SYNC_SETTINGS	Allows applications to read the sync settings
100	READ_SYNC_STATS	Allows applications to read the sync stats
101	READ_USER_DICTIONARY	Allows an application to read the user dictionary.
102	READ_VOICEMAIL	Allows an application to read voicemails in the system.
103	REBOOT	Required to be able to reboot the device.
104	RECEIVE_BOOT_COMPLETED	Allows an application to receive the ACTION_BOOT_COMPLETED that is broadcast after the system finishes booting.
105	RECEIVE_MMS	Allows an application to monitor incoming MMS messages, to record or perform processing on them.
106	RECEIVE_SMS	Allows an application to monitor incoming SMS messages, to record or perform processing on them.
107	RECEIVE_WAP_PUSH	Allows an application to monitor incoming WAP push messages.
108	RECORD_AUDIO	Allows an application to record audio
109	REORDER_TASKS	Allows an application to change the Z-order of tasks
110	RESTART_PACKAGES	This constant was deprecated in API level 8. The restartPackage(String) API is no longer supported.
111	SEND_RESPOND_VIA_MESSAGE	Allows an application (Phone) to send a request to other applications to handle the respond-via-message action during incoming calls.
112	SEND_SMS	Allows an application to send SMS messages.
113	SET_ACTIVITY_WATCHER	Allows an application to watch and control how activities are started globally in the system.
114	SET_ALARM	Allows an application to broadcast an Intent to set an alarm for the user.
115	SET_ALWAYS_FINISH	Allows an application to control whether activities are immediately finished when put in the background.
116	SET_ANIMATION_SCALE	Modify the global animation scaling factor.
117	SET_DEBUG_APP	Configure an application for debugging.
118	SET_ORIENTATION	Allows low-level access to setting the orientation (actually rotation) of the screen.
119	SET_POINTER_SPEED	Allows low-level access to setting the pointer speed.
120	SET_PREFERRED_APPLICATIONS	This constant was deprecated in API level 7. No longer useful, see addPackageToPreferred(String) for details.
121	SET_PROCESS_LIMIT	Allows an application to set the maximum number of (not needed) application processes that can be running.
122	SET_TIME	Allows applications to set the system time.
123	SET_TIME_ZONE	Allows applications to set the system time zone
124	SET_WALLPAPER	Allows applications to set the wallpaper
125	SET_WALLPAPER_HINTS	Allows applications to set the wallpaper hints
126	SIGNAL_PERSISTENT_PROCESSES	Allow an application to request that a signal be sent to all persistent processes.
127	STATUS_BAR	Allows an application to open, close, or disable the status bar and its icons.
128	SUBSCRIBED_FEEDS_READ	Allows an application to allow access the subscribed feeds ContentProvider.
129	SUBSCRIBED_FEEDS_WRITE	
130	SYSTEM_ALERT_WINDOW	Allows an application to open windows using the type TYPE_SYSTEM_ALERT, shown on top of all other applications.
131	TRANSMIT_IR	Allows using the device's IR transmitter, if available
132	UNINSTALL_SHORTCUT	Allows an application to uninstall a shortcut in Launcher
133	UPDATE_DEVICE_STATS	Allows an application to update device statistics.
134	USE_CREDENTIALS	Allows an application to request authtokens from the AccountManager
135	USE_SIP	Allows an application to use SIP service
136	VIBRATE	Allows access to the vibrator
137	WAKE_LOCK	Allows using PowerManager WakeLocks to keep processor from sleeping or screen from dimming
138	WRITE_APN_SETTINGS	Allows applications to write the apn settings.
139	WRITE_CALENDAR	Allows an application to write (but not read) the user's calendar data.
140	WRITE_CALL_LOG	Allows an application to write (but not read) the user's contacts data.
141	WRITE_CONTACTS	Allows an application to write (but not read) the user's contacts data.
142	WRITE_EXTERNAL_STORAGE	Allows an application to write to external storage.
143	WRITE_GSERVICES	Allows an application to modify the Google service map.
144	WRITE_HISTORY_BOOKMARKS	Allows an application to write (but not read) the user's browsing history and bookmarks.
145	WRITE_PROFILE	Allows an application to write (but not read) the user's personal profile data.
146	WRITE_SECURE_SETTINGS	Allows an application to read or write the secure system settings.
147	WRITE_SETTINGS	Allows an application to read or write the system settings.
148	WRITE_SMS	Allows an application to write SMS messages.

149	WRITE_SOCIAL_STREAM	This constant was deprecated in API level 21. This functionality will be unsupported in the future; cursors returned will be empty. Please do not use.
150	WRITE_SYNC_SETTINGS	Allows applications to write the sync settings
151	WRITE_USER_DICTIONARY	Allows an application to write to the user dictionary.
152	WRITE_VOICEMAIL	Allows an application to modify and remove existing voicemails in the system