


Практика 22

Создал конструкцию добавил IP и шлюзы для ПК и роутеров



```
Router0
Physical Config CLI Attributes
IOS Command Line Interface


191K bytes of NVRAM.
63488K bytes of ATA CompactFlash (Read/Write)
Cisco IOS Software, 1841 Software (C1841-ADVIPSERVICESK9-M), Version 12.4(15)T1, RELEASE SOFTWARE
(fc2)
Technical Support: http://www.cisco.com/techsupport
Copyright (c) 1986-2007 by Cisco Systems, Inc.
Compiled Wed 18-Jul-07 04:52 by pt_team

--- System Configuration Dialog ---

Would you like to enter the initial configuration dialog? [yes/no]:

Press RETURN to get started!

Router>enable
Router#
Router#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#interface FastEthernet0/0
Router(config-if)#
Router(config-if)#exit
Router(config)#interface FastEthernet0/1
Router(config-if)#ip address 100.10.10.1 255.0.0.0
Router(config-if)#ip address 100.10.10.1 255.0.0.0
Router(config-if)#exit
Router(config)#ip route 0.0.0.0 0.0.0.0 100.10.10.2
Router(config)#int fa0/0
Router(config-if)#ip nat inside
Router(config-if)#int fa0/1
Router(config-if)#ip nat outside
Router(config-if)#exit
Router(config)#ip nat inside source static 192.168.0.1 100.10.11.1
Router(config)#ip nat inside source static 192.168.0.1 100.10.11.2
Router(config)#
```



Router0

PhysicalConfigCLIAttributes

IOS Command Line Interface

```
Router#
Router#
Router#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#interface FastEthernet0/0
Router(config-if)#no shutdown
Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up

Router(config-if)#exit
Router(config)#interface FastEthernet0/1
Router(config-if)#no shutdown
Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/1, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/1, changed state to up

Router(config-if)#exit
Router(config)#show ip nat translations
^
% Invalid input detected at '^' marker.

Router(config)#exit
Router#
%SYS-5-CONFIG_I: Configured from console by console

Router#show ip nat translations,
^
% Invalid input detected at '^' marker.

Router#show ip nat translations
Pro  Inside global    Inside local    Outside local    Outside global
icmp 100.10.11.2:10     192.168.0.1:10  100.10.10.2:10   100.10.10.2:10
icmp 100.10.11.2:11     192.168.0.1:11  100.10.10.2:11   100.10.10.2:11
icmp 100.10.11.2:12     192.168.0.1:12  100.10.10.2:12   100.10.10.2:12
--- 100.10.11.1        192.168.0.1     ---              ---
--- 100.10.11.2        192.168.0.1     ---              ---

Router#
```

CopyPaste

☐ Top