

# SAP RFW Framework Complete Migration Dependencies

## Function Group: ZRFW\_CORE

ZRFW\_CORE serves as the central UI and infrastructure layer for the RFW framework, containing screens, GUI statuses, titles, and reusable logic.

Screen No.	Description
8001	Parameter input / variant management
8002	Variant retrieval screen
8003	Supporting subscreen for variants
9000	ALV main result display screen
9001	Result save or variant popup
9010	Progress or parameter display screen
9100	Download selection screen

## GUI Statuses

GUI Status	Context
GET_VARIANT	Retrieve saved variants
RESULT	Main ALV result display
RESULT_SAVE	Save ALV results
SAVE_AS_VARIANT	Save custom variant popup
SELBEDOWNL	Download screen
SELECTION	Selection screen GUI
SELRESULT	Result selection or history

## GUI Titles

GUI Title	Screen Association
GET_VARIANT	8002 / 8003
RESULT	9000
SAVE_AS_VARIANT	9001
SELECTION	8001
SELRESULT	9100

## Function Modules

Function Module	Purpose
-----------------	---------

ZRFW_CORE_GET_VARIANT	Loads user variants
ZRFW_CORE_SAVE_VARIANT	Saves variant data
ZRFW_CORE_RESULT_DISPLAY	Displays ALV results
ZRFW_CORE_DOWNLOAD	Handles file downloads
ZRFW_CORE_SELECTION_SCREEN	Manages dynamic selection subscreen

**Migration Checklist for ZRFW\_CORE**

Category	Object(s)
Function Group	ZRFW_CORE
Screens	8001, 8002, 8003, 9000, 9001, 9010, 9100
GUI Statuses	GET_VARIANT, RESULT, RESULT_SAVE, SAVE_AS_VARIANT, SELBEDOWNL,
GUI Titles	GET_VARIANT, RESULT, SAVE_AS_VARIANT, SELECTION, SELRESULT
Function Modules	ZRFW_CORE_*
Includes	All LZRFW_CORE* includes

**All RFW Framework Classes**

**Controller Layer**

Category	Object Names
Controller	ZCL_RFW_CONTROLLER
Function Group	ZRFW_CONTROLLER_M01
Function Module	ZRFW_CONTROLLER_M01_V01_L02

**View Layer**

View Class	Interface (if any)
ZCL_RFW_VIEW_REPORT_FACADE	ZIF_RFW_VIEW_REPORT
ZCL_RFW_VIEW_ALV_FACADE	ZIF_RFW_VIEW_ALV
ZCL_RFW_VIEW_BEDOWNL_FACADE	ZIF_RFW_VIEW_BEDOWNL
ZCL_RFW_VIEW_SELECTION_SCREEN	ZIF_RFW_MODEL_SELECTION
ZCL_RFW_VIEW_VARIANT_DLGSCR	—
ZCL_RFW_VIEW_PARAMETER_SUBSCR	—
ZCL_RFW_VIEW_RESULT_SCREEN	—
ZCL_RFW_VIEW_PROGRESS	—
ZCL_RFW_VIEW	Superclass (abstract)

### ***Model Layer***

Model Class	Interface (if any)
ZCL_RFW_MODEL_SELECTION_FACADE	ZIF_RFW_MODEL_SELECTION
ZCL_RFW_MODEL_ENVIRONMENT	—
ZCL_RFW_MODEL	Superclass (abstract)

### ***Interfaces***

Interface	Purpose
ZIF_RFW_VIEW_REPORT	Defines report-view methods
ZIF_RFW_VIEW_ALV	Defines ALV display logic
ZIF_RFW_VIEW_BEDOWNL	Defines download behavior
ZIF_RFW_MODEL_SELECTION	Links model to selection screen

### ***Custom Tables***

Table	Purpose
ZKCGT_WBS_RECOG	Recognition rules for WBS revenue recognition
ZVV_PARAM	Framework parameter table for dynamic lookups