


### Program 3

- i. Configure default route, static route to the router
- ii. Procedure along with the topology



- iii. Screen shots/ output

#### Router0 configuration

```
Router0
Physical Config CLI
IOS Command Line Interface
Would you like to enter the initial configuration dialog? [yes/no]: n
Press RETURN to get started!

Router>en
Router#config t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#interface Fa0/0
Router(config-if)#ip address 10.0.0.2 255.0.0.0
Router(config-if)#no shutdown


Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed
state to up
%IP-4-DUPADDR: Duplicate address 10.0.0.2 on FastEthernet0/0, sourced by
000C.CFC2.65B0

Router(config-if)#exit
Router(config)#interface Se2/0
Router(config-if)#ip address 20.0.0.1 255.0.0.0
Router(config-if)#no shutdown

%LINK-5-CHANGED: Interface Serial2/0, changed state to down
Router(config-if)#
```

## Router1 configuration



The screenshot shows the 'Router1' window with the 'CLI' tab selected. The title bar includes 'Router1', a minimize button, a maximize button, and a close button. The window has three tabs: 'Physical', 'Config', and 'CLI'. The 'CLI' tab is active, displaying the 'IOS Command Line Interface'. The interface contains a text area with the following text:

```
Press RETURN to get started!

Router>enable
Router#config t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#interface Se2/0
Router(config-if)#ip address 20.0.0.2 255.0.0.0
Router(config-if)#no shutdown

Router(config-if)#
%LINK-5-CHANGED: Interface Serial2/0, changed state to up


Router(config-if)#exit
Router(config)#interface Se
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial2/0, changed state to
up
3/0
Router(config-if)#ip address 30.0.0.1 255.0
^
% Invalid input detected at '^' marker.

Router(config-if)#ip address 30.0.0.1 255.0.0.0
Router(config-if)#no shutdown

%LINK-5-CHANGED: Interface Serial3/0, changed state to down
Router(config-if)#
```

Below the text area, there is a label 'Ctrl+F6 to exit CLI focus' and two buttons: 'Copy' and 'Paste'. At the bottom left, there is a checkbox labeled 'Top'.

## Router2 configuration



The screenshot shows the 'Router2' window with the 'CLI' tab selected. The title bar includes 'Router2', a minimize button, a maximize button, and a close button. The window has three tabs: 'Physical', 'Config', and 'CLI'. The 'CLI' tab is active, displaying the 'IOS Command Line Interface'. The interface contains a text area with the following text:

```
Router>enable
Router#config t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#interface Se3/0
Router(config-if)#ip address 30.0.0.2 255.0.0.0
Router(config-if)#no shutdown

Router(config-if)#
%LINK-5-CHANGED: Interface Serial3/0, changed state to up

Router(config-if)#exit
Router(config)#inter
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial3/0, changed state to
up
face Fa0/0
Router(config-if)#ip address 40.0.0.1 255.0.0.0
Router(config-if)#no dhutdoen
^
% Invalid input detected at '^' marker.

Router(config-if)#no shutdown


Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed
state to up
```

Below the text area, there is a label 'Ctrl+F6 to exit CLI focus' and two buttons: 'Copy' and 'Paste'. At the bottom left, there is a checkbox labeled 'Top'.

## Static Routing:

### Router0



```
Router0
Physical Config CLI
IOS Command Line Interface

Router>enable
Router#config t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#ip route 30.0.0.0 255.0.0.0 20.0.0.2
Router(config)#ip route 40.0.0.0 255.0.0.0 20.0.0.2
Router(config)#exit
Router#
%SYS-5-CONFIG_I: Configured from console by console


Router#show ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
       N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
       E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
       i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter
       area
       * - candidate default, U - per-user static route, o - ODR
       P - periodic downloaded static route

Gateway of last resort is not set

C    10.0.0.0/8 is directly connected, FastEthernet0/0
C    20.0.0.0/8 is directly connected, Serial2/0
S    30.0.0.0/8 [1/0] via 20.0.0.2
S    40.0.0.0/8 [1/0] via 20.0.0.2

Router#
Ctrl+F6 to exit CLI focus
Copy Paste
Top
```

### Router1



```
Router1
Physical Config CLI
IOS Command Line Interface

Router#
%SYS-5-CONFIG_I: Configured from console by console

Router#config t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#ip route 10.0.0.0 255.0.0.0 20.0.0.1
Router(config)#ip route 40.0.0.0 255.0.0.0 30.0.0.2
Router(config)#exit
Router#
%SYS-5-CONFIG_I: Configured from console by console


Router#show ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
       N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
       E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
       i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter
       area
       * - candidate default, U - per-user static route, o - ODR
       P - periodic downloaded static route

Gateway of last resort is not set

S    10.0.0.0/8 [1/0] via 20.0.0.1
C    20.0.0.0/8 is directly connected, Serial2/0
C    30.0.0.0/8 is directly connected, Serial3/0
S    40.0.0.0/8 [1/0] via 30.0.0.2

Router#
Ctrl+F6 to exit CLI focus
Copy Paste
Top
```

## Router2



The screenshot shows the Router2 CLI interface with the 'CLI' tab selected. The command history shows the user entering 'enable', 'config t', and two static routes: 'ip route 10.0.0.0 255.0.0.0 30.0.0.1' and 'ip route 20.0.0.0 255.0.0.0 30.0.0.1'. The user then enters 'show ip route' to display the routing table. The routing table shows two static routes: 'S 10.0.0.0/8 [1/0] via 30.0.0.1' and 'S 20.0.0.0/8 [1/0] via 30.0.0.1'. The interface also shows the status of the router's interfaces: 'C 30.0.0.0/8 is directly connected, Serial3/0' and 'C 40.0.0.0/8 is directly connected, FastEthernet0/0'.

```
Router>enable
Router#config t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#ip route 10.0.0.0 255.0.0.0 30.0.0.1
Router(config)#ip route 20.0.0.0 255.0.0.0 30.0.0.1
Router(config)#exit
Router#
%SYS-5-CONFIG_I: Configured from console by console

Router#show ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
       N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
       E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
       i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter
       area
       * - candidate default, U - per-user static route, o - ODR
       P - periodic downloaded static route


Gateway of last resort is not set

S    10.0.0.0/8 [1/0] via 30.0.0.1
S    20.0.0.0/8 [1/0] via 30.0.0.1
C    30.0.0.0/8 is directly connected, Serial3/0
C    40.0.0.0/8 is directly connected, FastEthernet0/0

Router#
```

## Dynamic Routing:

## Route0



The screenshot shows the Router0 CLI interface with the 'CLI' tab selected. The command history shows the user entering 'config t', 'ip route 0.0.0.0 0.0.0.0 20.0.0.2', and 'exit'. The user then enters 'show ip route' to display the routing table. The routing table shows two static routes: 'S 30.0.0.0/8 [1/0] via 20.0.0.2' and 'S 40.0.0.0/8 [1/0] via 20.0.0.2'. The interface also shows the status of the router's interfaces: 'C 10.0.0.0/8 is directly connected, FastEthernet0/0' and 'C 20.0.0.0/8 is directly connected, Serial2/0'.

```
Router0>enable
Router0#config t
Enter configuration commands, one per line. End with CNTL/Z.
Router0(config)#ip route 0.0.0.0 0.0.0.0 20.0.0.2
Router0(config)#exit
Router0#
%SYS-5-CONFIG_I: Configured from console by console


Router0#show ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
       N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
       E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
       i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter
       area
       * - candidate default, U - per-user static route, o - ODR
       P - periodic downloaded static route

Gateway of last resort is 20.0.0.2 to network 0.0.0.0

C    10.0.0.0/8 is directly connected, FastEthernet0/0
C    20.0.0.0/8 is directly connected, Serial2/0
S    30.0.0.0/8 [1/0] via 20.0.0.2
S    40.0.0.0/8 [1/0] via 20.0.0.2
S*   0.0.0.0/0 [1/0] via 20.0.0.2

Router0#
```

## Router2



The screenshot shows a window titled "Router2" with tabs for "Physical", "Config", and "CLI". The "CLI" tab is active, displaying the "IOS Command Line Interface". The terminal output shows the following commands and results:

```
C 30.0.0.0/8 is directly connected, Serial3/0
C 40.0.0.0/8 is directly connected, FastEthernet0/0

Router#config t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#ip route 0.0.0.0 0.0.0.0 30.0.0.1
Router(config)#exit
Router#
%SYS-5-CONFIG_I: Configured from console by console

Router#show ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
       N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
       E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
       i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter
       area
       * - candidate default, U - per-user static route, o - ODR
       P - periodic downloaded static route

Gateway of last resort is 30.0.0.1 to network 0.0.0.0

S    10.0.0.0/8 [1/0] via 30.0.0.1
S    20.0.0.0/8 [1/0] via 30.0.0.1
C    30.0.0.0/8 is directly connected, Serial3/0
C    40.0.0.0/8 is directly connected, FastEthernet0/0
S*   0.0.0.0/0 [1/0] via 30.0.0.1

Router#
```

At the bottom of the CLI window, there is a "Ctrl+F6 to exit CLI focus" label, "Copy" and "Paste" buttons, and a "Top" button.

## Pinging:

```
C:\>ping 40.0.0.2

Pinging 40.0.0.2 with 32 bytes of data:

Reply from 40.0.0.2: bytes=32 time=21ms TTL=125
Reply from 40.0.0.2: bytes=32 time=17ms TTL=125
Reply from 40.0.0.2: bytes=32 time=25ms TTL=125
Reply from 40.0.0.2: bytes=32 time=2ms TTL=125

Ping statistics for 40.0.0.2:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 2ms, Maximum = 25ms, Average = 16ms
```