

### 1.如果mysql --install命令报错

Install/Remove of the Service Denied!

则用管理员运行cmd即可

### 2.运行mysql --initialize 之前需要先清空data文件夹要不然可能安装失败

运行完之后密码一般在DESKTOP-KEG858A.err 这个文件夹中

DESKTOP-KEG858A.err - 记事本

文件(F) 编辑(E) 格式(O) 查看(V) 帮助(H)

```
2-09-08T01:41:51.509846Z 0 [Warning] TIMESTAMP with implicit DEFAULT value is deprecated. Please use --explicit_defaults_for_timestamp
2-09-08T01:41:52.852977Z 0 [Warning] InnoDB: New log files created, LSN=45790
2-09-08T01:41:53.201871Z 0 [Warning] InnoDB: Creating foreign key constraint system tables.
2-09-08T01:41:53.374247Z 0 [Warning] No existing UUID has been found, so we assume that this is the first time that this server has been s
2-09-08T01:41:53.407214Z 0 [Warning] Gtid table is not ready to be used. Table 'mysql.gtid_executed' cannot be opened.
2-09-08T01:41:53.414568Z 1 [Note] A temporary password is generated for root@localhost: XkFXAah5fU-5
2-09-08T01:42:22.370117Z 0 [Warning] TIMESTAMP with implicit DEFAULT value is deprecated. Please use --explicit_defaults_for_timestamp
2-09-08T01:42:22.370186Z 0 [Note] --secure-file-priv is set to NULL. Operations related to importing and exporting data are disabled
2-09-08T01:42:22.370463Z 0 [Note] MySQL (mysqld 5.7.26) starting as process 40532 ...
2-09-08T01:42:22.394345Z 0 [Note] InnoDB: Mutexes and rw_locks use Windows interlocked functions
```

### 3.安装完成之后第一次需要进入 mysql来更新密码

mysql -u root -p

然后回提示你输入密码：把上面第二点的密码填入即可

```
ALTER USER 'root'@'localhost' IDENTIFIED WITH mysql_native_password BY '新密码';
```

用上面的命令去变更成新密码，注意这个地方一定要有结尾的引号，这个地方是语句结束的标志。