

javax.swing.JTable

Methods declared in supertypes are hidden in subtypes

javax.swing.event. **ListSelectionListener**

void valueChanged (ListSelectionEvent e)

javax.swing.event. **CellEditorListener**

void editingCanceled (ChangeEvent e)

void editingStopped (ChangeEvent e)

javax.swing.event. **TableModelListener**

void tableChanged (TableModelEvent e)

javax.swing.event. **TableColumnModelListener**

void columnAdded (TableColumnModelEvent e)

void columnMarginChanged (ChangeEvent e)

void columnMoved (TableColumnModelEvent e)

void columnRemoved (TableColumnModelEvent e)

void columnSelectionChanged (ListSelectionEvent e)

java.awt. **Component**

java.awt. **Container**

JComponent

Scrollable

Dimension getPreferredSize ()
int getScrollableBlockIncrement (Rectangle visibleRect,
int orientation, int direction)

boolean getScrollableTracksViewportHeight ()

boolean getScrollableTracksViewportWidth ()

int getScrollableUnitIncrement (Rectangle visibleRect,
int orientation, int direction)

JTable

JTable ()

JTable (TableModel dm)

JTable (TableModel dm, TableColumnModel cm)

JTable (int numRows, int numColumns)

JTable (Vector rowData, Vector columnNames)

JTable (Object[][] rowData, Object[] columnNames)

JTable (TableModel dm, TableColumnModel cm, ListSelectionModel sm)

Accessors

boolean get / setAutoCreateColumnsFromModel ()

int get / setAutoResizeMode ()

TableCellEditor get / setCellEditor ()

TableCellEditor getCellEditor (int row, int column)

Rectangle getCellRect (int row, int column, boolean includeSpacing)

TableCellRenderer getCellRenderer (int row, int column)

boolean get / setCellSelectionEnabled ()

TableColumn getColumn (Object identifier)

Class getColumnClass (int column)

int getColumnCount ()

TableColumnModel get / setColumnModel ()

String getColumnName (int column)

boolean get / setColumnSelectionAllowed ()

TableCellEditor get / setDefaultEditor (Class columnClass)

TableCellRenderer get / setDefaultRenderer (Class columnClass)

boolean get / setDragEnabled ()

int get / setEditingColumn ()

int get / setEditingRow ()

Component getEditorComponent ()

Color get / setGridColor ()

Dimension get / setInterCellSpacing ()

TableModel get / setModel ()

int getRowCount ()

int get / setRowHeight ()

int get / setRowHeight (int row)

int get / setRowMargin ()

boolean get / setRowSelectionAllowed ()

int getSelectedColumn ()

int getSelectedColumnCount ()

int[] getSelectedColumns ()

int getSelectedRow ()

int getSelectedRowCount ()

int[] getSelectedRows ()

Color get / setSelectionBackground ()

Color get / setSelectionForeground ()

ListSelectionModel get / setSelectionModel ()

boolean get / setShowHorizontalLines ()

boolean get / setShowVerticalLines ()

boolean get / setSurrendersFocusOnKeystroke ()

JTableHeader get / setTableHeader ()

TableUI get / setUI ()

Object get / setValueAt (int row, int column)

boolean isCellEditable (int row, int column)

boolean isCellSelected (int row, int column)

boolean isColumnSelected (int column)

boolean isEditing ()

boolean isRowSelected (int row)

void setColumnSelectionInterval (int index0, int index1)

void setRowSelectionInterval (int index0, int index1)

void setSelectionMode (int selectionMode)

void setShowGrid (boolean showGrid)

Collectors

void add / removeColumn (TableColumn aColumn)

void add / removeColumnSelectionInterval (int index0, int index1)

void add / removeRowSelectionInterval (int index0, int index1)

void removeEditor ()

Event Methods

boolean editCellAt (int row, int column, EventObject e)

Other Public Methods

void changeSelection (int rowIndex, int columnIndex, boolean toggle, boolean extend)

void clearSelection ()

int columnAtPoint (Point point)

int convertColumnIndexToModel (int viewColumnIndex)

int convertColumnIndexToView (int modelColumnIndex)

void createDefaultColumnsFromModel ()

boolean editCellAt (int row, int column)

void moveColumn (int column, int targetColumn)

Component prepareEditor (TableCellEditor editor, int row, int column)

Component prepareRenderer (TableCellRenderer renderer, int row, int column)

int rowAtPoint (Point point)

void selectAll ()

void sizeColumnsToFit (int resizingColumn)

Other Protected Methods

void configureEnclosingScrollPane ()

TableColumnModel createDefaultColumnModel ()

TableModel createDefaultDataModel ()

void createDefaultEditors ()

void createDefaultRenderers ()

ListSelectionModel createDefaultSelectionModel ()

JTableHeader createDefaultTableHeader ()

void initializeLocalVars ()

void resizeAndRepaint ()

void unconfigureEnclosingScrollPane ()

int AUTO_RESIZE_OFF, AUTO_RESIZE_NEXT_COLUMN,
AUTO_RESIZE_SUBSEQUENT_COLUMNS, AUTO_RESIZE_LAST_COLUMN,
AUTO_RESIZE_ALL_COLUMNS