

ScrollPaneConstants

String

VIEWPORT, VERTICAL_SCROLLBAR, HORIZONTAL_SCROLLBAR, ROW_HEADER, COLUMN_HEADER, LOWER_LEFT_CORNER, LOWER_RIGHT_CORNER, UPPER_LEFT_CORNER, UPPER_RIGHT_CORNER, LOWER_LEADING_CORNER, LOWER_TRAILING_CORNER, UPPER_LEADING_CORNER, UPPER_TRAILING_CORNER, VERTICAL_SCROLLBAR_POLICY, HORIZONTAL_SCROLLBAR_POLICY, VERTICAL_SCROLLBAR_AS_NEEDED, VERTICAL_SCROLLBAR_NEVER, VERTICAL_SCROLLBAR_ALWAYS, HORIZONTAL_SCROLLBAR_AS_NEEDED, HORIZONTAL_SCROLLBAR_NEVER, HORIZONTAL_SCROLLBAR_ALWAYS

int

javax.swing.*

Scrolling

Methods declared in supertypes are hidden in subtypes

Component

java.awt

Container

java.awt

JComponent

java

Serializable

ScrollPaneLayout

Accessors + Collectors

JViewport getColumnHeader ()
Component getCorner (String key)
JScrollbar getHorizontalScrollbar ()
int get / setHorizontalScrollbarPolicy ()
JViewport getRowHeader ()
JScrollbar getVerticalScrollbar ()
int get / setVerticalScrollbarPolicy ()
JViewport getViewPort ()
Component addSingletonComponent (Component oldC, Component newC)
Other Public Methods
void syncWithScrollPane (JScrollPane sp)

class

UIResource

LayoutManager

java.awt

ViewPortLayout

Serializable

JScrollPane

JScrollPane ()
JScrollPane (Component view)
JScrollPane (int vsbPolicy, int hsbPolicy)
JScrollPane (Component view, int vsbPolicy, int hsbPolicy)

Accessors

JViewport getColumnHeader ()
Component get / setCorner (String key)
JScrollbar get / setHorizontalScrollbar ()
int get / setHorizontalScrollbarPolicy ()
JViewport get / setRowHeader ()
ScrollPaneUI get / setUI ()
JScrollbar get / setVerticalScrollbar ()
int get / setVerticalScrollbarPolicy ()
JViewport get / setViewport ()
Border get / setViewportBorder ()
Rectangle getViewportBorderBounds ()
boolean is / setWheelScrollingEnabled ()
void setColumnHeaderView (Component view)
void setRowHeaderView (Component view)
void setViewportView (Component view)
Other Methods
JScrollbar createHorizontalScrollbar ()
JScrollbar createVerticalScrollbar ()
JViewport createViewport ()

Scrollable

Dimension getPreferredSize (ViewportSize i)
int getScrollableBlockIncrement (Rectangle visibleRect, int orientation, int direction)
boolean getScrollableTracksViewportHeight ()
boolean getScrollableTracksViewportWidth ()
int getScrollableUnitIncrement (Rectangle visibleRect, int orientation, int direction)

JViewport

JViewport ()

Accessors

Dimension get / setExtentSize ()
int get / setScrollMode ()
ViewportUI get / setUI ()
Component get / setView ()
Point get / setViewPosition ()
Rectangle getViewRect ()
Dimension get / setViewSize ()
Event Methods
void add / removeChangeListener (ChangeListener i)
ViewListener createViewListener ()
void fireStateChanged ()
ChangeListener[] getChangeListeners ()
Other Public Methods
Dimension toViewCoordinates (Dimension size)
Point toViewCoordinates (Point p)
Other Protected Methods
computeBlit (int dx, int dy, Point blitFrom, Point blitTo, Dimension blitSize, Rectangle blitPaint)
LayoutManager createLayoutManager ()
int BLIT_SCROLL_MODE, BACKINGSTORE_SCROLL_MODE, SIMPLE_SCROLL_MODE

JScrollbar

JScrollbar ()
JScrollbar (int orientation)
JScrollbar (int orientation, int value, int extent, int min, int max)

Accessors

int getBlockIncrement ()
BoundedRangeModel get / setModel ()
ScrollbarUI get / setUI ()
int getUnitIncrement (int direction)
boolean get / setValuesAdjusting ()
void setValues (int newValue, int newExtent, int newMin, int newMax)
Event Methods
void fireAdjustmentValueChanged (int id, int type, int value)
AdjustmentListener[] getAdjustmentListeners ()

Adjustable

java.awt

Accessors

int get / setBlockIncrement ()
int get / setMaximum ()
int get / setMinimum ()
int getOrientation ()
int get / setUnitIncrement ()
int get / setValue ()
int get / setVisibleAmount ()
Event Methods
void add / removeAdjustmentListener (AdjustmentListener i)
int HORIZONTAL, VERTICAL, NO_ORIENTATION