

```
Linux - Desktop Viewer
Workstation
rhel01
CGI Linux Client

insmod xfs
set root='hd0,msdos1'
if [ x$feature_platform_search_hint = xy ]; then
    search --no-floppy --fs-uuid --set=root --hint-bios=hd0,msdos1 --hin\
t-efi=hd0,msdos1 --hint-baremetal=ahci0,msdos1 --hint='hd0,msdos1' ca3940ec-4\
d68-4a0f-bcd4-4690ee833d2b
else
    search --no-floppy --fs-uuid --set=root ca3940ec-4d68-4a0f-bcd4-4690\
ee833d2b
fi
linux16 /vmlinuz-3.10.0-123.el7.x86_64 root=UUID=520501f1-49df-44d1-83\
5f-e9f1b68fb426 ro rd.lvm.lv=rhel/root rd.lvm.lv=rhel/swap vconsole.font=lata\
rcyrheb-sun16 vconsole.keymap=us rd.break quiet LANG=en_US.UTF-8
initrd16 /initramfs-3.10.0-123.el7.x86_64.img

Press Ctrl-x to start, Ctrl-c for a command prompt or Escape to
discard edits and return to the menu. Pressing Tab lists
possible completions.

Activate Windows
Go to Settings to activate Windows.
```

```
Linux - Desktop Viewer
Workstation
rhel01
CGI Linux Client

[ OK ] Reached target basic system.
Starting File System Check on /dev/disk/by-uuid/5205...e9f1b68fb426...
[ OK ] Reached target basic system.
systemd-fsck[552]: fsck: error 2 (No such file or directory) while executing fsck.ext2 for /dev/disk/by-uuid/520501f1-49df-44d1-835f-e9f1b68fb426
[ OK ] Started File System Check on /dev/disk/by-uuid/5205...f-e9f1b68fb426.
[ OK ] Started dracut initqueue hook.
Mounting /sysroot...
[ OK ] Mounted /sysroot.
[ OK ] Reached target Initrd Root File System.
Starting Reload Configuration from the Real Root...
[ OK ] Started Reload Configuration from the Real Root.
[ OK ] Reached target Initrd File Systems.
[ OK ] Reached target Initrd Default Target.
dracut-pre-pivot[756]: Warning: Break before switch_root
Generating "/run/initramfs/rdsosreport.txt"

Entering emergency mode. Exit the shell to continue.
Type "journalctl" to view system logs.
You might want to save "/run/initramfs/rdsosreport.txt" to a USB stick or /boot
after mounting them and attach it to a bug report.

switch_root:/# mount -o remount, rw /sysroot
switch_root:/# chroot /sysroot
sh-4.2# passwd
Changing password for user root.
New password:
BAD PASSWORD: The password is shorter than 8 characters
Retype new password:
passwd: all authentication tokens updated successfully.
sh-4.2# touch /.autorelabel
sh-4.2# exit
exit
switch_root:/# exit
logout
[ 247.569910] piix4_smbus 0000:00:07.3: Host SMBus controller not enabled!

Activate Windows
Go to Settings to activate Windows.
```

