

BRP SUB (BRP IS "MNEMONIC" FOR BET RAISE POT)

```

080C BRP   :A9D4 ;BET   -- Set "I" to ASCII string for "BET RSE POT"
OE       6C00 ;VC=00 -- VC is VX coordinate for display "BET"

0810      6D00 ;VD=00 -- VD is VY      "      "
12      2846 PRINT -- Do sub -- print one ASCII string ("I" changed)
14      6C34 ;VC=34 -- VC is VX coordinate for display "RSE"
16      2846 PRINT -- Do sub -- print one ASCII string ("I" changed)
18      6C1A ;VC=1A -- VC is VX coordinate for display "POT"
1A      6D1B ;VD=1B -- VD is VY      "      "
1C      2846 PRINT -- Do sub -- print one ASCII string
1E      00EE ;RET   -- Return

```

BRP VALUE SUBS

```

0820 BET$   :6C00 ;VC=00 -- VC is VX coordinate for number display
22      6D06 ;VD=06 -- VD is VY      "      "
24      8090 ;V0=V9 -- V0 passes value for display to sub
26      279C NUMBS -- Do sub -- convert/display value in V0
28      00EE ;RET   -- Return
2A RSE$     :6C34 ;VC=34 -- VC is VX coordinate for number display
2C      6D06 ;VD=06 -- VD is VY      "      "
2E      80A0 ;V0=VA -- V0 passes value for display to sub

0830      279C NUMBS -- Do sub -- convert/display value in V0
32      00EE ;RET   -- Return
34 POT$     :6C1A ;VC=1A -- VC is VX coordinate for number display
36      6D21 ;VD=21 -- VD is VY      "      "
38      80B0 ;V0=VB -- V0 passes value for display to sub
3A      279C NUMBS -- Do sub -- convert/display value in V0
3C      00EE ;RET   -- Return

```

MESSAGE CENTER SUB/PRINT SUB

```

083E MCENT :093A ;MLS   -- Do MLS -- Clear message area (erasing old
                        message)
0840      094A ;MLS   -- Do MLS -- set "I" to ASCII message indexed
42      6C00 ;VC=00 -- Vc is VX coordinate for display /by V0
44      6D2A ;VD=2A -- VD is VY      "      "
46 PRINT :0244 ;MLS   -- Do MLS -- Call messenger (prints message)
48      DCD5 ;SHOW  -- DXYN instruction for use by messenger
4A      00EE ;RET   -- Return

```