

Doireann Ní Ghrioghair |
FLYUX | UX Design Institute


Module 10 | Project 16: Wireframes for Mobile

01.01 Landing Page_Intro



1 sec screen on app loading
and dissolve to *1.2 Landing Page*

01.02 Landing Page



On selection, user is brought to log-in page

- If user already logged in, first name will appear after greeting
- Greeting changes to 'Good Afternoon' or 'Good Evening' depending on user's local time zone.

Attractive destination image in background, changing seasonally

On selection, user is brought to **02.01 Flight Search_Home**
- 'Ease Out' transition, 0.4sec

On selection, user is brought to check-in page.

On selection, animated side navigation bar appears

On selection, user is brought to page with latest Covid-19 updates & rules in destinations served by airline

02.01 Flight Search_Home

The screenshot shows a mobile app interface for flight search. At the top is a blue header with a back arrow and the text 'FLIGHT SEARCH'. Below this are two buttons: 'RETURN' (highlighted in blue) and 'ONE-WAY' (greyed out). The main form has two sections. The first section is for origin and destination: 'Fly from' with a dropdown menu showing 'Dublin' and 'DUB', and 'Fly to' with a text input field containing 'Where are you going?'. A swap button with two arrows is between them. The second section is for travel type: 'Departing' and 'Return' buttons, both with 'SELECT' text and a calendar icon. Below these are 'Adults' (1) and 'Children' (0) with plus and minus icons. At the bottom is a large grey 'Find Flights' button. Orange circles and lines point from various text boxes to specific UI elements: the 'RETURN' button, the 'Fly from' dropdown, the 'Fly to' input, the swap button, the 'Departing' button, the 'Return' button, the 'Adults' and 'Children' stepper icons, the 'Find Flights' button, and the background image.

- 'Fly from' is prepopulated with user's nearest airport
- If geolocation not enabled on user's browser, form is filled with: "Where are you flying from?"
- Upon selection, user is brought to **02.02 Flight Search_Airport List_1** ('slide up' transition - 0.2sec)

Button that allows for values of 'Fly from' and 'Fly to' to be switched.

Upon selection, user is brought to **02.03 Flight Search_Airport List_2** ('slide up' transition - 0.2sec)

Upon selection of 'Departing' or 'Return' boxes, user is brought to **02.04 Flight Search_Calendar_1** ('slide up' transition - 0.2sec)

Number stepper '+' icons are grey and can't be selected until destination & date forms are filled. See: **02.07 Flight Search_Home_2** for changed state.

'Find Flights' CTA remains grey and can't be selected until airports & date forms filled. See: **02.07 Flight Search_Home_2** for changed state.

Background is image from **01.02 Landing Page** but with blur overlay

- Preset to return
- User can select 'One-Way', which will remove the 'Return' option

Upon selection, user is brought to **01.02 Landing Page**.

02.02 Flight Search_Airport List_1

FLIGHT SEARCH

Q

Search

Suggested Airports

Dublin

Rep. of Ireland

DUB

Belfast

United Kingdom

BFS

All Airports

Aberdeen

United Kingdom

ABZ

Agadir

Morocco

AGA

Amsterdam

Netherlands

AMS

Ancona

Italy

AOI

Athens

Greece

ATH

Barcelona Reus

Spain

REU

Bari

Italy

BRI

Belfast

United Kingdom

BFS

Berlin

Germany

BER

Copenhagen

Denmark

CPH

Cologne

Germany

CGN

Delhi

India

DEL

Dhaka

Bangladesh

DAC

Doha

Quatar

DOH

Dubai

United Arab Emirates

DXD

Dublin

Ireland

DUB

Dubrovnik

Croatia

DBV

Fez

Morocco

FEZ

Guam

Guam

GUM

Guangzhou

China

CAN

Helsinki

Finland

HEL

Hiroshima

Japan

HIJ

Hong Kong

Hong Kong - SAR of China

HKG

Istanbul (All Airports)

Turkey

IST

Lanzarote Island

Spain

ACE

Lisbon

Portugal

LIS

Ljubljana

Slovenia

LJU

London (All Airports)

United Kingdom

LDN

London (Gatwick)

United Kingdom

LGW

London (Heathrow)

United Kingdom

LHR

London (Luton)

United Kingdom

LTN

London (Stansted)

United Kingdom

STN

Milan

Italy

MLA

Malmo

Sweden

MMX

Malta

Malta

MLT

Naples

Italy

NAP

Nice

France

NCE

Oslo

Norway

OSL

Osaka (Kansai)

Japan

KIX

Podgorica

Montenegro

TGB

Rabat

Morocco

RBA

Riga

Latvia

RIX

Salzburg

Austria

SZG

Shannon

Ireland

SNN

Thessaloniki

Greece

SKG

Tokyo (All Airports)

Japan

TYO

Tokyo (Haneda)

Japan

HND

Tokyo (Narita Int.)

Japan

NRT

Turin

Italy

TRN

Venice (Marco Polo)

Italy

VCE

- On selection, flashing cursor appears in 'Search' box and QWERTY keyboard appears.

- Nearest airports to user are displayed first under 'Suggested Airports'.
- All other airports are then displayed alphabetically.
- Screen header and 'Search' bar remain fixed on screen as user scrolls through airport list.
- As user types, list modifies corresponding with letters typed eg. if user types 'L', all airports beginning with 'L' will appear, while the rest disappear. If the user then types 'o', then 'London' airport options appear only.
- On selection of airport from list, user is brought back to **02.02 Flight Search_Home** with 'Fly from' field populated with selection value ('slide down' transition - 0.2sec)

On selection, user is brought to **02.01 Flight Search_Home** ('slide down' transition - 0.2sec)

<scrollable area

02.03 Flight Search_Airport List_2

FLIGHT SEARCH

Search

Recent Searches

Tokyo (*All Airports*)
Rep. of Ireland

TOK

Naples
Italy

NAP

All Airports

Aberdeen
United Kingdom

ABZ

Agadir
Morocco

AGA

Amsterdam
Netherlands

AMS

Ancona
Italy

AOI

Athens
Greece

ATH

Barcelona Reus
Spain

REU

Bari
Italy

BRI

Belfast
United Kingdom

BFS

Berlin
Germany

BER

Copenhagen
Denmark

CPH

Cologne
Germany

CGN

Delhi
India

DEL

Dhaka
Bangladesh

DAC

Doha
Quatar

DOH

Dubai
United Arab Emirates

DXD

Dublin
Ireland

DUB

Dubrovnik
Croatia

DBV

Fez
Morocco

FEZ

Guam
Guam

GUM

Guangzhou
China

CAN

Helsinki
Finland

HEL

Hiroshima
Japan

HIJ

Hong Kong
Hong Kong - SAR of China

HKG

Istanbul (*All Airports*)
Turkey

IST

Lanzarote Island
Spain

ACE

Lisbon
Portugal

LIS

Ljubljana
Slovenia

LJU

London (*All Airports*)
United Kingdom

LDN

London (Gatwick)
United Kingdom

LGW

London (Heathrow)
United Kingdom

LHR

London (Luton)
United Kingdom

LTN

London (Stansted)
United Kingdom

STN

Milan
Italy

MLX

Malmö
Sweden

MMX

Malta
Malta

MLT

Naples
Italy

NAP

Nice
France

NCE

Oslo
Norway

OSL

Osaka (*Kansai*)
Japan

KIX

Podgorica
Montenegro

TGB

Rabat
Morocco

RBA

Riga
Latvia

RIX

Salzburg
Austria

SZG

Shannon
Ireland

SNN

Thessaloniki
Greece

SKG

Tokyo (*All Airports*)
Japan

TYO

Tokyo (*Haneda*)
Japan

HND

Tokyo (*Narita Int.*)
Japan

NRT

Turin
Italy

TRN

Venice (*Marco Polo*)
Italy

VCE

- On selection, flashing cursor appears in 'Search' box and QWERTY keyboard appears.

- Recent searches are displayed first.
- All other airports are then displayed alphabetically.
- Screen header and 'Search' bar remain fixed on screen as user scrolls through airport list.
- As user types, list modifies corresponding with letters typed eg. if user types 'L', all airports beginning with 'L' will appear, while the rest disappear. If the user then types 'o', then 'London' airport options appear only.
- On selection of airport from list, user is brought back to **02.02 Flight Search_Home** with 'Fly to' field populated with selection value ('slide down' transition - 0.2sec)

On selection, user is brought to **02.01 Flight Search_Home** ('slide down' transition - 0.2sec)


<scrollable area

02.04 Flight Search_Calendar_1

CHOOSE DATES

Going Out

London



Tokyo

Mon	Tues	Wed	Thurs	Fri	Sat	Sun
December 2020						
	1	2	3	4	5	6
7	8	9	10	11	12	13
14	15	16	17	18	19	20
21	22	23	24	25	26	27
28	29	30	31			
January 2021						
				1	2	3
4	5	6	7	8	9	10
11	12	13	14	15	16	17
18	19	20	21	22	23	24
25	26	27	28	29	30	31
February 2021						
1	2	3	4	5	6	7
8	9	10	11	12	13	14
15	16	17	18	19	20	21
22	23	24	25	26	27	28
March 2021						
1	2	3	4	5	6	7
8	9	10	11	12	13	14
15	16	17	18	19	20	21
22	23	24	25	26	27	28
29	30	31				
April 2021						
			1	2	3	4
5	6	7	8	9	10	11
12	13	14	15	16	17	18
19	20	21	22	23	24	25
26	27	28	29	30		

Page header, 'Going Out', airport names & icon, days of week remain fixed position on screen while user scrolls through calendar.

Upon selection of date, this page changes state - see: **02.05 Flight Search_Calendar_2** (fixed screen position on transition)

On selection, user is brought to **02.01 Flight Search_Home**

<scrollable area

end of viewport

02.05 Flight Search_Calendar_2


✕

CHOOSE DATES

Coming Back

RESET

Tokyo



London

Mon

Tues

Wed

Thurs

Fri

Sat

Sun

December 2020

1

2

3

4

5

6

7

8

9

10

11

12

13

14

15

16

17

18

19

20

21

22

23

24

25

26

27

28

29

30

31

January 2021

1

2

3

4

5

6

7

8

9

10

11

12

13

14

15

16

17

18

19

20

21

22

23

24

25

26

27

28

29

30

31

February 2021

1

2

3

4

5

6

7

8

9

10

11

12

13

14

15

16

17

18

19

20

21

22

23

24

25

26

27

28

March 2021

1

2

3

4

5

6

7

8

9

10

11

12

13

14

15

16

17

18

19

20

21

22

23

24

25

26

27

28

29

30

31

April 2021

1

2

3

4

5

6

7

8

9

10

11

12

13

14

15

16

17

18

19

20

21

22

23

24

25

26

27

28

29

30

Upon selection, screen
reverts to original state
- see:
02.04 Flight Search_Calendar_1

Page header, 'Coming Back',
airport names & icon,
days of week remain
fixed position on screen
while user scrolls through
calendar.

- Selected date appears bold,
white with teal circle
background.
- Upon selection of return date,
screen changes state. See:
02.06 Flight Search_Calendar_3
(fixed screen position on
transition)

On selection, user is
brought to
02.01 Flight Search_Home

02.06 Flight Search_Calendar_3

✕

CHOOSE DATES

Coming Back

RESET

Tokyo

London

Mon

Tues

Wed

Thurs

Fri

Sat

Sun

December 2020

1

2

3

4

5

6

7

8

9

10

11

12

13

14

15

16

17

18

19

20

21

22

23

24

25

26

27

28

29

30

31

January 2021

1

2

3

4

5

6

7

8

9

10

11

12

13

14

15

16

17

14 nights in Tokyo

Continue

8

9

10

11

12

13

14

15

16

17

18

19

20

21

22

23

24

25

26

27

28

March 2021

1

2

3

4

5

6

7

8

9

10

11

12

13

14

15

16

17

18

19

20

21

22

23

24

25

26

27

28

29

30

31

April 2021

1

2

3

4

5

6

7

8

9

10

11

12

13

14

15

16

17

18

19

20

21

22

23

24

25

26

27

28

29

30

Upon selection, screen
reverts to original state
- see:
02.04 Flight Search_Calendar_1

Pop-up bar at bottom
of screen with 'nights'
displayed corresponding
with selected dates.

On selection, user is
brought to
02.07 Flight Search_Home_2
(‘slide-down’ transition - 0.2 sec)


Selected dates appear
as such with low opacity
teal highlighting dates
between.

On selection, user is
brought to
02.01 Flight Search_Home

<scrollable area

end of viewport

02.07 Flight Search_Home_2




The image shows a mobile app interface for flight search. At the top is a blue header with a back arrow and the text 'FLIGHT SEARCH'. Below this are two tabs: 'RETURN' (active) and 'ONE-WAY'. The main form has two rows for destination selection. The first row is 'Fly from' with 'London (All Airports)' and 'LDN'. The second row is 'Fly to' with 'Tokyo (All Airports)' and 'TOK'. Below these are date pickers for 'Departing' (FRI 12 March 2021) and 'Return' (FRI 26 March 2021). At the bottom are two number steppers: 'Adults' (set to 2) and 'Children' (set to 0). A large blue 'Find Flights' button is at the bottom. Orange circles highlight the 'Fly to' field, the 'Return' date, and the 'Find Flights' button. An orange line connects the 'Return' date to a text box on the right. Another orange line connects the 'Find Flights' button to a text box on the right.

- Once 'Fly from' & 'Fly to', 'Departing' & 'Return' forms are filled, number stepper icons turn colour
- Number increases upon selection of '+'
- Once number is over 1, 'minus' icon appears to left of number.
- Min adults is set to 1
- Children set to 0


'Find Flights' CTA is appears with colour once all forms are filled. On selection, user is brought to transition animation screens (see **02.08 Transition Search_Transition**) preceding Flight Selection options

02.08 Flight Search_Transition



Transition animation lasting 0.21 sec or while flight results are loading.

03.01 Flight Selection_No Flights



On selection, user is brought to:
02.07 Flight Search_Home_2
(with all forms filled as before)

On selection, pop-up appears
with currency options.
Preset to user's local currency.

On selection of or on swipe/scroll
right, screen changes state - see:
03.02 Flight Selection_Going Out_1

Card that appears if no flights
available on day, but other flights
available on surrounding dates.

On selection or on swipe/scroll left,
screen changes state so 'Thurs 11
March' is main card/ departure date
and available flights are shown for
that day.

On selection, user is brought to:
02.07 Flight Search_Home_2
(with all forms filled as before)

03.02 Flight Selection_Going Out_1



On selection, user is brought to: **02.07 Flight Search_Home_2** (with all forms filled as before)

On selection, pop-up appears with currency options. Preset to user's local currency.


On selection or on swipe/scroll left, screen changes state so 'Sun 14 March' is main card/ departure date and available flights are shown for that day.

On selection, panel animates to expand to 'open' state - see: **03.03 Flight Selection_Going Out_2** (transition 'ease in' - 0.4sec)

On selection, user is brought to: **03.01 Flight Selection_No Flights**

On selection, user is brought to: **03.01 Flight Selection_No Flights**

03.03 Flight Selection_Going Out_2



On selection, user is brought to:
02.07 Flight Search_Home_2
(with all forms filled as before)

Page header , Dep & dest
airports & icon remain fixed
when user scrolls

On selection, panel animates
to 'closed' state - see:
03.02 Flight Selection_Going Out_1
(transition 'ease in' - 0.4 sec)

On selection, pop-up
appears with airline baggage
rules.

On selection of fare
(anywhere in fare panel),
page state changes. See:
03.04 Flight Selection_Going Out_3

Dynamic chevron at bottom of
viewport that disappears when
user scrolls.

On selection or on swipe/scroll left,
screen changes state so 'Fri 12
March' is main card/ departure date
and available flights are shown for
that day.

On selection, user is brought to
previous screen eg.
03.02 Flight Selection_Going Out_1


3. Flight Selection

18/02/2020

03.04 Flight Selection_Going Out_3



03.04 Flight Selection_Coming Back_1



On selection, user is brought to:
02.07 Flight Search_Home_2
(with all forms filled as before)

On selection, user is brought to:
03.05 Flight Selection_Coming Back_2

If discrepancy between number of nights originally selected in:
02.Flight Search and **03.Flight Selection**
(due to flight availability, etc),
number of nights appears with
exclamation mark and yellow background

On selection or on swipe/scroll left,
screen changes state so 'Thurs 25
March' is main card/ return date
and available flights are shown for
that day.

On selection, user is brought to:
03.03 Flight Selection_Going Out_3


03.05 Flight Selection_Coming Back_2



If **no discrepancy** between number of nights originally selected in: **02.Flight Search** and **03.Flight Selection** number of nights appears with low opacity teal background

On selection, panel animates to 'open' state - see: **03.06 Flight Selection_Coming Back_3** (transition 'ease in' - 0.4 sec)

03.06 Flight Selection_Coming Back_3



Page header , Dep & dest airports & icon remain fixed when user scrolls

On selection, panel animates to 'closed' state - see: **03.02 Flight Selection_Going Out_1** (transition 'ease in' - 0.4 sec)

On selection, pop-up appears with airline baggage rules.

On selection of fare (anywhere in fare panel), page state changes. See: **03.04 Flight Selection_Coming Back_4**

Dynamic chevron at bottom of viewport that disappears when user scrolls.


end of viewport

<scrollable area

3. Flight Selection

18/02/2020

03.05 Flight Selection_Coming Back_4



04.01 Flight Selection Summary

The screenshot shows a mobile app interface for a flight selection summary. At the top is a teal header with a back arrow and the text 'SELECTION SUMMARY'. Below this are two flight cards. The first card is for 'SAT 13 March 2021 Going Out' with an 'Edit' button. It shows a flight from London Gatwick (LGW) to Tokyo Haneda (HND), departing at 16:45 and arriving at 19:45⁺¹ after 18h (1 stop). The price is €320 for adults x 2, with a total of €640. The second card is for 'SAT 26 March 2021 Coming Back' with an 'Edit' button. It shows a flight from Tokyo Haneda (HND) to London Heathrow (LHR), departing at 16:45 and arriving at 19:45⁺¹ after 18h (1 stop). The price is €250 for adults x 2, with a total of €500. At the bottom, there is a white box containing 'TOTAL €1140' and a teal 'Continue' button. Orange circles and lines highlight specific elements: a back arrow, the 'Edit' button of the first flight, the 'Edit' button of the second flight, the 'Continue' button, and the total price.

SELECTION SUMMARY

SAT 13 March 2021 **Going Out** **Edit**

✈ London Gatwick (LGW)
Tokyo Haneda (HND)

Depart LGW **Arrive HND**
16:45 19:45⁺¹
18h (1 stop) ⓘ

Adults x 2 €320
Total €640

SAT 26 March 2021 **Coming Back** **Edit**

✈ Tokyo Haneda (HND)
London Heathrow (LHR)

Depart HND **Arrive LHR**
16:45 19:45⁺¹
18h (1 stop) ⓘ

Adults x 2 €250
Total €500

TOTAL €1140 **Continue**


On selection, user is brought to:
03.05 Flight Selection_Coming Back_2

On selection, user is brought to:
03.02 Flight Selection_Going Out_1

- On selection, if there is a discrepancy between airports in either location eg. departs from one airport in a city, but returns to another airport in same city, screen changes state to:
04.02 Flight Selection Summary_Alert Box
- Else, user is brought to:
05.01 Passenger Details_Sign In

On selection, user is brought to:
03.05 Flight Selection_Coming Back_4

04.02 Flight Selection Summary_Alert Box



On selection, user is brought to:
05.01 Passenger Details_Sign In

On selection, user is brought to:
04.01 Flight Selection Summary

05.01 Passenger Details_Sign In

- On selection, flashing cursor appears in email form and QWERTY keyboard pops-up.
- Error message appears if entry not recognised email format
- User selects 'password' form to enter password once email is complete
- Password entry appears in dots on screen.

- Only able to select once email and password entered.
- Error message appears if email and password don't match, with link to reset password if forgotten.
- On selection, user is brought to form with their details pre-populated and form to fill in details of second passenger

On selection, user is brought to 'Sign Up' page

On selection, user is brought to:
05.02 Passenger Details_1

Background image corresponds to chosen destination and season eg. cherry blossoms for a trip to Japan in March

On selection, user is brought to:
04.01 Flight Selection Summary

05.02 Passenger Details_1

PASSENGER DETAILS

Passenger 1 Edit

Full Name

D.O.B.

Passenger 2 Edit

Full Name

D.O.B.

On selection, flashing cursor appears in 'Full Name' form and Qwerty keyboard pops-up.

On selection, flashing cursor appears in 'Full Name' form and Qwerty keyboard pops-up

On selection number, number keypad pops-up and flashing cursor appears in D.O.B. form.

On selection, flashing cursor appears in 'Full Name' form and Qwerty keyboard pops-up.

On selection, flashing cursor appears in 'Full Name' form and Qwerty keyboard pops-up

On selection number, number keypad pops-up and flashing cursor appears in D.O.B. form.

On selection, user is brought to:
05.01 Passenger Details_Sign In

*Once all forms filled,
page changes state to display
'Continue' CTA. See:
05.02 Passenger Details_Sign In_Continue

05.02 Passenger Details_Sign In_Continue

PASSENGER DETAILS

Passenger 1 [Edit](#)

Full Name
Yukio Mishima

D.O.B.
14 / 01 / 1925

Passenger 2 [Edit](#)

Full Name
Natsume Soseki

D.O.B.
09 / 02 / 1867

Continue

On selection, user is brought to:
05.03 Passenger Details_Contact Details

05.03 Passenger Details_Contact Details

CONTACT DETAILS

Let us know how to contact you and where to send your booking:

Email Edit

Tel +353 / /

On selection, QWERTY keyboard pops-up and flashing cursor appears in 'email' form.


- On selection, QWERTY keyboard pops-up and flashing cursor appears in email form.
- Error message appears if input is not in email format.

- Tel form with preset country according to user's location, can be changed on selection
- On selection, number keypad pops-up and flashing cursor appears in form
- Error message appears if number not in recognised format

On selection, user is brought to:
05.02 Passenger Details_Sign In_Continue

Once all forms completed, screen changes state to display 'Continue' CTA:
05.04 Passenger Details_Contact Details_Continue

05.04 Passenger Details_Contact Details_Continue



The image shows a mobile application screen titled "CONTACT DETAILS". At the top, there is a teal header bar with a white back arrow icon on the left and the text "CONTACT DETAILS" in white. Below the header, the main content area has a light gray background. It starts with the text "Let us know how to contact you and where to send your booking:". Below this, there is a white card with a light gray border. Inside the card, the word "Email" is followed by the text "yukie@goldentemple.com". To the right of the email field is a small teal "Edit" link. Below the email field, the word "Tel" is followed by the text "+353 / 123 / 567888". At the bottom of the screen, there is a large teal button with the word "Continue" in white. An orange circle is positioned on the right side of the "Continue" button, with a line extending from it to a callout box on the right.

On selection, screen changes state to display seat selection pop-up. See: *05.05 Passenger Details_Seat Pop-Up*

05.05 Passenger Details_Seat Pop-Up


The screenshot shows a mobile app interface for 'CONTACT DETAILS'. At the top is a teal header with a back arrow and the title 'CONTACT DETAILS'. Below the header, the text 'Let us know how to contact you and where to send your booking:' is displayed. Underneath is an 'Email' input field with a placeholder 'mike@oldtemplate.com' and an 'Edit' link. A white pop-up overlay is centered on the screen. The pop-up has a title 'Want to sit together?' and a subtitle 'If you skip seat selection, you'll be randomly assigned seats at check-in'. It contains two buttons: 'Select Seats' (teal) and 'Skip' (light pink). At the bottom of the screen is a large teal 'Continue' button. Three orange circles with lines pointing to them are used as callouts: one on the 'Select Seats' button, one on the 'Skip' button, and one on the 'Continue' button.

On selection, user is brought to:
06.01 Seat Selection

On selection, user is brought to:
07.01 Extras_Closed Panel

On selection anywhere on screen except pop-up, screen returns to previous state. See:
05.04 Passenger Details_Contact Details_Continue

06.01 Seat Selection



On selection, user is brought to:
07.01 Extras_Closed Panel

Passenger whose seat is currently being selected is highlighted.
-On selection of other name button, screen is set to select seats for new name

Dynamic chevron appears at bottom of viewport and disappears when user scrolls.

On selection, user is brought to:
07.01 Extras_Closed Panel

- On selection of chevron, pop-up appears of current cost breakdown.
-'Running total' updates on seat selection

On selection of desired seat, screen changes state. See:
06.02 Seat Selection (fixed screen position on transition)

On selection user is brought to:
05.04 Passenger Details_Contact Details_Continue

London

Istanbul

Your seat

Available

Unavailable

Extra Legroom

Yukie Mishima

Natsume Soseki

Yukie Mishima

Seat 25A

€7.00

Confirm

FRONT: €17 - €28

1

A

B

C

2

A

B

C

A

B

C

3

A

B

C

A

B

C

↑

RUNNING TOTAL €1147

Continue

5

A

B

C

A

B

C

6

A

B

C

A

B

C

7

A

B

C

A

B

C

8

A

B

C

A

B

C

9

A

B

C

A

B

C

10

A

B

C

A

B

C

11

A

B

C

A

B

C

STANDARD: €10

12

A

B

C

A

B

C

13

A

B

C

A

B

C

14

A

B

C

A

B

C

15

A

B

C

A

B

C

EXTRA LEGROOM: €28

16

STANDARD: €10

17

A

B

C

A

B

C

18

A

B

C

A

B

C

19

A

B

C

A

B

C

20

A

B

C

A

B

C

STANDARD: €7

21

A

B

C

A

B

C

22

A

B

C

A

B

C

23

A

B

C

A

B

C

24

A

B

C

A

B

C

25

A

B

C

26

A

B

C

A

B

C

27

A

B

C

A

B

C

28

A

B

C

A

B

C

29

A

B

C

A

B

C

30

A

B

C

A

B

C

31

A

B

C

A

B

C


06.03 Seat Selection

On selection of anywhere else on screen except pop-up, pop-up disappears

'Running Total' dynamically updates in accordance with seat selection

- Selected seat is displayed with teal background
- On selection of screen outside of pop-up and subsequent selection of new seat, teal disappears from original selection and appears on new selection

06.03 Seat Selection



SEAT SELECTION

London → Istanbul

Your seat Available Unavailable Extra Legroom

Yukie Mishima Natsume Soseki

Natsume Soseki Seat 25B €7.00

Confirm

FRONT: €17 - €20

1 2 3

4 5 6 7 8 9 10 11

RUNNING TOTAL: €1154 Continue

end of viewport

STANDARD: €10

EXTRA LEGROOM: €28

STANDARD: €10

STANDARD: €7


06.05 Seat Selection

On selection of anywhere else on screen except pop-up, pop-up disappears

'Running Total' dynamically updates in accordance with seat selection

- Selected seat is displayed with teal background
- On selection of screen outside of pop-up and subsequent selection of new seat, teal disappears from original selection and appears on new selection

06.05 Seat Selection



06.06 Seat Selection Summary

The screenshot shows a mobile app interface for 'SEAT SELECTION SUMMARY'. It features a list of flight segments with details on dates, directions, routes, and passenger fares. Each segment has an 'Edit' button. At the bottom, there is a 'Continue' button and a 'RUNNING TOTAL' of €1196. A dashed pink line indicates the 'end of viewport', and a vertical pink label on the left indicates the '<scrollable area'. Annotations with orange circles point to specific elements: the 'Edit' buttons for the first three segments, the 'Continue' button, and the 'Edit' button for the fourth segment. These annotations describe the user flow after selecting an option.

SEAT SELECTION SUMMARY

SAT 13 March 2021 Going Out Edit

✈ London Gatwick (LGW)
Istanbul (IST)

Yukie Mishima 25A €7.00
Natsume Soseki 26B €7.00

Total €14.00

SAT 13 March 2021 Going Out Edit

✈ Istanbul (IST)
Tokyo Haneda (HND)

Yukie Mishima 25A €7.00
Natsume Soseki 26B €7.00

Total €14.00

SAT 27 March 2021 Coming Back Edit

✈ Tokyo Haneda (LGW)
Istanbul (IST)

Yukie Mishima 25A €7.00
Natsume Soseki 26B €7.00

Total €14.00

end of viewport

RUNNING TOTAL €1196 Continue

SAT 27 March 2021 Coming Back Edit

✈ Istanbul (IST)
London Heathrow (LHR)

Yukie Mishima 25A €7.00
Natsume Soseki 26B €7.00

Total €14.00

<scrollable area

On selection, user is brought to: **06.06 Seat Selection**

On selection, user is brought to corresponding seat selection page.


On selection, user is brought to corresponding seat selection page.

On selection, user is brought to: **07.01 Extras_Closed Panels**

On selection, user is brought to corresponding seat selection page.

On selection, pop-up appears with detailed breakdown of 'Running Total'

07.01 Extras_Closed Panels



On selection, panel animates to expand to 'open' state - see: **07.02 Extras_Open Luggage** (transition 'ease in' - 0.4sec)

On selection, panel animates to 'open' state, with relevant particular information displayed. (transition 'ease in' - 0.4 sec)

On selection, user is brought to: **08.01 Payment_Final Summary**

On selection, pop-up appears with detailed breakdown of 'Running Total'

On selection, user is brought to: **06.06 Seat Selection Summary**

07.02 Extras_Open Luggage Panel

ADD EXTRAS

Extra Hold Luggage

Yukie Mishima

15kg Hold Bag
€20 per flight

25kg Hold Bag
€25 per flight

Nastume Soseki

15kg Hold Bag
€20 per flight

25kg Hold Bag
€25 per flight

Insure Your Trip

Special Assistance Request

Musical / Sports Equipment

RUNNING TOTAL €1236

Continue

On selection, panel animates to 'closed' state - see: **03.02 Flight Selection_Going Out_1** (transition 'ease in' - 0.4 sec)

- Number stepper preset at 0
- On selection of 'plus', number changes & 'Running Total' dynamically updates. Also, 'minus' turns 'grey' to 'green'

On selection, user is brought to: **08.01 Payment_Final Summary**

On selection, pop-up appears with detailed breakdown of 'Running Total'

'Running Total' dynamically updates with user's selection in number stepper.

07.01 Extras_Closed Panels

08.01 Payment_Final Summary


<

FLIGHT SUMMARY

SAT 13 March 2021

Going Out

Edit



London Gatwick (LGW)
Tokyo Haneda (HND)

Depart LGW

16:45

18h (1 stop) ⓘ


Arrive HND

19:45⁺¹

Adults x 2

€320


LGW -> IST



x 2


€7

IST -> HND




x 2

€7



15kg hold luggage x 2

€20




TOTAL €708

SAT 26 March 2021

Coming Back

Edit



Tokyo Haneda (HND)
London Heathrow (LHR)

Depart HND

16:45

18h (1 stop) ⓘ


Arrive LHR

19:45⁺¹

Adults x 2

€250


HND -> IST



x 2


€7

IST -> LHR




x 2

€7



15kg hold luggage x 2

€20



TOTAL €554

TOTAL PAYABLE

€1276

Continue to payment

- On selection, pop-up appears to let users decide what they wish to edit ie. flight, seats or extras
- Users are then brought to relevant page

On selection, pop-up appears with detailed info on lay-over.


- On selection, pop-up appears to let users decide what they wish to edit ie. flight, seats or extras
- Users are then brought to relevant page

On selection, pop-up appears with detailed info on lay-over.

On selection, user is brought to:
08.02 Payment_Contact Details Confirmation

On selection, user is brought to:
07.01 Extras Closed Panels

08.02 Payment_Contact Details Confirmation



08.03 Payment_Pay

< PAYMENT

Nearly on your way to Tokyo!

Enter your card details

VISA Mastercard

Payment amount:
€1276.00

Name on card: _____

Card Number: XXXX - XXXX - XXXX - XXXX

Expiry Date: MM / YY Security Code: XXXX

Pay €1276

By pressing the Pay button, you agree to our [terms](#)

Payment by **stripe**


On selection, QWERTY keypad pops-up and flashing cursor appears in form.

-On selection, numerical keypad pops up and flashing cursor appears in form.
-Error message appears if all forms are not filled.

-Error message appears if selected before all forms filled
- On selection, once all forms filled, user is brought to:
08.04 Payment_Processing


On selection, user is brought to:
08.02 Payment_Contact Details Confirmation

08.04 Payment_Processing



- Transition animation lasting 0.21 sec or while payment is processing.
- On successful payment, user is brought to:
08.05 Payment Confirmation

08.05 Payment Confirmation



On selection, pop-up appears with phone's native apps for 'share' options

On selection, user is brought to page with latest Covid-19 updates & rules in destinations served by airline