



# Cisco ASA 5520 sur GNS3

## Table des matières

1	Installer une image ASA .....	2
2	Installer une clé d'activation.....	10
3	Configuration Initiale du routeur .....	13
3.1	Topologie.....	13
3.2	Configuration .....	13

## 1 Installer une image ASA



New QEMU VM template ? X

**QEMU VM name**  
Please choose a descriptive name for your new QEMU virtual machine.

Name: ASA5520\_915

☒ This is a legacy ASA VM

< Back Next > Cancel



New QEMU VM template ? X

**QEMU binary and memory**  
Please check the Qemu binary is correctly set and the virtual machine has enough memory to work.

Qemu binary: /usr/bin/qemu-system-x86\_64 (v2.5.0)

RAM: 1024 MB

< Back Next > Cancel



Qemu image creator

**Binary and format**  
Please select a qemu-img binary, and the format for your new image.

Qemu-img binary: /usr/bin/qemu-img (v2.5.0)

Image format:

- ☐ Qcow2
- ☒ Qcow
- ☐ VHD
- ☐ VDI
- ☐ VMDK
- ☐ Raw

< Back   Next >   Cancel



Qemu image creator



**Size and location**

File location: ASA5520\_915-hda.qcow


Disk size: 30,000 MiB

< Back   Finish   Cancel






Changer la priorité à *Normal* dans le Template :







```
ASA5520_915-1
Cisco Systems, Inc.
170 West Tasman Drive
San Jose, California 95134-1706

config_fetcher: channel open failed
ERROR: MIGRATION - Could not get the startup configuration.

INFO: Power-On Self-Test in process.
.....
INFO: Power-On Self-Test complete.
COREDUMP UPDATE: open message queue fail: No such file or directory/2
COREDUMP UPDATE: unable to send coredump message to lina_monitor


INFO: MIGRATION - Saving the startup errors to file 'flash:upgrade_startup_errors_201612121412.log'
Pre-configure Firewall now through interactive prompts [yes]? no

Type help or '?' for a list of available commands.
ciscoasa> enable
Password:
ciscoasa#
```

## 2 Installer une clé d'activation

Avant :

```
ciscoasa# show version
```



```
ASA5520_915-1
Licensed features for this platform:
Maximum Physical Interfaces      : Unlimited      perpetual
Maximum VLANs                   : 100           perpetual
Inside Hosts                    : Unlimited      perpetual
Failover                        : Disabled       perpetual
Encryption-DES                  : Disabled       perpetual
Encryption-3DES-AES             : Disabled       perpetual
Security Contexts               : 0             perpetual
GTP/GPRS                        : Disabled       perpetual
AnyConnect Premium Peers        : 5000          perpetual
AnyConnect Essentials           : Disabled       perpetual
Other VPN Peers                 : 5000          perpetual
Total VPN Peers                 : 0             perpetual
Shared License                  : Disabled       perpetual
AnyConnect for Mobile           : Disabled       perpetual
AnyConnect for Cisco VPN Phone  : Disabled       perpetual
Advanced Endpoint Assessment     : Disabled       perpetual
UC Phone Proxy Sessions         : 2             perpetual
Total UC Proxy Sessions         : 2             perpetual
Botnet Traffic Filter           : Disabled       perpetual
Intercompany Media Engine       : Disabled       perpetual
Cluster                        : Disabled       perpetual
<--- More --->
```

## Installer la clé d'activation

```
ciscoasa# activation-key 0x953ac945 0x80a5a4eb 0xa1a0e4d8
0xd56484d4 0x8e14dabe

Validating activation key. This may take a few minutes...
Failed to retrieve permanent activation key.
Failover is different.
    running permanent activation key: Restricted(R)
    new permanent activation key: Unrestricted(UR)
WARNING:
The running activation key was not updated with the requested key.
Proceed with update flash activation key? [confirm]
The flash permanent activation key was updated with the requested
key,
and will become active after the next reload.
```

```
ciscoasa# reload
Proceed with reload? [confirm]
ciscoasa#

***
*** --- START GRACEFUL SHUTDOWN ---
Shutting down isakmp
Shutting down License Controller
Shutting down File system
```

Après :

```
ciscoasa# show version
```

Licensed features for this platform:

Maximum Physical Interfaces	: Unlimited	perpetual
Maximum VLANs	: 100	perpetual
Inside Hosts	: Unlimited	perpetual
Failover	: Active/Active	perpetual
Encryption-DES	: Enabled	perpetual
Encryption-3DES-AES	: Enabled	perpetual
Security Contexts	: 20	perpetual
GTP/GPRS	: Disabled	perpetual
AnyConnect Premium Peers	: 1000	perpetual
AnyConnect Essentials	: 10000	perpetual
Other VPN Peers	: 5000	perpetual
Total VPN Peers	: 0	perpetual
Shared License	: Enabled	perpetual
AnyConnect for Mobile	: Enabled	perpetual
AnyConnect for Cisco VPN Phone	: Enabled	perpetual
Advanced Endpoint Assessment	: Enabled	perpetual
UC Phone Proxy Sessions	: 1000	perpetual
Total UC Proxy Sessions	: 1000	perpetual
Botnet Traffic Filter	: Enabled	perpetual
Intercompany Media Engine	: Disabled	perpetual
Cluster	: Disabled	perpetual

Afficher la clé d'activation


```
ciscoasa# show activation-key
```

Serial Number: JHX000000000

Running Permanent Activation Key: 0x953ac945 0x80a5a4eb 0xa1a0e4d8  
0xd56484d4 0x8e14dabe

### 3 Configuration Initiale du routeur

#### 3.1 Topologie



#### 3.2 Configuration

```
interface GigabitEthernet0
 nameif INSIDE
 security-level 100
 ip address dhcp

interface GigabitEthernet1
 nameif OUTSIDE
 security-level 0
 ip address 192.168.1.1 255.255.255.0

http server enable
http 192.168.137.0 255.255.255.0 INSIDE
http 192.168.124.0 255.255.255.0 INSIDE
```