

Octave Name	MIDI Octave	MIDI Note Number	Note Name	Function	Player
--	-5	0	C	Play / Stop	1
--	-5	1	C#/Db	Play / Stop	2
--	-5	2	D	Play / Stop	3
--	-5	3	D#/Eb	Play / Stop	4
--	-5	4	E	Play / Stop	5
--	-5	5	F	Play / Stop	6
--	-5	6	F#/Gb	Play / Stop	7
--	-5	7	G	Play / Stop	8
--	-5	8	G#/Ab	Play / Stop	9
--	-5	9	A	Play / Stop	10
--	-5	10	A#/Bb	Play / Stop	11
--	-5	11	B	Play / Stop	12
--	-4	12	C	Play / Stop	13
--	-4	13	C#/Db	Play / Stop	14
--	-4	14	D	Play / Stop	15
--	-4	15	D#/Eb	Play / Stop	16
--	-4	16	E	Play / Stop	17
--	-4	17	F	Play / Stop	18
--	-4	18	F#/Gb	Play / Stop	19
--	-4	19	G	Play / Stop	20
--	-4	20	G#/Ab	Play / Stop	21
--	-4	21	A	Play / Stop	22
--	-4	22	A#/Bb	Play / Stop	23
--	-4	23	B	Play / Stop	24
--	-3	24	C	Play / Pause	1
--	-3	25	C#/Db	Play / Pause	2
--	-3	26	D	Play / Pause	3
--	-3	27	D#/Eb	Play / Pause	4
--	-3	28	E	Play / Pause	5
--	-3	29	F	Play / Pause	6
--	-3	30	F#/Gb	Play / Pause	7
Low	-3	31	G	Play / Pause	8
Low	-3	32	G#/Ab	Play / Pause	9
Low	-3	33	A	Play / Pause	10
Low	-3	34	A#/Bb	Play / Pause	11
Low	-3	35	B	Play / Pause	12
Low	-2	36	C	Play / Pause	13
Low	-2	37	C#/Db	Play / Pause	14
Low	-2	38	D	Play / Pause	15
Low	-2	39	D#/Eb	Play / Pause	16
Low	-2	40	E	Play / Pause	17
Low	-2	41	F	Play / Pause	18
Low	-2	42	F#/Gb	Play / Pause	19
Bass	-2	43	G	Play / Pause	20
Bass	-2	44	G#/Ab	Play / Pause	21
Bass	-2	45	A	Play / Pause	22
Bass	-2	46	A#/Bb	Play / Pause	23
Bass	-2	47	B	Play / Pause	24
Bass	-1	48	C	Play / Fade-Out	1
Bass	-1	49	C#/Db	Play / Fade-Out	2
Bass	-1	50	D	Play / Fade-Out	3
Bass	-1	51	D#/Eb	Play / Fade-Out	4
Bass	-1	52	E	Play / Fade-Out	5
Bass	-1	53	F	Play / Fade-Out	6
Bass	-1	54	F#/Gb	Play / Fade-Out	7
Middle	-1	55	G	Play / Fade-Out	8
Middle	-1	56	G#/Ab	Play / Fade-Out	9
Middle	-1	57	A	Play / Fade-Out	10
Middle	-1	58	A#/Bb	Play / Fade-Out	11
Middle	-1	59	B	Play / Fade-Out	12
Middle	0	60	C	Play / Fade-Out	13
Middle	0	61	C#/Db	Play / Fade-Out	14
Middle	0	62	D	Play / Fade-Out	15
Middle	0	63	D#/Eb	Play / Fade-Out	16
Middle	0	64	E	Play / Fade-Out	17
Middle	0	65	F	Play / Fade-Out	18
Treble	0	66	F#/Gb	Play / Fade-Out	19
Treble	0	67	G	Play / Fade-Out	20
Treble	0	68	G#/Ab	Play / Fade-Out	21
Treble	0	69	A	Play / Fade-Out	22
Treble	0	70	A#/Bb	Play / Fade-Out	23
Treble	0	71	B	Play / Fade-Out	24
Treble	1	72	C	Hold & Play	1
Treble	1	73	C#/Db	Hold & Play	2
Treble	1	74	D	Hold & Play	3
Treble	1	75	D#/Eb	Hold & Play	4
Treble	1	76	E	Hold & Play	5
Treble	1	77	F	Hold & Play	6
High	1	78	F#/Gb	Hold & Play	7
High	1	79	G	Hold & Play	8
High	1	80	G#/Ab	Hold & Play	9
High	1	81	A	Hold & Play	10
High	1	82	A#/Bb	Hold & Play	11
High	1	83	B	Hold & Play	12
High	2	84	C	Hold & Play	13
High	2	85	C#/Db	Hold & Play	14
High	2	86	D	Hold & Play	15
High	2	87	D#/Eb	Hold & Play	16
High	2	88	E	Hold & Play	17
High	2	89	F	Hold & Play	18
--	2	90	F#/Gb	Hold & Play	19
--	2	91	G	Hold & Play	20
--	2	92	G#/Ab	Hold & Play	21
--	2	93	A	Hold & Play	22
--	2	94	A#/Bb	Hold & Play	23
--	2	95	B	Hold & Play	24
--	3	96	C	-	
--	3	97	C#/Db	-	
--	3	98	D	-	
--	3	99	D#/Eb	-	
--	3	100	E	-	
--	3	101	F	-	
--	3	102	F#/Gb	-	
--	3	103	G	-	
--	3	104	G#/Ab	-	
--	3	105	A	-	
--	3	106	A#/Bb	-	
--	3	107	B	-	
--	4	108	C	-	
--	4	109	C#/Db	-	
--	4	110	D	-	
--	4	111	D#/Eb	-	
--	4	112	E	-	
--	4	113	F	-	
--	4	114	F#/Gb	-	
--	4	115	G	-	
--	4	116	G#/Ab	-	
--	4	117	A	-	
--	4	118	A#/Bb	-	
--	4	119	B	-	
--	5	120	C	-	
--	5	121	C#/Db	-	
--	5	122	D	-	
--	5	123	D#/Eb	-	
--	5	124	E	-	
--	5	125	F	-	
--	5	126	F#/Gb	-	
--	5	127	G	-	

**Play / Stop:** Durch drücken dieser Taste wird der Player abgespielt. Bei erneutem drücken wird dieser wieder Gestoppt.

**Play / Pause:** Durch drücken dieser Taste wird der Player abgespielt. Bei erneutem drücken wird dieser in den Pausemodus versetzt.

**Play / Fade-Out:** Durch drücken dieser Taste wird der Player abgespielt. Bei erneutem drücken wird dieser Aufgeblendet.

**Hold & Play:** Solange die Taste gedrückt wird der Player abgespielt.