

--- System Configuration Dialog ---

Would you like to enter the initial configuration dialog? [yes/no]: no

Press RETURN to get started!

Router>enable

Router#show running-config

Building configuration...

Current configuration : 686 bytes

!

version 12.2

no service timestamps log datetime msec

no service timestamps debug datetime msec

no service password-encryption

!

hostname Router

!

!

!

!

!

!

!

!

ip cef

no ipv6 cef

!

!

!

!

!

!

!

!

!

!

!

!

!

!

!

!

!

!

interface FastEthernet0/0

no ip address

duplex auto

```
speed auto
shutdown
!
interface FastEthernet1/0
no ip address
duplex auto
speed auto
shutdown
!
interface Serial2/0
no ip address
shutdown
!
interface Serial3/0
no ip address
shutdown
!
interface FastEthernet4/0
no ip address
shutdown
!
interface FastEthernet5/0
no ip address
shutdown
!
ip classless
!
ip flow-export version 9
!
!
!
!
!
!
!
!
line con 0
!
line aux 0
!
line vty 0 4
login
!
!
!
end
```

Router#config terminal

Enter configuration commands, one per line. End with CNTL/Z.

Router(config)#hostname R1

```
R1(config)#banner motd #Unauthorized access to this device is prohibited!#
R1(config)#enable password cisco
R1(config)#enable secret itsasecret
R1(config)#line console 0
R1(config-line)#password letmein
R1(config-line)#login
R1(config-line)#service password-encryption
R1(config)#^Z
R1#
%SYS-5-CONFIG_I: Configured from console by console
```

```
R1#copy running-config startup-config
Destination filename [startup-config]?
Building configuration...
[OK]
R1#exit
```

R1 con0 is now available

Press RETURN to get started.

Unauthorized access to this device is prohibited!

User Access Verification

Password:

R1>enable

Password:

Password:

R1#enable

R1#config terminal

Enter configuration commands, one per line. End with CNTL/Z.

R1(config)#hostname R1

R1(config)#interface SerialR1(config)#% Bad secrets

R1(config)#interface Serial2/0

R1(config-if)#ip address 192.100.100.1 255.255.255.0

R1(config-if)#clock rate 64000

R1(config-if)#no shutdown

%LINK-5-CHANGED: Interface Serial2/0, changed state to down

--- System Configuration Dialog ---

Would you like to enter the initial configuration dialog? [yes/no]: no

Press RETURN to get started!



```
speed auto
shutdown
!
interface Serial2/0
no ip address
shutdown
!
interface Serial3/0
no ip address
shutdown
!
interface FastEthernet4/0
no ip address
shutdown
!
interface FastEthernet5/0
no ip address
shutdown
!
ip classless
!
ip flow-export version 9
!
!
!
!
!
!
!
!
line con 0
!
line aux 0
!
line vty 0 4
login
!
!
!
end
```

Router#config terminal

Enter configuration commands, one per line. End with CNTL/Z.

Router(config)#hostname R2

R2(config)#banner motd #Unauthorized access to this device is prohibited!#

R2(config)#enable password cisco

R2(config)#enable secret itsasecret

R2(config)#line console 0

R2(config-line)#password letmein

R2(config-line)#login

```
R2(config-line)#service password-encryption
R2(config)#^Z
R2#
%SYS-5-CONFIG_I: Configured from console by console
```

```
R2#copy running-config startup-config
Destination filename [startup-config]?
Building configuration...
[OK]
R2#exit
```

R2 con0 is now available

Press RETURN to get started.

Unauthorized access to this device is prohibited!

User Access Verification

Password:

R2>enable

Password:

Password:

R2#enable

R2#config terminal

Enter configuration commands, one per line. End with CNTL/Z.

R2(config)#hostname R2

R2(config)#interface SerialR2(config)#% Bad secrets

R2(config)#interface Serial2/0

R2(config-if)#ip address 192.100.100.2 255.255.255.0

R2(config-if)#clock rate 64000

R2(config-if)#no shutdown

%LINK-5-CHANGED: Interface Serial2/0, changed state to down