



[ECCO-2] The “Women“ radiobutton isn’t selected in the “Gender“ field on the create account page by the keyboard navigation after pressing the Enter key. Created:

19/септ./23 Updated: 21/септ./23

Status:	To Do
Project:	ECCO
Components:	None
Affects versions:	None
Fix versions:	None

Type:	Bug	Priority:	Medium
Reporter:	Viktoriya	Assignee:	Unassigned
Resolution:	Unresolved	Votes:	0
Labels:	None		
Remaining Estimate:	Not Specified		
Time Spent:	Not Specified		
Original estimate:	Not Specified		

Attachments:	 bandicam 2023-08-19 22-26-09-427.mp4  bandicam 2023-08-19 22-30-00-388.png
Rank:	0 i0003r:
Sprint:	Accessibility Sprint

Description

Precondition: The website <https://gb.ecco.com/> is opened. The keyboard is used for navigation. The "Create ECCO account" page is opened.

Steps to reproduce:

1. Press the Tab key twenty four times to navigate to the “First name“ field.
2. Fill the “First name“ field with valid data and press Tab key.
3. Fill the “Last name“ field with valid data and press Tab key.
4. Fill the “Email“ field with valid data and press Tab key.
5. Fill the “Password“ field with valid data and press Tab key.
6. Fill the “Confirm password“ field with valid data and press Tab key.
7. Press Tab key one more time.
8. Press Enter key.
9. Look at the “Gender“ field.
10. Pay attention to the “Women“ and “Man“ radiobuttons.

Actual result: The “Women“ radiobutton isn’t selected in the “Gender“ field on the create account page by the keyboard navigation after pressing the Enter key.

Expected result: The “Women“ radiobutton is displayed as selected in the “Gender“ field on the create account page by the keyboard navigation after pressing the Enter key.

Additional information: The same bug is reproduced in the “Accept terms” field after selecting the “I accept...” checkbox.

Windows 10, Chrom 116.0.5845.96.

Generated at Wed Aug 23 21:28:36 UTC 2023 by Viktoriya using Jira 1001.0.0-SNAPSHOT#100234-sha1:0a0107a1b65ca072f19b363cb42c6868f92bf5b3.

My ECCO - Create new customer x +

gb.ecco.com/en-GB/My-ECCO/Register

FREE DELIVERY AND EASY RETURNS

ecco NEW WOMEN MEN KIDS OUTDOOR GOLF OFFERS LEATHER GOODS CRAFTSMANSHIP

MY ECCO > REGISTER NEED HELP? FIND A STORE EN

CREATE ECCO ACCOUNT

First name *

Wika ✓

Last name *

123 ✓

Email *

sfsdfsdfsdfs@gmail.com ✓

Password *

..... ✓

Confirm password *

..... ✓

Gender

☐ Women

☐ Man

Accept terms *

☐ I accept that a MY ECCO account will be created for me. I can delete it all times and read about MY ECCO and my consent. Read terms [here](#).

Create account now

Get a quick answer ?