

RTVoice

2.5.0

Generated by Doxygen 1.8.11

Contents

1	Namespace Index	1
1.1	Packages	1
2	Hierarchical Index	3
2.1	Class Hierarchy	3
3	Class Index	5
3.1	Class List	5
4	Namespace Documentation	9
4.1	Crosstales Namespace Reference	9
4.2	Crosstales.RTVoice Namespace Reference	9
4.3	Crosstales.RTVoice.AdventureCreator Namespace Reference	9
4.4	Crosstales.RTVoice.Demo Namespace Reference	10
4.5	Crosstales.RTVoice.Demo.Util Namespace Reference	10
4.5.1	Enumeration Type Documentation	11
4.5.1.1	Platform	11
4.6	Crosstales.RTVoice.EditorExt Namespace Reference	11
4.7	Crosstales.RTVoice.Model Namespace Reference	12
4.7.1	Enumeration Type Documentation	12
4.7.1.1	SpeakMode	12
4.8	Crosstales.RTVoice.Model.Event Namespace Reference	12
4.9	Crosstales.RTVoice.PlayMaker Namespace Reference	13
4.10	Crosstales.RTVoice.Provider Namespace Reference	13
4.11	Crosstales.RTVoice.SALSA Namespace Reference	13
4.12	Crosstales.RTVoice.SLATE Namespace Reference	13
4.13	Crosstales.RTVoice.Tool Namespace Reference	13
4.14	Crosstales.RTVoice.UDEA2 Namespace Reference	14
4.15	Crosstales.RTVoice.Util Namespace Reference	14
4.16	HutongGames Namespace Reference	14
4.17	HutongGames.PlayMaker Namespace Reference	14
4.18	HutongGames.PlayMaker.Actions Namespace Reference	14
4.19	PixelCrushers Namespace Reference	15
4.20	PixelCrushers.DialogueSystem Namespace Reference	15
4.21	PixelCrushers.DialogueSystem.SequencerCommands Namespace Reference	15

5	Class Documentation	17
5.1	Crosstales.RTVoice.AdventureCreator.ACConnector Class Reference	17
5.1.1	Detailed Description	17
5.1.2	Member Data Documentation	17
5.1.2.1	CallOnStopSpeech	17
5.1.2.2	Culture	18
5.1.2.3	SimulateSkipSpeech	18
5.1.2.4	Voices	18
5.2	Crosstales.RTVoice.AdventureCreator.ACConnectorEditor Class Reference	18
5.2.1	Detailed Description	18
5.3	Crosstales.RTVoice.AdventureCreator.ACConnectorMenu Class Reference	18
5.3.1	Detailed Description	19
5.4	Crosstales.RTVoice.AdventureCreator.ACSwitcher Class Reference	19
5.4.1	Detailed Description	19
5.5	Crosstales.RTVoice.AdventureCreator.ACVoiceWrapper Class Reference	19
5.5.1	Detailed Description	20
5.5.2	Member Data Documentation	20
5.5.2.1	ACVoiceName	20
5.5.2.2	IgnoreCharacter	20
5.5.2.3	Pitch	21
5.5.2.4	Rate	21
5.5.2.5	RTVoiceNameAndroid	21
5.5.2.6	RTVoiceNameIOS	21
5.5.2.7	RTVoiceNameMac	21
5.5.2.8	RTVoiceNameWindows	21
5.5.2.9	Source	21
5.5.2.10	UseSpeechAudioSource	21
5.5.2.11	Volume	21
5.5.3	Property Documentation	22
5.5.3.1	RTVoiceName	22

5.6	Crosstales.RTVoice.Demo.Util.AudioVisualizer Class Reference	22
5.6.1	Detailed Description	22
5.7	Crosstales.RTVoice.EditorExt.AutoInitalize Class Reference	22
5.7.1	Detailed Description	23
5.8	Crosstales.RTVoice.Provider.BaseVoiceProvider Class Reference	23
5.8.1	Detailed Description	25
5.8.2	Member Function Documentation	25
5.8.2.1	Silence()	25
5.8.2.2	Silence(Guid uid)	25
5.8.2.3	Speak(Wrapper wrapper)	25
5.8.2.4	SpeakNative(WrapperNative wrapper)	25
5.8.3	Property Documentation	26
5.8.3.1	AudioFileExtension	26
5.8.3.2	Voices	26
5.8.4	Event Documentation	26
5.8.4.1	OnErrorInfo	26
5.8.4.2	OnSpeakAudioGenerationComplete	26
5.8.4.3	OnSpeakAudioGenerationStart	26
5.8.4.4	OnSpeakComplete	26
5.8.4.5	OnSpeakNativeComplete	26
5.8.4.6	OnSpeakNativeCurrentPhoneme	27
5.8.4.7	OnSpeakNativeCurrentViseme	27
5.8.4.8	OnSpeakNativeCurrentWord	27
5.8.4.9	OnSpeakNativeStart	27
5.8.4.10	OnSpeakStart	27
5.9	Crosstales.RTVoice.EditorExt.BuildPostprocessor Class Reference	27
5.9.1	Detailed Description	27
5.10	Crosstales.RTVoice.EditorExt.ConfigBase Class Reference	28
5.10.1	Detailed Description	28
5.11	Crosstales.RTVoice.EditorExt.ConfigLoader Class Reference	28

5.11.1 Detailed Description	28
5.12 Crosstales.RTVoice.EditorExt.ConfigPreferences Class Reference	29
5.12.1 Detailed Description	29
5.13 Crosstales.RTVoice.EditorExt.ConfigWindow Class Reference	29
5.13.1 Detailed Description	30
5.14 Crosstales.RTVoice.Util.Constants Class Reference	30
5.14.1 Detailed Description	32
5.14.2 Member Data Documentation	32
5.14.2.1 ASSET_API_URL	32
5.14.2.2 ASSET_AUTHOR	32
5.14.2.3 ASSET_AUTHOR_URL	32
5.14.2.4 ASSET_BUILD	32
5.14.2.5 ASSET_CHANGED	32
5.14.2.6 ASSET_CONTACT	32
5.14.2.7 ASSET_CREATED	32
5.14.2.8 ASSET_CT_URL	32
5.14.2.9 ASSET_FORUM_URL	32
5.14.2.10 ASSET_MANUAL_URL	33
5.14.2.11 ASSET_NAME	33
5.14.2.12 ASSET_UID	33
5.14.2.13 ASSET_UPDATE_CHECK_URL	33
5.14.2.14 ASSET_URL	33
5.14.2.15 ASSET_VERSION	33
5.14.2.16 AUDIOFILE_AUTOMATIC_DELETE	33
5.14.2.17 AUDIOFILE_PATH	33
5.14.2.18 DEBUG	33
5.14.2.19 ENFORCE_32BIT_WINDOWS	33
5.14.2.20 PREFAB_AUTOLOAD	34
5.14.2.21 PREFAB_PATH	34
5.14.2.22 RTVOICE_SCENE_OBJECT_NAME	34

5.14.2.23 TTS_KILL_TIME	34
5.14.2.24 TTS_MACOS	34
5.14.2.25 TTS_WINDOWS_BUILD	34
5.14.2.26 TTS_WINDOWS_BUILD_x86	34
5.14.2.27 TTS_WINDOWS_EDITOR	34
5.14.2.28 TTS_WINDOWS_EDITOR_x86	34
5.14.2.29 UPDATE_CHECK	34
5.14.2.30 UPDATE_OPEN_UAS	35
5.15 Crosstales.RTVoice.Model.Event.CurrentPhonemeEventArgs Class Reference	35
5.15.1 Detailed Description	35
5.15.2 Member Data Documentation	35
5.15.2.1 Phoneme	35
5.16 Crosstales.RTVoice.Model.Event.CurrentVisemeEventArgs Class Reference	36
5.16.1 Detailed Description	36
5.16.2 Member Data Documentation	36
5.16.2.1 Viseme	36
5.17 Crosstales.RTVoice.Model.Event.CurrentWordEventArgs Class Reference	36
5.17.1 Detailed Description	37
5.17.2 Member Data Documentation	37
5.17.2.1 SpeechTextArray	37
5.17.2.2 WordIndex	37
5.18 Crosstales.RTVoice.SLATE.CutSceneStart Class Reference	37
5.19 Crosstales.RTVoice.Demo.Dialog Class Reference	38
5.19.1 Detailed Description	38
5.20 Crosstales.RTVoice.EditorExt.EditorHelper Class Reference	38
5.20.1 Detailed Description	39
5.20.2 Member Function Documentation	39
5.20.2.1 AddRTVoice()	39
5.20.2.2 NoVoicesUI()	39
5.20.2.3 SeparatorUI(int space=20)	39

5.20.3	Member Data Documentation	39
5.20.3.1	MENU_ID	39
5.20.4	Property Documentation	40
5.20.4.1	isRTVoiceInScene	40
5.21	Crosstales.RTVoice.Demo.FFTAnalyzer Class Reference	40
5.21.1	Detailed Description	40
5.22	Crosstales.RTVoice.Demo.GUIAudioFilter Class Reference	41
5.22.1	Detailed Description	41
5.23	Crosstales.RTVoice.Demo.GUIDialog Class Reference	42
5.23.1	Detailed Description	42
5.24	Crosstales.RTVoice.Demo.GUIMain Class Reference	42
5.24.1	Detailed Description	43
5.25	Crosstales.RTVoice.Demo.GUIMultiAudioFilter Class Reference	43
5.25.1	Detailed Description	44
5.26	Crosstales.RTVoice.Demo.GUIScenes Class Reference	44
5.26.1	Detailed Description	45
5.27	Crosstales.RTVoice.Demo.GUISpeech Class Reference	45
5.27.1	Detailed Description	46
5.28	Crosstales.RTVoice.Demo.GUISpeechMobile Class Reference	46
5.28.1	Detailed Description	47
5.29	Crosstales.RTVoice.Util.Helper Class Reference	47
5.29.1	Detailed Description	48
5.29.2	Member Function Documentation	48
5.29.2.1	CleanText(string text, bool removePunctuation=true)	48
5.29.2.2	ClearSpaces(string text)	48
5.29.2.3	CTDump< T >(this T[] array)	48
5.29.2.4	CTDump< T >(this List< T > list)	49
5.29.2.5	HSVToRGB(float h, float s, float v, float a=1f)	49
5.29.2.6	MarkSpokenText(string[] speechTextArray, int wordIndex, bool markAll↵ SpokenWords=false, string markPrefix=""< color=green>"", string mark↵ Postfix=""< /color>"")	49

5.29.2.7	SplitStringToLines(string text)	50
5.29.2.8	ValidatePath(string path)	50
5.29.3	Property Documentation	50
5.29.3.1	isAndroidPlatform	50
5.29.3.2	isEditorMode	50
5.29.3.3	isIOSPlatform	51
5.29.3.4	isMacOSPlatform	51
5.29.3.5	isSupportedPlatform	51
5.29.3.6	isWindowsPlatform	51
5.30	Crosstales.RTVoice.LiveSpeaker Class Reference	51
5.30.1	Detailed Description	52
5.30.2	Member Function Documentation	52
5.30.2.1	Silence()	52
5.30.2.2	Speak(Wrapper wrapper)	52
5.30.2.3	Speak(string args)	52
5.30.2.4	Speak(string[] args)	53
5.30.2.5	SpeakNative(WrapperNative wrapper)	53
5.30.2.6	SpeakNative(string args)	53
5.30.2.7	SpeakNative(string[] args)	53
5.31	Crosstales.RTVoice.Tool.Loudspeaker Class Reference	53
5.31.1	Detailed Description	54
5.31.2	Member Data Documentation	54
5.31.2.1	SilenceSource	54
5.31.2.2	Source	54
5.31.2.3	Synchronized	54
5.32	Crosstales.RTVoice.Demo.Util.MaterialChanger Class Reference	55
5.32.1	Detailed Description	55
5.33	Crosstales.RTVoice.Demo.NativeAudio Class Reference	55
5.33.1	Detailed Description	56
5.34	Crosstales.RTVoice.Demo.NativeDisabler Class Reference	56

5.35	Crosstales.RTVoice.Demo.Util.PlatformEnabler Class Reference	56
5.35.1	Detailed Description	57
5.36	Crosstales.RTVoice.Demo.PreGeneratedAudio Class Reference	57
5.36.1	Detailed Description	57
5.37	Crosstales.RTVoice.Demo.Util.RandomColor Class Reference	58
5.37.1	Detailed Description	58
5.38	Crosstales.RTVoice.Demo.Util.RandomRotator Class Reference	58
5.38.1	Detailed Description	58
5.39	Crosstales.RTVoice.Demo.Util.RandomScaler Class Reference	59
5.39.1	Detailed Description	59
5.40	PixelCrushers.DialogueSystem.RTVoiceActor Class Reference	59
5.40.1	Member Function Documentation	60
5.40.1.1	GetVoice()	60
5.40.1.2	OnBarkLine(Subtitle subtitle)	60
5.40.1.3	OnConversationLine(Subtitle subtitle)	61
5.40.1.4	Speak(string text)	61
5.40.2	Member Data Documentation	61
5.40.2.1	voicePreferences	61
5.40.2.2	waitForVoiceInConversations	61
5.41	RTVoiceIOSBridge Class Reference	61
5.41.1	Method Documentation	62
5.41.1.1	setVoices()	62
5.41.1.2	speak:rate:pitch:volume:culture:(NSString *text,[rate] float rate,[pitch] float pitch,[volume] float volume,[culture] NSString *culture)	62
5.41.1.3	stop()	62
5.42	RTVoiceIOSBridge() Category Reference	62
5.43	Crosstales.RTVoice.EditorExt.RTVoiceMenu Class Reference	63
5.43.1	Detailed Description	63
5.44	Crosstales.RTVoice.Demo.Util.ScrollRectHandler Class Reference	63
5.44.1	Detailed Description	63
5.45	Crosstales.RTVoice.Demo.SendMessage Class Reference	63

5.45.1 Detailed Description	64
5.46 Crosstales.RTVoice.Model.Sequence Class Reference	64
5.46.1 Detailed Description	65
5.46.2 Member Data Documentation	65
5.46.2.1 Mode	65
5.46.2.2 Pitch	65
5.46.2.3 Rate	65
5.46.2.4 RTVoiceNameAndroid	65
5.46.2.5 RTVoiceNameIOS	65
5.46.2.6 RTVoiceNameMac	65
5.46.2.7 RTVoiceNameWindows	65
5.46.2.8 Source	65
5.46.2.9 Text	66
5.46.2.10 Volume	66
5.46.3 Property Documentation	66
5.46.3.1 RTVoiceName	66
5.47 Crosstales.RTVoice.Demo.SequenceCaller Class Reference	66
5.47.1 Detailed Description	66
5.48 Crosstales.RTVoice.Tool.Sequencer Class Reference	67
5.48.1 Detailed Description	67
5.48.2 Member Function Documentation	67
5.48.2.1 PlayAllSequences()	67
5.48.2.2 PlayNextSequence()	68
5.48.2.3 PlaySequence(int index=0)	68
5.48.2.4 StopAllSequences()	68
5.48.3 Member Data Documentation	68
5.48.3.1 Culture	68
5.48.3.2 Delay	68
5.48.3.3 PlayOnStart	68
5.48.3.4 Sequences	68

5.48.4	Property Documentation	68
5.48.4.1	CurrentSequence	68
5.49	PixelCrushers.DialogueSystem.SequencerCommands.SequencerCommandRTVoiceWait Class Reference	69
5.49.1	Detailed Description	69
5.50	Crosstales.RTVoice.EditorExt.SequencerEditor Class Reference	69
5.50.1	Detailed Description	70
5.51	HutongGames.PlayMaker.Actions.Silence Class Reference	70
5.51.1	Detailed Description	70
5.52	Crosstales.RTVoice.Demo.Simple Class Reference	70
5.52.1	Detailed Description	71
5.53	Crosstales.RTVoice.Demo.SimpleNative Class Reference	71
5.53.1	Detailed Description	72
5.54	HutongGames.PlayMaker.Actions.Speak Class Reference	72
5.54.1	Detailed Description	73
5.54.2	Member Data Documentation	73
5.54.2.1	Culture	73
5.54.2.2	RTVoiceNameAndroid	73
5.54.2.3	RTVoiceNameIOS	73
5.54.2.4	RTVoiceNameMac	73
5.54.2.5	RTVoiceNameWindows	73
5.54.2.6	Text	74
5.55	Crosstales.RTVoice.SALSA.Speak Class Reference	74
5.56	HutongGames.PlayMaker.Actions.SpeakBase Class Reference	74
5.56.1	Detailed Description	75
5.56.2	Member Data Documentation	75
5.56.2.1	AudioSource	75
5.56.2.2	Mode	75
5.56.2.3	Pitch	75
5.56.2.4	Rate	76
5.56.2.5	Volume	76

5.57 Crosstales.RTVoice.PlayMaker.SpeakEditor Class Reference	76
5.57.1 Detailed Description	76
5.58 Crosstales.RTVoice.Speaker Class Reference	76
5.58.1 Detailed Description	78
5.58.2 Member Function Documentation	78
5.58.2.1 ApproximateSpeechLength(string text, float rate=1f, float wordsPerMinute=175f, float timeFactor=0.9f)	78
5.58.2.2 Silence()	79
5.58.2.3 Silence(Guid uid)	79
5.58.2.4 Speak(string text, AudioSource source=null, Voice voice=null, bool speak↔ Immediately=true, float rate=1f, float volume=1f, string outputFile="","", float pitch=1f)	79
5.58.2.5 Speak(Wrapper wrapper)	80
5.58.2.6 SpeakMarkedWordsWithUID(Guid uid, string text, AudioSource source, Voice voice=null, float rate=1f, float pitch=1f)	80
5.58.2.7 SpeakNative(string text, Voice voice=null, float rate=1f, float volume=1f, float pitch=1f)	80
5.58.2.8 SpeakNative(WrapperNative wrapper)	81
5.58.2.9 SpeakNativeWithUID(WrapperNative wrapper)	81
5.58.2.10 SpeakWithUID(Wrapper wrapper)	81
5.58.2.11 VoiceForCulture(string culture, int index=0)	81
5.58.2.12 VoiceForName(string name)	81
5.58.2.13 VoicesForCulture(string culture)	82
5.58.3 Property Documentation	82
5.58.3.1 AudioFileExtension	82
5.58.3.2 Cultures	82
5.58.3.3 isTTSAvailable	82
5.58.3.4 Voices	83
5.58.4 Event Documentation	83
5.58.4.1 OnErrorInfo	83
5.58.4.2 OnSpeakAudioGenerationComplete	83
5.58.4.3 OnSpeakAudioGenerationStart	83
5.58.4.4 OnSpeakComplete	83

5.58.4.5	OnSpeakNativeComplete	83
5.58.4.6	OnSpeakNativeCurrentPhoneme	83
5.58.4.7	OnSpeakNativeCurrentViseme	83
5.58.4.8	OnSpeakNativeCurrentWord	83
5.58.4.9	OnSpeakNativeStart	84
5.58.4.10	OnSpeakStart	84
5.59	Crosstales.RTVoice.EditorExt.SpeakerEditor Class Reference	84
5.59.1	Detailed Description	84
5.60	Crosstales.RTVoice.Model.Event.SpeakEventArgs Class Reference	84
5.60.1	Detailed Description	85
5.60.2	Member Data Documentation	85
5.60.2.1	Wrapper	85
5.61	Crosstales.RTVoice.Model.Event.SpeakNativeEventArgs Class Reference	85
5.61.1	Detailed Description	86
5.61.2	Member Data Documentation	86
5.61.2.1	Wrapper	86
5.62	HutongGames.PlayMaker.Actions.SpeakUI Class Reference	86
5.62.1	Detailed Description	86
5.62.2	Member Data Documentation	87
5.62.2.1	Culture	87
5.62.2.2	RTVoiceName	87
5.62.2.3	Text	87
5.63	Crosstales.RTVoice.PlayMaker.SpeakUIEditor Class Reference	87
5.63.1	Detailed Description	87
5.64	Crosstales.RTVoice.Demo.SpeakWrapper Class Reference	88
5.64.1	Detailed Description	88
5.65	Crosstales.RTVoice.Tool.SpeechText Class Reference	88
5.65.1	Detailed Description	89
5.65.2	Member Data Documentation	90
5.65.2.1	Culture	90

5.65.2.2	FileInsideAssets	90
5.65.2.3	FileName	90
5.65.2.4	FilePath	90
5.65.2.5	GenerateAudioFile	90
5.65.2.6	Mode	90
5.65.2.7	Pitch	90
5.65.2.8	PlayOnStart	90
5.65.2.9	Rate	90
5.65.2.10	RTVoiceNameAndroid	90
5.65.2.11	RTVoiceNameIOS	91
5.65.2.12	RTVoiceNameMac	91
5.65.2.13	RTVoiceNameWindows	91
5.65.2.14	Source	91
5.65.2.15	Text	91
5.65.2.16	Volume	91
5.65.3	Property Documentation	91
5.65.3.1	RTVoiceName	91
5.66	Crosstales.RTVoice.EditorExt.SpeechTextEditor Class Reference	91
5.66.1	Detailed Description	92
5.67	Crosstales.RTVoice.UDEA2.UDEAConnector Class Reference	92
5.67.1	Detailed Description	92
5.67.2	Member Data Documentation	92
5.67.2.1	Culture	92
5.67.2.2	Voices	93
5.68	Crosstales.RTVoice.UDEA2.UDEAConnectorEditor Class Reference	93
5.68.1	Detailed Description	93
5.69	Crosstales.RTVoice.UDEA2.UDEAVoiceWrapper Class Reference	93
5.69.1	Detailed Description	94
5.69.2	Member Data Documentation	94
5.69.2.1	IgnoreCharacter	94

5.69.2.2	Pitch	94
5.69.2.3	Rate	94
5.69.2.4	RTVoiceNameAndroid	95
5.69.2.5	RTVoiceNameIOS	95
5.69.2.6	RTVoiceNameMac	95
5.69.2.7	RTVoiceNameWindows	95
5.69.2.8	Source	95
5.69.2.9	UDEAVoiceName	95
5.69.2.10	Volume	95
5.69.3	Property Documentation	95
5.69.3.1	RTVoiceName	95
5.70	Crosstales.RTVoice.EditorExt.UpdateCheck Class Reference	95
5.70.1	Detailed Description	96
5.71	Crosstales.RTVoice.Model.Voice Class Reference	96
5.71.1	Detailed Description	96
5.71.2	Constructor & Destructor Documentation	96
5.71.2.1	Voice(string name, string description, string gender, string age, string culture)	96
5.71.2.2	Voice(string name, string description, string culture)	97
5.71.3	Member Function Documentation	97
5.71.3.1	ToShortString()	97
5.71.4	Member Data Documentation	97
5.71.4.1	Age	97
5.71.4.2	Culture	97
5.71.4.3	Description	97
5.71.4.4	Gender	98
5.71.4.5	Name	98
5.72	PixelCrushers.DialogueSystem.RTVoiceActor.VoicePreference Class Reference	98
5.73	Crosstales.RTVoice.Provider.VoiceProviderAndroid Class Reference	98
5.73.1	Detailed Description	99
5.73.2	Member Function Documentation	99

5.73.2.1	Silence()	99
5.73.2.2	Speak(Wrapper wrapper)	99
5.73.2.3	SpeakNative(WrapperNative wrapper)	99
5.74	Crosstales.RTVoice.Provider.VoiceProviderIOS Class Reference	100
5.74.1	Detailed Description	100
5.74.2	Member Function Documentation	101
5.74.2.1	GetVoices()	101
5.74.2.2	SetState(string state)	101
5.74.2.3	SetVoices(string voicesText)	101
5.74.2.4	Silence()	101
5.74.2.5	Speak(string gameObject, string text, float rate=0.5f, float pitch=1f, float volume=1f, string culture="")	101
5.74.2.6	Speak(Wrapper wrapper)	102
5.74.2.7	SpeakNative(WrapperNative wrapper)	102
5.74.2.8	Stop()	102
5.74.2.9	WordSpoken()	102
5.75	Crosstales.RTVoice.Provider.VoiceProviderMacOS Class Reference	102
5.75.1	Detailed Description	103
5.75.2	Member Function Documentation	103
5.75.2.1	Speak(Wrapper wrapper)	103
5.75.2.2	SpeakNative(WrapperNative wrapper)	103
5.76	Crosstales.RTVoice.Provider.VoiceProviderWindows Class Reference	104
5.76.1	Detailed Description	104
5.76.2	Member Function Documentation	104
5.76.2.1	Speak(Wrapper wrapper)	104
5.76.2.2	SpeakNative(WrapperNative wrapper)	105
5.77	Crosstales.RTVoice.Model.Wrapper Class Reference	105
5.77.1	Detailed Description	106
5.77.2	Constructor & Destructor Documentation	106
5.77.2.1	Wrapper(string text, AudioSource source=null, Voice voice=null, bool speak← Immediately=true, float rate=1f, float pitch=1f, float volume=1f, string outputFile="")	106

5.77.2.2	Wrapper(Guid uid, string text, AudioSource source=null, Voice voice=null, bool speakImmediately=true, float rate=1f, float pitch=1f, float volume=1f, string outputFile="")	106
5.77.3	Member Data Documentation	107
5.77.3.1	OutputFile	107
5.77.3.2	Source	107
5.77.3.3	SpeakImmediately	107
5.77.3.4	Text	107
5.77.3.5	Uid	107
5.77.3.6	Voice	107
5.77.4	Property Documentation	107
5.77.4.1	Pitch	107
5.77.4.2	Rate	107
5.77.4.3	Volume	107
5.78	Crosstales.RTVoice.Model.WrapperNative Class Reference	108
5.78.1	Detailed Description	108
5.78.2	Constructor & Destructor Documentation	108
5.78.2.1	WrapperNative(string text, Voice voice=null, float rate=1f, float pitch=1f, float volume=1f)	108
5.78.2.2	WrapperNative(Guid uid, string text, Voice voice=null, float rate=1f, float pitch=1f, float volume=1f)	109
5.78.3	Member Data Documentation	109
5.78.3.1	Text	109
5.78.3.2	Uid	109
5.78.3.3	Voice	109
5.78.4	Property Documentation	109
5.78.4.1	Pitch	109
5.78.4.2	Rate	109
5.78.4.3	Volume	109

Chapter 1

Namespace Index

1.1 Packages

Here are the packages with brief descriptions (if available):

Crosstales	9
Crosstales.RTVoice	9
Crosstales.RTVoice.AdventureCreator	9
Crosstales.RTVoice.Demo	10
Crosstales.RTVoice.Demo.Util	10
Crosstales.RTVoice.EditorExt	11
Crosstales.RTVoice.Model	12
Crosstales.RTVoice.Model.Event	12
Crosstales.RTVoice.PlayMaker	13
Crosstales.RTVoice.Provider	13
Crosstales.RTVoice.SALSA	13
Crosstales.RTVoice.SLATE	13
Crosstales.RTVoice.Tool	13
Crosstales.RTVoice.UDEA2	14
Crosstales.RTVoice.Util	14
HutongGames	14
HutongGames.PlayMaker	14
HutongGames.PlayMaker.Actions	14
PixelCrushers	15
PixelCrushers.DialogueSystem	15
PixelCrushers.DialogueSystem.SequencerCommands	15

Chapter 2

Hierarchical Index

2.1 Class Hierarchy

This inheritance list is sorted roughly, but not completely, alphabetically:

Crosstales.RTVoice.AdventureCreator.ACConnectorMenu	18
Crosstales.RTVoice.AdventureCreator.ACVoiceWrapper	19
Crosstales.RTVoice.EditorExt.AutoInitalize	22
<AVSpeechSynthesizerDelegate>	
RTVoiceIOSBridge()	62
Crosstales.RTVoice.Provider.BaseVoiceProvider	23
Crosstales.RTVoice.Provider.VoiceProviderAndroid	98
Crosstales.RTVoice.Provider.VoiceProviderIOS	100
Crosstales.RTVoice.Provider.VoiceProviderMacOS	102
Crosstales.RTVoice.Provider.VoiceProviderWindows	104
Crosstales.RTVoice.EditorExt.BuildPostprocessor	27
Crosstales.RTVoice.EditorExt.ConfigLoader	28
Crosstales.RTVoice.Util.Constants	30
CustomActionEditor	
Crosstales.RTVoice.PlayMaker.SpeakEditor	76
Crosstales.RTVoice.PlayMaker.SpeakUIEditor	87
Editor	
Crosstales.RTVoice.AdventureCreator.ACConnectorEditor	18
Crosstales.RTVoice.EditorExt.SequencerEditor	69
Crosstales.RTVoice.EditorExt.SpeakerEditor	84
Crosstales.RTVoice.EditorExt.SpeechTextEditor	91
Crosstales.RTVoice.UDEA2.UDEAConnectorEditor	93
Crosstales.RTVoice.EditorExt.EditorHelper	38
EditorWindow	
Crosstales.RTVoice.EditorExt.ConfigBase	28
Crosstales.RTVoice.EditorExt.ConfigPreferences	29
Crosstales.RTVoice.EditorExt.ConfigWindow	29
EventArgs	
Crosstales.RTVoice.Model.Event.SpeakEventArgs	84
Crosstales.RTVoice.Model.Event.SpeakNativeEventArgs	85
Crosstales.RTVoice.Model.Event.CurrentPhonemeEventArgs	35
Crosstales.RTVoice.Model.Event.CurrentVisemeEventArgs	36
Crosstales.RTVoice.Model.Event.CurrentWordEventArgs	36
FsmStateAction	
HutongGames.PlayMaker.Actions.Silence	70

HutongGames.PlayMaker.Actions.SpeakBase	74
HutongGames.PlayMaker.Actions.Speak	72
HutongGames.PlayMaker.Actions.SpeakUI	86
Crosstales.RTVoice.Util.Helper	47
MonoBehaviour	
Crosstales.RTVoice.AdventureCreator.ACConnector	17
Crosstales.RTVoice.AdventureCreator.ACSwitcher	19
Crosstales.RTVoice.Demo.Dialog	38
Crosstales.RTVoice.Demo.FFTAnalyzer	40
Crosstales.RTVoice.Demo.GUIAudioFilter	41
Crosstales.RTVoice.Demo.GUIDialog	42
Crosstales.RTVoice.Demo.GUIMain	42
Crosstales.RTVoice.Demo.GUIMultiAudioFilter	43
Crosstales.RTVoice.Demo.GUIScenes	44
Crosstales.RTVoice.Demo.GUISpeech	45
Crosstales.RTVoice.Demo.GUISpeechMobile	46
Crosstales.RTVoice.Demo.NativeAudio	55
Crosstales.RTVoice.Demo.NativeDisabler	56
Crosstales.RTVoice.Demo.PreGeneratedAudio	57
Crosstales.RTVoice.Demo.SendMessage	63
Crosstales.RTVoice.Demo.SequenceCaller	66
Crosstales.RTVoice.Demo.Simple	70
Crosstales.RTVoice.Demo.SimpleNative	71
Crosstales.RTVoice.Demo.SpeakWrapper	88
Crosstales.RTVoice.Demo.Util.AudioVisualizer	22
Crosstales.RTVoice.Demo.Util.MaterialChanger	55
Crosstales.RTVoice.Demo.Util.PlatformEnabler	56
Crosstales.RTVoice.Demo.Util.RandomColor	58
Crosstales.RTVoice.Demo.Util.RandomRotator	58
Crosstales.RTVoice.Demo.Util.RandomScaler	59
Crosstales.RTVoice.Demo.Util.ScrollRectHandler	63
Crosstales.RTVoice.LiveSpeaker	51
Crosstales.RTVoice.SALSA.Speak	74
Crosstales.RTVoice.SLATE.CutSceneStart	37
Crosstales.RTVoice.Speaker	76
Crosstales.RTVoice.Tool.Loudspeaker	53
Crosstales.RTVoice.Tool.Sequencer	67
Crosstales.RTVoice.Tool.SpeechText	88
Crosstales.RTVoice.UDEA2.UDEAConnector	92
PixelCrushers.DialogueSystem.RTVoiceActor	59
NSObject	
RTVoiceIOSBridge	61
Crosstales.RTVoice.EditorExt.RTVoiceMenu	63
Crosstales.RTVoice.Model.Sequence	64
SequencerCommand	
PixelCrushers.DialogueSystem.SequencerCommands.SequencerCommandRTVoiceWait	69
Crosstales.RTVoice.UDEA2.UDEAVoiceWrapper	93
Crosstales.RTVoice.EditorExt.UpdateCheck	95
Crosstales.RTVoice.Model.Voice	96
PixelCrushers.DialogueSystem.RTVoiceActor.VoicePreference	98
Crosstales.RTVoice.Model.Wrapper	105
Crosstales.RTVoice.Model.WrapperNative	108

Chapter 3

Class Index

3.1 Class List

Here are the classes, structs, unions and interfaces with brief descriptions:

Crosstales.RTVoice.AdventureCreator.ACConnector	17
Connects Adventure Creator and RT-Voice. It listens to AC-events and speaks when needed.	
Crosstales.RTVoice.AdventureCreator.ACConnectorEditor	18
Custom editor for the 'ACConnector'-class.	
Crosstales.RTVoice.AdventureCreator.ACConnectorMenu	18
Editor component for adding the prefabs for 'Adventure Creator'.	
Crosstales.RTVoice.AdventureCreator.ACSwitcher	19
Allows to switch scenes with Adventure Creator.	
Crosstales.RTVoice.AdventureCreator.ACVoiceWrapper	19
Wrapper for an AC-character to an RT-Voice.	
Crosstales.RTVoice.Demo.Util.AudioVisualizer	22
Simple audio visualizer.	
Crosstales.RTVoice.EditorExt.AutoInitialize	22
Automatically adds the necessary RTVoice-prefabs to the current scene.	
Crosstales.RTVoice.Provider.BaseVoiceProvider	23
Base class for voice providers.	
Crosstales.RTVoice.EditorExt.BuildPostprocessor	27
BuildPostprocessor for Windows. Adds the TTS-wrapper to the build.	
Crosstales.RTVoice.EditorExt.ConfigBase	28
Base class for editor windows.	
Crosstales.RTVoice.EditorExt.ConfigLoader	28
Loads the configuration of the asset.	
Crosstales.RTVoice.EditorExt.ConfigPreferences	29
Unity "Preferences" extension.	
Crosstales.RTVoice.EditorExt.ConfigWindow	29
Editor window extension.	
Crosstales.RTVoice.Util.Constants	30
Collected constants of very general utility for the asset.	
Crosstales.RTVoice.Model.Event.CurrentPhonemeEventArgs	35
EventArgs for the current phoneme.	
Crosstales.RTVoice.Model.Event.CurrentVisemeEventArgs	36
EventArgs for the current viseme.	
Crosstales.RTVoice.Model.Event.CurrentWordEventArgs	36
EventArgs for the current word.	
Crosstales.RTVoice.SLATE.CutSceneStart	37

Crosstales.RTVoice.Demo.Dialog	
Simple dialog system with TTS voices.	38
Crosstales.RTVoice.EditorExt.EditorHelper	
Editor helper class.	38
Crosstales.RTVoice.Demo.FFTAnalyzer	
FFT analyzer for an audio channel.	40
Crosstales.RTVoice.Demo.GUIAudioFilter	
Simple GUI for audio filters.	41
Crosstales.RTVoice.Demo.GUIDialog	
Simple GUI for runtime dialogs with all available OS voices.	42
Crosstales.RTVoice.Demo.GUIMain	
Main GUI component for all demo scenes.	42
Crosstales.RTVoice.Demo.GUIMultiAudioFilter	
Simple GUI for audio filters on multiple objects.	43
Crosstales.RTVoice.Demo.GUIScenes	
Main GUI scene manager for all demo scenes.	44
Crosstales.RTVoice.Demo.GUISpeech	
Simple GUI for runtime TTS with all available OS voices.	45
Crosstales.RTVoice.Demo.GUISpeechMobile	
Simple GUI for runtime TTS with all available OS voices.	46
Crosstales.RTVoice.Util.Helper	
Various helper functions.	47
Crosstales.RTVoice.LiveSpeaker	
Wrapper of the main component from RTVoice for MonoBehaviour-access (like "SendMessage").	51
Crosstales.RTVoice.Tool.Loudspeaker	
Loudspeaker for an AudioSource.	53
Crosstales.RTVoice.Demo.Util.MaterialChanger	
Changes the material of a renderer while an AudioSource is playing.	55
Crosstales.RTVoice.Demo.NativeAudio	
Simple example with native audio for exact timing.	55
Crosstales.RTVoice.Demo.NativeDisabler	
.	56
Crosstales.RTVoice.Demo.Util.PlatformEnabler	
Enables game objects for a given platform.	56
Crosstales.RTVoice.Demo.PreGeneratedAudio	
Simple example with pre-generated audio for exact timing.	57
Crosstales.RTVoice.Demo.Util.RandomColor	
Random color changer.	58
Crosstales.RTVoice.Demo.Util.RandomRotator	
Random rotation changer.	58
Crosstales.RTVoice.Demo.Util.RandomScaler	
Random scale changer.	59
PixelCrushers.DialogueSystem.RTVoiceActor	
.	59
RTVoiceIOSBridge	
.	61
RTVoiceIOSBridge()	
.	62
Crosstales.RTVoice.EditorExt.RTVoiceMenu	
Editor component for adding the various prefabs.	63
Crosstales.RTVoice.Demo.Util.ScrollRectHandler	
Changes the sensitivity of ScrollRects under various platforms.	63
Crosstales.RTVoice.Demo.SendMessage	
Simple "SendMessage" example.	63
Crosstales.RTVoice.Model.Sequence	
Model for a sequence.	64
Crosstales.RTVoice.Demo.SequenceCaller	
Simple Sequence caller example.	66
Crosstales.RTVoice.Tool.Sequencer	
Simple sequencer.	67
PixelCrushers.DialogueSystem.SequencerCommands.SequencerCommandRTVoiceWait	
Sequencer command RTVoiceWait(). Waits for the current RT-Voice audio clip to finish.	69

Crosstales.RTVoice.EditorExt.SequencerEditor	
Custom editor for the 'Sequencer'-class.	69
HutongGames.PlayMaker.Actions.Silence	
Silence-action for PlayMaker	70
Crosstales.RTVoice.Demo.Simple	
Simple TTS example.	70
Crosstales.RTVoice.Demo.SimpleNative	
Simple native TTS example.	71
HutongGames.PlayMaker.Actions.Speak	
Speak-action for PlayMaker	72
Crosstales.RTVoice.SALSA.Speak	
Base for Speak-actions in PlayMaker	74
HutongGames.PlayMaker.Actions.SpeakBase	
Base for Speak-actions in PlayMaker	74
Crosstales.RTVoice.PlayMaker.SpeakEditor	
Custom editor for the Speak-action.	76
Crosstales.RTVoice.Speaker	
Main component of RTVoice	76
Crosstales.RTVoice.EditorExt.SpeakerEditor	
Custom editor for the 'Speaker'-class.	84
Crosstales.RTVoice.Model.Event.SpeakEventArgs	
EventArgs and base class for all speaker events.	84
Crosstales.RTVoice.Model.Event.SpeakNativeEventArgs	
EventArgs and base class for all speaker (native) events.	85
HutongGames.PlayMaker.Actions.SpeakUI	
Speak-action for UI-components in PlayMaker	86
Crosstales.RTVoice.PlayMaker.SpeakUIEditor	
Custom editor for the SpeakUI-action.	87
Crosstales.RTVoice.Demo.SpeakWrapper	
Wrapper for the dynamic speakers.	88
Crosstales.RTVoice.Tool.SpeechText	
Allows to speak and store generated audio.	88
Crosstales.RTVoice.EditorExt.SpeechTextEditor	
Custom editor for the 'SpeechText'-class.	91
Crosstales.RTVoice.UDEA2.UDEAConnector	
Connects UDEA and RT-Voice. Must be placed on a dialogue prefab.	92
Crosstales.RTVoice.UDEA2.UDEAConnectorEditor	
Custom editor for the 'UDEAConnector'-class.	93
Crosstales.RTVoice.UDEA2.UDEAVoiceWrapper	
Wrapper for an UDEA-character to an RT-Voice.	93
Crosstales.RTVoice.EditorExt.UpdateCheck	
Checks for updates of the asset.	95
Crosstales.RTVoice.Model.Voice	
Model for a voice.	96
PixelCrushers.DialogueSystem.RTVoiceActor.VoicePreference	
Voice preference for RTVoiceActor	98
Crosstales.RTVoice.Provider.VoiceProviderAndroid	
Android voice provider.	98
Crosstales.RTVoice.Provider.VoiceProviderIOS	
iOS voice provider.	100
Crosstales.RTVoice.Provider.VoiceProviderMacOS	
MacOS voice provider.	102
Crosstales.RTVoice.Provider.VoiceProviderWindows	
Windows voice provider.	104
Crosstales.RTVoice.Model.Wrapper	
Wrapper for "Speak"-function calls.	105
Crosstales.RTVoice.Model.WrapperNative	
Wrapper (native mode) for "SpeakNative"-function calls.	108

Chapter 4

Namespace Documentation

4.1 Crosstales Namespace Reference

Namespaces

4.2 Crosstales.RTVoice Namespace Reference

Namespaces

Classes

- class [LiveSpeaker](#)
Wrapper of the main component from [RTVoice](#) for MonoBehaviour-access (like "SendMessage").
- class [Speaker](#)
Main component of [RTVoice](#).

4.3 Crosstales.RTVoice.AdventureCreator Namespace Reference

Classes

- class [ACConnector](#)
Connects Adventure Creator and RT-Voice. It listens to AC-events and speaks when needed.
- class [ACConnectorEditor](#)
Custom editor for the '[ACConnector](#)'-class.
- class [ACConnectorMenu](#)
Editor component for adding the prefabs for 'Adventure Creator'.
- class [ACSceneSwitcher](#)
Allows to switch scenes with Adventure Creator.
- class [ACVoiceWrapper](#)
Wrapper for an AC-character to an RT-Voice.

4.4 Crosstales.RTVoice.Demo Namespace Reference

Namespaces

Classes

- class [Dialog](#)
Simple dialog system with TTS voices.
- class [FFTAnalyzer](#)
FFT analyzer for an audio channel.
- class [GUIAudioFilter](#)
Simple GUI for audio filters.
- class [GUIDialog](#)
Simple GUI for runtime dialogs with all available OS voices.
- class [GUIMain](#)
Main GUI component for all demo scenes.
- class [GUIMultiAudioFilter](#)
Simple GUI for audio filters on multiple objects.
- class [GUIScenes](#)
Main GUI scene manager for all demo scenes.
- class [GUISpeech](#)
Simple GUI for runtime TTS with all available OS voices.
- class [GUISpeechMobile](#)
Simple GUI for runtime TTS with all available OS voices.
- class [NativeAudio](#)
Simple example with native audio for exact timing.
- class [NativeDisabler](#)
- class [PreGeneratedAudio](#)
Simple example with pre-generated audio for exact timing.
- class [SendMessage](#)
Simple "SendMessage" example.
- class [SequenceCaller](#)
Simple Sequence caller example.
- class [Simple](#)
Simple TTS example.
- class [SimpleNative](#)
Simple native TTS example.
- class [SpeakWrapper](#)
Warapper for the dynamic speakers.

4.5 Crosstales.RTVoice.Demo.Util Namespace Reference

Classes

- class [AudioVisualizer](#)
Simple audio visualizer.
- class [MaterialChanger](#)
Changes the material of a renderer while an AudioSource is playing.

- class [PlatformEnabler](#)
Enables game objects for a given platform.
- class [RandomColor](#)
Random color changer.
- class [RandomRotator](#)
Random rotation changer.
- class [RandomScaler](#)
Random scale changer.
- class [ScrollRectHandler](#)
Changes the sensitivity of ScrollRects under various platforms.

Enumerations

- enum [Platform](#) {
OSX, Windows, IOS, Android,
Unsupported }
All available platforms.

4.5.1 Enumeration Type Documentation

4.5.1.1 enum Crosstales.RTVoice.Demo.Util.Platform [strong]

All available platforms.

4.6 Crosstales.RTVoice.EditorExt Namespace Reference

Classes

- class [AutoInitialize](#)
Automatically adds the necessary RTVoice-prefabs to the current scene.
- class [BuildPostprocessor](#)
BuildPostprocessor for Windows. Adds the TTS-wrapper to the build.
- class [ConfigBase](#)
Base class for editor windows.
- class [ConfigLoader](#)
Loads the configuration of the asset.
- class [ConfigPreferences](#)
Unity "Preferences" extension.
- class [ConfigWindow](#)
Editor window extension.
- class [EditorHelper](#)
Editor helper class.
- class [RTVoiceMenu](#)
Editor component for adding the various prefabs.
- class [SequencerEditor](#)
Custom editor for the 'Sequencer'-class.
- class [SpeakerEditor](#)
Custom editor for the 'Speaker'-class.
- class [SpeechTextEditor](#)
Custom editor for the 'SpeechText'-class.
- class [UpdateCheck](#)
Checks for updates of the asset.

4.7 Crosstales.RTVoice.Model Namespace Reference

Namespaces

Classes

- class [Sequence](#)
Model for a sequence.
- class [Voice](#)
Model for a voice.
- class [Wrapper](#)
Wrapper for "Speak"-function calls.
- class [WrapperNative](#)
Wrapper (native mode) for "SpeakNative"-function calls.

Enumerations

- enum [SpeakMode](#) { **Speak**, **SpeakNative** }
Available Speak-modes.

4.7.1 Enumeration Type Documentation

4.7.1.1 enum **Crosstales.RTVoice.Model.SpeakMode** [strong]

Available Speak-modes.

4.8 Crosstales.RTVoice.Model.Event Namespace Reference

Classes

- class [CurrentPhonemeEventArgs](#)
EventArgs for the current phoneme.
- class [CurrentVisemeEventArgs](#)
EventArgs for the current viseme.
- class [CurrentWordEventArgs](#)
EventArgs for the current word.
- class [SpeakEventArgs](#)
EventArgs and base class for all speaker events.
- class [SpeakNativeEventArgs](#)
EventArgs and base class for all speaker (native) events.

4.9 Crosstales.RTVoice.PlayMaker Namespace Reference

Classes

- class [SpeakEditor](#)
Custom editor for the Speak-action.
- class [SpeakUIEditor](#)
Custom editor for the SpeakUI-action.

4.10 Crosstales.RTVoice.Provider Namespace Reference

Classes

- class [BaseVoiceProvider](#)
Base class for voice providers.
- class [VoiceProviderAndroid](#)
Android voice provider.
- class [VoiceProviderIOS](#)
iOS voice provider.
- class [VoiceProviderMacOS](#)
MacOS voice provider.
- class [VoiceProviderWindows](#)
Windows voice provider.

4.11 Crosstales.RTVoice.SALSA Namespace Reference

Classes

- class [Speak](#)

4.12 Crosstales.RTVoice.SLATE Namespace Reference

Classes

- class [CutSceneStart](#)

4.13 Crosstales.RTVoice.Tool Namespace Reference

Classes

- class [Loudspeaker](#)
Loudspeaker for an AudioSource.
- class [Sequencer](#)
Simple sequencer.
- class [SpeechText](#)
Allows to speak and store generated audio.

4.14 Crosstales.RTVoice.UDEA2 Namespace Reference

Classes

- class [UDEAConnector](#)
Connects UDEA and RT-Voice. Must be placed on a dialogue prefab.
- class [UDEAConnectorEditor](#)
Custom editor for the 'UDEAConnector'-class.
- class [UDEAVoiceWrapper](#)
Wrapper for an UDEA-character to an RT-Voice.

4.15 Crosstales.RTVoice.Util Namespace Reference

Classes

- class [Constants](#)
Collected constants of very general utility for the asset.
- class [Helper](#)
Various helper functions.

4.16 HutongGames Namespace Reference

Namespaces

4.17 HutongGames.PlayMaker Namespace Reference

Namespaces

4.18 HutongGames.PlayMaker.Actions Namespace Reference

Classes

- class [Silence](#)
Silence-action for [PlayMaker](#).
- class [Speak](#)
Speak-action for [PlayMaker](#).
- class [SpeakBase](#)
Base for Speak-actions in [PlayMaker](#).
- class [SpeakUI](#)
Speak-action for UI-components in [PlayMaker](#).

4.19 PixelCrushers Namespace Reference

Namespaces

4.20 PixelCrushers.DialogueSystem Namespace Reference

Namespaces

Classes

- class [RTVoiceActor](#)

4.21 PixelCrushers.DialogueSystem.SequencerCommands Namespace Reference

Classes

- class [SequencerCommandRTVoiceWait](#)

Sequencer command RTVoiceWait(). Waits for the current RT-Voice audio clip to finish.


Chapter 5

Class Documentation

5.1 Crosstales.RTVoice.AdventureCreator.ACConnector Class Reference

Connects Adventure Creator and RT-Voice. It listens to AC-events and speaks when needed.

Inheritance diagram for Crosstales.RTVoice.AdventureCreator.ACConnector:



Public Attributes

- [ACVoiceWrapper\[\] Voices](#)
Voices for the AC-characters (optional).
- string [Culture](#)
Fallback culture for all sequences (e.g. 'en', optional).
- bool [CallOnStopSpeech](#) = true
Calls a AC-'OnStopSpeech' at the end of a speech (default: on).
- bool [SimulateSkipSpeech](#) = false
Simulates AC-'SkipSpeech' at the end of a speech (default: off).

5.1.1 Detailed Description

Connects Adventure Creator and RT-Voice. It listens to AC-events and speaks when needed.

5.1.2 Member Data Documentation

5.1.2.1 bool Crosstales.RTVoice.AdventureCreator.ACConnector.CallOnStopSpeech = true

Calls a AC-'OnStopSpeech' at the end of a speech (default: on).

5.1.2.2 string Crosstales.RTVoice.AdventureCreator.ACConnector.Culture

Fallback culture for all sequences (e.g. 'en', optional).

5.1.2.3 bool Crosstales.RTVoice.AdventureCreator.ACConnector.SimulateSkipSpeech = false

Simulates AC-'SkipSpeech' at the end of a speech (default: off).

5.1.2.4 ACVoiceWrapper [] Crosstales.RTVoice.AdventureCreator.ACConnector.Voices

Voices for the AC-characters (optional).


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/crosstales/RTVoice/3rd party/Adventure Creator/Scripts/ACConnector.cs

5.2 Crosstales.RTVoice.AdventureCreator.ACConnectorEditor Class Reference

Custom editor for the '[ACConnector](#)'-class.

Inheritance diagram for Crosstales.RTVoice.AdventureCreator.ACConnectorEditor:



Public Member Functions

- override void **OnInspectorGUI** ()

5.2.1 Detailed Description

Custom editor for the '[ACConnector](#)'-class.

The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/crosstales/RTVoice/3rd party/Adventure Creator/Editor/ACConnectorEditor.cs

5.3 Crosstales.RTVoice.AdventureCreator.ACConnectorMenu Class Reference

Editor component for adding the prefabs for 'Adventure Creator'.

5.3.1 Detailed Description

Editor component for adding the prefabs for 'Adventure Creator'.


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/crosstales/RTVoice/3rd party/Adventure Creator/Editor/ACConnectorMenu.cs

5.4 Crosstales.RTVoice.AdventureCreator.ACSceneSwitcher Class Reference

Allows to switch scenes with Adventure Creator.

Inheritance diagram for Crosstales.RTVoice.AdventureCreator.ACSceneSwitcher:



5.4.1 Detailed Description

Allows to switch scenes with Adventure Creator.

The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/crosstales/RTVoice/3rd party/Adventure Creator/Scripts/ACSceneSwitcher.cs

5.5 Crosstales.RTVoice.AdventureCreator.ACVoiceWrapper Class Reference

Wrapper for an AC-character to an RT-Voice.

Public Member Functions

- override string **ToString** ()

Public Attributes

- string `ACVoiceName` = `string.Empty`
Name of the AC-character on-screen.
- string `RTVoiceNameWindows` = `string.Empty`
"Name of the RT-Voice under Windows.
- string `RTVoiceNameMac` = `string.Empty`
Name of the RT-Voice under macOS.
- string `RTVoiceNameAndroid` = `string.Empty`
Name of the RT-Voice under Android.
- string `RTVoiceNameIOS` = `string.Empty`
Name of the RT-Voice under iOS.
- bool `UseSpeechAudioSource` = `true`
Use speech AudioSource of the character (default: on).
- AudioSource `Source`
Origin AudioSource (optional).
- float `Rate` = `1f`
Speech rate of the speaker in percent (1 = 100%, default: 1, optional).
- float `Pitch` = `1f`
Speech pitch of the speaker in percent (1 = 100%, default: 1, optional, mobile only).
- float `Volume` = `1f`
Volume of the speaker in percent (1 = 100%, default: 1, optional).
- bool `IgnoreCharacter` = `false`
Ignore this character (default: off).
- bool `initialized` = `false`

Properties

- string `RTVoiceName` `[get]`
Name of the RT-Voice.

5.5.1 Detailed Description

Wrapper for an AC-character to an RT-Voice.

5.5.2 Member Data Documentation

5.5.2.1 string `Crosstales.RTVoice.AdventureCreator.ACVoiceWrapper.ACVoiceName` = `string.Empty`

Name of the AC-character on-screen.

5.5.2.2 bool `Crosstales.RTVoice.AdventureCreator.ACVoiceWrapper.IgnoreCharacter` = `false`

Ignore this character (default: off).

5.5.2.3 float Crosstales.RTVoice.AdventureCreator.ACVoiceWrapper.Pitch = 1f

Speech pitch of the speaker in percent (1 = 100%, default: 1, optional, mobile only).

5.5.2.4 float Crosstales.RTVoice.AdventureCreator.ACVoiceWrapper.Rate = 1f

Speech rate of the speaker in percent (1 = 100%, default: 1, optional).

5.5.2.5 string Crosstales.RTVoice.AdventureCreator.ACVoiceWrapper.RTVoiceNameAndroid = string.Empty

Name of the RT-Voice under Android.

5.5.2.6 string Crosstales.RTVoice.AdventureCreator.ACVoiceWrapper.RTVoiceNameIOS = string.Empty

Name of the RT-Voice under iOS.

5.5.2.7 string Crosstales.RTVoice.AdventureCreator.ACVoiceWrapper.RTVoiceNameMac = string.Empty

Name of the RT-Voice under macOS.

5.5.2.8 string Crosstales.RTVoice.AdventureCreator.ACVoiceWrapper.RTVoiceNameWindows = string.Empty

"Name of the RT-Voice under Windows.

5.5.2.9 AudioSource Crosstales.RTVoice.AdventureCreator.ACVoiceWrapper.Source

Origin AudioSource (optional).

5.5.2.10 bool Crosstales.RTVoice.AdventureCreator.ACVoiceWrapper.UseSpeechAudioSource = true

Use speech AudioSource of the character (default: on).

5.5.2.11 float Crosstales.RTVoice.AdventureCreator.ACVoiceWrapper.Volume = 1f

Volume of the speaker in percent (1 = 100%, default: 1, optional).

5.5.3 Property Documentation

5.5.3.1 string Crosstales.RTVoice.AdventureCreator.ACVoiceWrapper.RTVoiceName [get]

Name of the RT-Voice.


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/crosstales/RTVoice/3rd party/Adventure Creator/Scripts/ACVoiceWrapper.cs

5.6 Crosstales.RTVoice.Demo.Util.AudioVisualizer Class Reference

[Simple](#) audio visualizer.

Inheritance diagram for Crosstales.RTVoice.Demo.Util.AudioVisualizer:



Public Attributes

- [FFTAnalyzer](#) **Analyzer**
- GameObject **VisualPrefab**
- float **Width** = 0.075f
- float **Gain** = 70f
- bool **LeftToRight** = true

5.6.1 Detailed Description

[Simple](#) audio visualizer.

The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/crosstales/RTVoice/Demo/Scripts/Util/AudioVisualizer.cs

5.7 Crosstales.RTVoice.EditorExt.AutoInitalize Class Reference

Automatically adds the neccessary RTVoice-prefabs to the current scene.

5.7.1 Detailed Description

Automatically adds the necessary RTVoice-prefabs to the current scene.


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/crosstales/RTVoice/Plugins/↔ Editor/AutoInitialize.cs

5.8 Crosstales.RTVoice.Provider.BaseVoiceProvider Class Reference

Base class for voice providers.

Inheritance diagram for Crosstales.RTVoice.Provider.BaseVoiceProvider:



Public Member Functions

- delegate void **SpeakNativeCurrentWord** ([CurrentWordEventArgs](#) e)
- delegate void **SpeakNativeCurrentPhoneme** ([CurrentPhonemeEventArgs](#) e)
- delegate void **SpeakNativeCurrentViseme** ([CurrentVisemeEventArgs](#) e)
- delegate void **SpeakNativeStart** ([SpeakNativeEventArgs](#) e)
- delegate void **SpeakNativeComplete** ([SpeakNativeEventArgs](#) e)
- delegate void **SpeakStart** ([SpeakEventArgs](#) e)
- delegate void **SpeakComplete** ([SpeakEventArgs](#) e)
- delegate void **SpeakAudioGenerationStart** ([SpeakEventArgs](#) e)
- delegate void **SpeakAudioGenerationComplete** ([SpeakEventArgs](#) e)
- delegate void **ErrorInfo** (string info)
- virtual void **Silence** ()
Silence all active TTS-providers.
- virtual void **Silence** (Guid uid)
Silence the current TTS-provider (native mode).
- abstract IEnumerator **SpeakNative** ([WrapperNative](#) wrapper)
The current provider speaks a text with a given voice (native mode).
- abstract IEnumerator **Speak** ([Wrapper](#) wrapper)
The current provider speaks a text with a given voice.

Protected Member Functions

- void **fileCopy** (string inputFile, string outputFile, bool move=false)

Static Protected Member Functions

- static void **onSpeakNativeCurrentWord** ([WrapperNative](#) wrapper, string[] speechTextArray, int wordIndex)
- static void **onSpeakNativeCurrentPhoneme** ([WrapperNative](#) wrapper, string phoneme)
- static void **onSpeakNativeCurrentViseme** ([WrapperNative](#) wrapper, string viseme)
- static void **onSpeakNativeStart** ([WrapperNative](#) wrapper)
- static void **onSpeakNativeComplete** ([WrapperNative](#) wrapper)
- static void **onSpeakStart** ([Wrapper](#) wrapper)
- static void **onSpeakComplete** ([Wrapper](#) wrapper)
- static void **onSpeakAudioGenerationStart** ([Wrapper](#) wrapper)
- static void **onSpeakAudioGenerationComplete** ([Wrapper](#) wrapper)
- static void **onErrorInfo** (string info)

Protected Attributes

- Dictionary< Guid, Process > **processes** = new Dictionary<Guid, Process>()
- bool **silence** = false

Static Protected Attributes

- static List< [Voice](#) > **cachedVoices**
- static char[] **splitCharWords** = new char[] { ' ' }

Properties

- abstract string [AudioFileExtension](#) [get]
Returns the extension of the generated audio files.
- abstract List< [Voice](#) > [Voices](#) [get]
Get all available voices from the current TTS-provider and fills it into a given list.

Events

- static SpeakNativeCurrentWord [OnSpeakNativeCurrentWord](#)
An event triggered whenever a new word is spoken (native mode, Windows only).
- static SpeakNativeCurrentPhoneme [OnSpeakNativeCurrentPhoneme](#)
An event triggered whenever a new phoneme is spoken (native mode, Windows only).
- static SpeakNativeCurrentViseme [OnSpeakNativeCurrentViseme](#)
An event triggered whenever a new viseme is spoken (native mode, Windows only).
- static SpeakNativeStart [OnSpeakNativeStart](#)
An event triggered whenever a native speak is started.
- static SpeakNativeComplete [OnSpeakNativeComplete](#)
An event triggered whenever a native speak is completed.
- static SpeakStart [OnSpeakStart](#)
An event triggered whenever a speak is started.
- static SpeakComplete [OnSpeakComplete](#)
An event triggered whenever a native speak is completed.
- static SpeakAudioGenerationStart [OnSpeakAudioGenerationStart](#)
An event triggered whenever a speak audio generation is started.
- static SpeakAudioGenerationComplete [OnSpeakAudioGenerationComplete](#)
An event triggered whenever a speak audio generation is completed.
- static ErrorInfo [OnErrorInfo](#)
An event triggered whenever an error occurs.

5.8.1 Detailed Description

Base class for voice providers.

5.8.2 Member Function Documentation

5.8.2.1 virtual void Crosstales.RTVoice.Provider.BaseVoiceProvider.Silence () [virtual]

Silence all active TTS-providers.

Reimplemented in [Crosstales.RTVoice.Provider.VoiceProviderAndroid](#), and [Crosstales.RTVoice.Provider.VoiceProviderIOS](#).

5.8.2.2 virtual void Crosstales.RTVoice.Provider.BaseVoiceProvider.Silence (Guid uid) [virtual]

Silence the current TTS-provider (native mode).

Parameters

<i>uid</i>	UID of the speaker
------------	--------------------

5.8.2.3 abstract IEnumerator Crosstales.RTVoice.Provider.BaseVoiceProvider.Speak (Wrapper wrapper) [pure virtual]

The current provider speaks a text with a given voice.

Parameters

<i>wrapper</i>	Wrapper containing the data.
----------------	------------------------------

Implemented in [Crosstales.RTVoice.Provider.VoiceProviderWindows](#), [Crosstales.RTVoice.Provider.VoiceProviderIOS](#), [Crosstales.RTVoice.Provider.VoiceProviderMacOS](#), and [Crosstales.RTVoice.Provider.VoiceProviderAndroid](#).

5.8.2.4 abstract IEnumerator Crosstales.RTVoice.Provider.BaseVoiceProvider.SpeakNative (WrapperNative wrapper) [pure virtual]

The current provider speaks a text with a given voice (native mode).

Parameters

<i>wrapper</i>	Wrapper containing the data.
----------------	------------------------------

Implemented in [Crosstales.RTVoice.Provider.VoiceProviderIOS](#), [Crosstales.RTVoice.Provider.VoiceProviderWindows](#), [Crosstales.RTVoice.Provider.VoiceProviderMacOS](#), and [Crosstales.RTVoice.Provider.VoiceProviderAndroid](#).

[Android](#).

5.8.3 Property Documentation

5.8.3.1 abstract string `Crosstales.RTVoice.Provider.BaseVoiceProvider.AudioFileExtension` `[get]`

Returns the extension of the generated audio files.

Returns

Extension of the generated audio files.

5.8.3.2 abstract List<Voice> `Crosstales.RTVoice.Provider.BaseVoiceProvider.Voices` `[get]`

Get all available voices from the current TTS-provider and fills it into a given list.

Returns

All available voices from the current TTS-provider as list.

5.8.4 Event Documentation

5.8.4.1 `ErrorInfo` `Crosstales.RTVoice.Provider.BaseVoiceProvider.OnErrorInfo` `[static]`

An event triggered whenever an error occurs.

5.8.4.2 `SpeakAudioGenerationComplete` `Crosstales.RTVoice.Provider.BaseVoiceProvider.OnSpeakAudioGenerationComplete` `[static]`

An event triggered whenever a speak audio generation is completed.

5.8.4.3 `SpeakAudioGenerationStart` `Crosstales.RTVoice.Provider.BaseVoiceProvider.OnSpeakAudioGenerationStart` `[static]`

An event triggered whenever a speak audio generation is started.

5.8.4.4 `SpeakComplete` `Crosstales.RTVoice.Provider.BaseVoiceProvider.OnSpeakComplete` `[static]`

An event triggered whenever a native speak is completed.

5.8.4.5 `SpeakNativeComplete` `Crosstales.RTVoice.Provider.BaseVoiceProvider.OnSpeakNativeComplete` `[static]`

An event triggered whenever a native speak is completed.

5.8.4.6 `SpeakNativeCurrentPhoneme` `Crosstales.RTVoice.Provider.BaseVoiceProvider.OnSpeakNativeCurrentPhoneme` `[static]`

An event triggered whenever a new phoneme is spoken (native mode, Windows only).

5.8.4.7 `SpeakNativeCurrentViseme` `Crosstales.RTVoice.Provider.BaseVoiceProvider.OnSpeakNativeCurrentViseme` `[static]`

An event triggered whenever a new viseme is spoken (native mode, Windows only).

5.8.4.8 `SpeakNativeCurrentWord` `Crosstales.RTVoice.Provider.BaseVoiceProvider.OnSpeakNativeCurrentWord` `[static]`

An event triggered whenever a new word is spoken (native mode, Windows only).

5.8.4.9 `SpeakNativeStart` `Crosstales.RTVoice.Provider.BaseVoiceProvider.OnSpeakNativeStart` `[static]`

An event triggered whenever a native speak is started.

5.8.4.10 `SpeakStart` `Crosstales.RTVoice.Provider.BaseVoiceProvider.OnSpeakStart` `[static]`

An event triggered whenever a speak is started.

The documentation for this class was generated from the following file:

- `D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/crosstales/RTVoice/Plugins/↔ Scripts/Provider/BaseVoiceProvider.cs`

5.9 Crosstales.RTVoice.EditorExt.BuildPostprocessor Class Reference

[BuildPostprocessor](#) for Windows. Adds the TTS-wrapper to the build.

Static Public Member Functions

- static void **OnPostprocessBuild** (BuildTarget target, string pathToBuiltProject)

5.9.1 Detailed Description

[BuildPostprocessor](#) for Windows. Adds the TTS-wrapper to the build.


The documentation for this class was generated from the following file:

- `D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/crosstales/RTVoice/Plugins/↔ Editor/BuildPostprocessor.cs`

5.10 Crosstales.RTVoice.EditorExt.ConfigBase Class Reference

Base class for editor windows.

Inheritance diagram for Crosstales.RTVoice.EditorExt.ConfigBase:



Static Protected Member Functions

- static void **showConfiguration** ()
- static void **showAbout** ()
- static void **save** ()

Static Protected Attributes

- static string **updateText** = UpdateCheck.TEXT_NOT_CHECKED

5.10.1 Detailed Description

Base class for editor windows.

The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/crosstales/RTVoice/Plugins/↔ Editor/ConfigBase.cs

5.11 Crosstales.RTVoice.EditorExt.ConfigLoader Class Reference

Loads the configuration of the asset.

5.11.1 Detailed Description

Loads the configuration of the asset.


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/crosstales/RTVoice/Plugins/↔ Editor/ConfigLoader.cs

5.12 Crosstales.RTVoice.EditorExt.ConfigPreferences Class Reference

Unity "Preferences" extension.

Inheritance diagram for Crosstales.RTVoice.EditorExt.ConfigPreferences:



Additional Inherited Members

5.12.1 Detailed Description

Unity "Preferences" extension.


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/crosstales/RTVoice/Plugins/↔ Editor/ConfigPreferences.cs

5.13 Crosstales.RTVoice.EditorExt.ConfigWindow Class Reference

Editor window extension.

Inheritance diagram for Crosstales.RTVoice.EditorExt.ConfigWindow:



Public Member Functions

- delegate void **StopPlayback** ()

Static Public Member Functions

- static void **ShowWindow** ()

Events

- static StopPlayback **OnStopPlayback**

Additional Inherited Members

5.13.1 Detailed Description

Editor window extension.

The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/crosstales/RTVoice/Plugins/↔ Editor/ConfigWindow.cs

5.14 Crosstales.RTVoice.Util.Constants Class Reference

Collected constants of very general utility for the asset.

Public Attributes

- const string **ASSET_NAME** = "RTVoice PRO"
Name of the asset.
- const string **ASSET_VERSION** = "2.5.0"
Version of the asset.
- const int **ASSET_BUILD** = 250
Build number of the asset.
- const string **ASSET_AUTHOR** = "crosstales LLC"
Author of the asset.
- const string **ASSET_AUTHOR_URL** = "http://www.crosstales.com"
URL of the asset author.
- const string **ASSET_URL** = "https://www.assetstore.unity3d.com/#!/content/41068"
URL of the asset.
- const string **ASSET_UPDATE_CHECK_URL** = "http://www.crosstales.com/media/assets/rtvoice_versions.↔ txt"
URL for update-checks of the asset
- const string **ASSET_CONTACT** = "rtvoice@crosstales.com"
Contact to the owner of the asset.
- const string **ASSET_MANUAL_URL** = "http://www.crosstales.com/en/assets/rtvoice/RTVoice-doc.pdf"
URL of the asset manual.
- const string **ASSET_API_URL** = "http://goo.gl/6w4Fy0"
URL of the asset API.
- const string **ASSET_FORUM_URL** = "http://goo.gl/Z6MZMI"
URL of the asset forum.
- const string **ASSET_CT_URL** = "http://www.crosstales.com/en/assets/rtvoice/"
URL of the asset in crosstales.
- const string **RTVOICE_SCENE_OBJECT_NAME** = "RTVoice"

Name of the RT-Voice scene object.

- const string **KEY_DEBUG** = KEY_PREFIX + "DEBUG"
- const string **KEY_UPDATE_CHECK** = KEY_PREFIX + "UPDATE_CHECK"
- const string **KEY_UPDATE_OPEN_UAS** = KEY_PREFIX + "UPDATE_OPEN_UAS"
- const string **KEY_PREFAB_PATH** = KEY_PREFIX + "PREFAB_PATH"
- const string **KEY_PREFAB_AUTOLOAD** = KEY_PREFIX + "PREFAB_AUTOLOAD"
- const string **KEY_AUDIOFILE_PATH** = KEY_PREFIX + "AUDIOFILE_PATH"
- const string **KEY_AUDIOFILE_AUTOMATIC_DELETE** = KEY_PREFIX + "AUDIOFILE_AUTOMATIC_DELETE"
- const string **KEY_UPDATE_DATE** = KEY_PREFIX + "UPDATE_DATE"
- const string **KEY_ENFORCE_32BIT_WINDOWS** = KEY_PREFIX + "ENFORCE_32BIT_WINDOWS"

Static Public Attributes

- static readonly DateTime **ASSET_CREATED** = new DateTime(2015, 4, 29)
Create date of the asset (YYYY, MM, DD).
- static readonly DateTime **ASSET_CHANGED** = new DateTime(2016, 9, 12)
Change date of the asset (YYYY, MM, DD).
- static readonly Guid **ASSET_UID** = new Guid("181f4dab-261f-4746-85f8-849c2866d353")
UID of the asset.
- static bool **DEBUG** = false
Enable or disable debug logging for the asset.
- static bool **UPDATE_CHECK** = true
<summary>Enable or disable update-checks for the asset.
- static bool **UPDATE_OPEN_UAS** = false
<summary>Open the UAS-site when an update is found.
- static string **PREFAB_PATH** = "Assets/crosstales/RTVoice/Prefabs/"
Path of the prefabs.
- static bool **PREFAB_AUTOLOAD** = true
Automatically load and add the prefabs to the scene.
- static string **AUDIOFILE_PATH** = Path.GetTempPath()
Path to the generated audio files.
- static bool **AUDIOFILE_AUTOMATIC_DELETE** = true
Automatically delete the generated audio files.
- static bool **ENFORCE_32BIT_WINDOWS** = false
Enforce 32bit versions of voices under Windows.
- static string **TTS_WINDOWS_EDITOR** = Application.dataPath + @"/crosstales/RTVoice/Plugins/Windows/RTVoiceTTSWrapper.exe"
Location of the TTS-wrapper under Windows (Editor).
- static string **TTS_WINDOWS_EDITOR_x86** = Application.dataPath + @"/crosstales/RTVoice/Plugins/Windows/RTVoiceTTSWrapper_x86.exe"
Location of the TTS-wrapper under Windows (Editor).
- static string **TTS_WINDOWS_BUILD** = Application.dataPath + @"/RTVoiceTTSWrapper.exe"
Location of the TTS-wrapper under Windows (stand-alone).
- static string **TTS_WINDOWS_BUILD_x86** = Application.dataPath + @"/RTVoiceTTSWrapper_x86.exe"
Location of the TTS-wrapper under Windows (stand-alone).
- static string **TTS_MACOS** = "say"
Location of the TTS-system under MacOS.
- static int **TTS_KILL_TIME** = 5000
Kill processes after 5000 milliseconds.
- static string **TEXT_TOSTRING_START** = "{"
- static string **TEXT_TOSTRING_END** = "}"
- static string **TEXT_TOSTRING_DELIMITER** = ", "
- static string **TEXT_TOSTRING_DELIMITER_END** = ""

5.14.1 Detailed Description

Collected constants of very general utility for the asset.

5.14.2 Member Data Documentation

5.14.2.1 `const string Crosstales.RTVoice.Util.Constants.ASSET_API_URL = "http://goo.gl/6w4Fy0"`

URL of the asset API.

5.14.2.2 `const string Crosstales.RTVoice.Util.Constants.ASSET_AUTHOR = "crosstales LLC"`

Author of the asset.

5.14.2.3 `const string Crosstales.RTVoice.Util.Constants.ASSET_AUTHOR_URL = "http://www.crosstales.com"`

URL of the asset author.

5.14.2.4 `const int Crosstales.RTVoice.Util.Constants.ASSET_BUILD = 250`

Build number of the asset.

5.14.2.5 `readonly DateTime Crosstales.RTVoice.Util.Constants.ASSET_CHANGED = new DateTime(2016, 9, 12) [static]`

Change date of the asset (YYYY, MM, DD).

5.14.2.6 `const string Crosstales.RTVoice.Util.Constants.ASSET_CONTACT = "rtvoice@crosstales.com"`

Contact to the owner of the asset.

5.14.2.7 `readonly DateTime Crosstales.RTVoice.Util.Constants.ASSET_CREATED = new DateTime(2015, 4, 29) [static]`

Create date of the asset (YYYY, MM, DD).

5.14.2.8 `const string Crosstales.RTVoice.Util.Constants.ASSET_CT_URL = "http://www.crosstales.com/en/assets/rtvoice/"`

URL of the asset in crosstales.

5.14.2.9 `const string Crosstales.RTVoice.Util.Constants.ASSET_FORUM_URL = "http://goo.gl/Z6MZMI"`

URL of the asset forum.

5.14.2.10 `const string Crosstales.RTVoice.Util.Constants.ASSET_MANUAL_URL = "http://www.crosstales.com/en/assets/rtvoice/RTVoice-doc.pdf"`

URL of the asset manual.

5.14.2.11 `const string Crosstales.RTVoice.Util.Constants.ASSET_NAME = "RTVoice PRO"`

Name of the asset.

5.14.2.12 `readonly Guid Crosstales.RTVoice.Util.Constants.ASSET_UID = new Guid("181f4dab-261f-4746-85f8-849c2866d353")`
`[static]`

UID of the asset.

5.14.2.13 `const string Crosstales.RTVoice.Util.Constants.ASSET_UPDATE_CHECK_URL = "http://www.crosstales.com/media/assets/rtvoice_versions.txt"`

URL for update-checks of the asset

5.14.2.14 `const string Crosstales.RTVoice.Util.Constants.ASSET_URL = "https://www.assetstore.unity3d.com/#!/content/41068"`

URL of the asset.

5.14.2.15 `const string Crosstales.RTVoice.Util.Constants.ASSET_VERSION = "2.5.0"`

Version of the asset.

5.14.2.16 `bool Crosstales.RTVoice.Util.Constants.AUDIOFILE_AUTOMATIC_DELETE = true` `[static]`

Automatically delete the generated audio files.

5.14.2.17 `string Crosstales.RTVoice.Util.Constants.AUDIOFILE_PATH = Path.GetTempPath()` `[static]`

Path to the generated audio files.

5.14.2.18 `bool Crosstales.RTVoice.Util.Constants.DEBUG = false` `[static]`

Enable or disable debug logging for the asset.

5.14.2.19 `bool Crosstales.RTVoice.Util.Constants.ENFORCE_32BIT_WINDOWS = false` `[static]`

Enforce 32bit versions of voices under Windows.

5.14.2.20 `bool Crosstales.RTVoice.Util.Constants.PREFAB_AUTOLOAD = true` `[static]`

Automatically load and add the prefabs to the scene.

5.14.2.21 `string Crosstales.RTVoice.Util.Constants.PREFAB_PATH = "Assets/crosstales/RTVoice/Prefabs/"` `[static]`

Path of the prefabs.

5.14.2.22 `const string Crosstales.RTVoice.Util.Constants.RTVOICE_SCENE_OBJECT_NAME = "RTVoice"`

Name of the RT-Voice scene object.

5.14.2.23 `int Crosstales.RTVoice.Util.Constants.TTS_KILL_TIME = 5000` `[static]`

Kill processes after 5000 milliseconds.

5.14.2.24 `string Crosstales.RTVoice.Util.Constants.TTS_MACOS = "say"` `[static]`

Location of the TTS-system under MacOS.

5.14.2.25 `string Crosstales.RTVoice.Util.Constants.TTS_WINDOWS_BUILD = Application.dataPath +
@"/RTVoiceTTSWrapper.exe"` `[static]`

Location of the TTS-wrapper under Windows (stand-alone).

5.14.2.26 `string Crosstales.RTVoice.Util.Constants.TTS_WINDOWS_BUILD_x86 = Application.dataPath +
@"/RTVoiceTTSWrapper_x86.exe"` `[static]`

Location of the TTS-wrapper under Windows (stand-alone).

5.14.2.27 `string Crosstales.RTVoice.Util.Constants.TTS_WINDOWS_EDITOR = Application.dataPath +
@"/crosstales/RTVoice/Plugins/Windows/RTVoiceTTSWrapper.exe"` `[static]`

Location of the TTS-wrapper under Windows (Editor).

5.14.2.28 `string Crosstales.RTVoice.Util.Constants.TTS_WINDOWS_EDITOR_x86 = Application.dataPath +
@"/crosstales/RTVoice/Plugins/Windows/RTVoiceTTSWrapper_x86.exe"` `[static]`

Location of the TTS-wrapper under Windows (Editor).

5.14.2.29 `bool Crosstales.RTVoice.Util.Constants.UPDATE_CHECK = true` `[static]`

<summaryEnable or disable update-checks for the asset.

5.14.2.30 `bool Crosstales.RTVoice.Util.Constants.UPDATE_OPEN_UAS = false` `[static]`

<summary>Open the UAS-site when an update is found.


The documentation for this class was generated from the following file:

- `D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/crosstales/RTVoice/Plugins/Scripts/Util/Constants.cs`

5.15 Crosstales.RTVoice.Model.Event.CurrentPhonemeEventArgs Class Reference

EventArgs for the current phoneme.

Inheritance diagram for `Crosstales.RTVoice.Model.Event.CurrentPhonemeEventArgs`:



Public Member Functions

- **CurrentPhonemeEventArgs** ([WrapperNative](#) wrapper, string phoneme)

Public Attributes

- string [Phoneme](#)
Current phoneme.

5.15.1 Detailed Description

EventArgs for the current phoneme.

5.15.2 Member Data Documentation

5.15.2.1 `string Crosstales.RTVoice.Model.Event.CurrentPhonemeEventArgs.Phoneme`

Current phoneme.


The documentation for this class was generated from the following file:

- `D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/crosstales/RTVoice/Plugins/Scripts/Model/Event/CurrentPhonemeEventArgs.cs`

5.16 Crosstales.RTVoice.Model.Event.CurrentVisemeEventArgs Class Reference

EventArgs for the current viseme.

Inheritance diagram for Crosstales.RTVoice.Model.Event.CurrentVisemeEventArgs:



Public Member Functions

- **CurrentVisemeEventArgs** ([WrapperNative](#) wrapper, string viseme)

Public Attributes

- string [Viseme](#)
Current viseme.

5.16.1 Detailed Description

EventArgs for the current viseme.

5.16.2 Member Data Documentation

5.16.2.1 string Crosstales.RTVoice.Model.Event.CurrentVisemeEventArgs.Viseme

Current viseme.


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/crosstales/RTVoice/Plugins/↔ Scripts/Model/Event/CurrentVisemeEventArgs.cs

5.17 Crosstales.RTVoice.Model.Event.CurrentWordEventArgs Class Reference

EventArgs for the current word.

Inheritance diagram for Crosstales.RTVoice.Model.Event.CurrentWordEventArgs:



Public Member Functions

- **CurrentWordEventArgs** ([WrapperNative](#) wrapper, string[] speechTextArray, int wordIndex)

Public Attributes

- string[] [SpeechTextArray](#)
Array with the text splitted into words.
- int [WordIndex](#)
Current word index.

5.17.1 Detailed Description

EventArgs for the current word.

5.17.2 Member Data Documentation

5.17.2.1 string[] Crosstales.RTVoice.Model.Event.CurrentWordEventArgs.SpeechTextArray

Array with the text splitted into words.

5.17.2.2 int Crosstales.RTVoice.Model.Event.CurrentWordEventArgs.WordIndex


Current word index.

The documentation for this class was generated from the following file:

- D:/slauberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/crosstales/RTVoice/Plugins/↔ Scripts/Model/Event/CurrentWordEventArgs.cs

5.18 Crosstales.RTVoice.SLATE.CutSceneStart Class Reference

Inheritance diagram for Crosstales.RTVoice.SLATE.CutSceneStart:



Public Attributes

- Cutscene **Cut**


The documentation for this class was generated from the following file:

- D:/slauberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/crosstales/RTVoice/3rd party/SLATE/Scripts/CutSceneStart.cs

5.19 Crosstales.RTVoice.Demo.Dialog Class Reference

[Simple](#) dialog system with TTS voices.

Inheritance diagram for Crosstales.RTVoice.Demo.Dialog:



Public Member Functions

- void **Start** ()
- IEnumerator **DialogSequence** ()

Public Attributes

- string **Culture** = "en"
- AudioSource **AudioPersonA**
- AudioSource **AudioPersonB**
- GameObject **VisualsA**
- GameObject **VisualsB**
- string[] **DialogPersonA**
- string[] **DialogPersonB**
- string **CurrentDialogA** = string.Empty
- string **CurrentDialogB** = string.Empty
- bool **Running** = false
- float **RateA** = 1f
- float **RateB** = 1f
- float **VolumeA** = 1f
- float **VolumeB** = 1f

5.19.1 Detailed Description

[Simple](#) dialog system with TTS voices.

The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/crosstales/RTVoice/Demo/↔ Scripts/Dialog.cs

5.20 Crosstales.RTVoice.EditorExt.EditorHelper Class Reference

Editor helper class.

Static Public Member Functions

- static void [NoVoicesUI](#) ()
Shows the "no voices found"-UI.
- static void [SeparatorUI](#) (int space=20)
Shows a separator-UI.
- static void [AddRTVoice](#) ()
Adds the '[RTVoice](#)'-prefab to the scene.

Public Attributes

- const int [MENU_ID](#) = 2000
Start index inside the "Tools"-menu.

Properties

- static bool [isRTVoiceInScene](#) [get]
Checks if the '[RTVoice](#)'-prefab is in the scene.

5.20.1 Detailed Description

Editor helper class.

5.20.2 Member Function Documentation

5.20.2.1 static void Crosstales.RTVoice.EditorExt.EditorHelper.AddRTVoice () [static]

Adds the '[RTVoice](#)'-prefab to the scene.

5.20.2.2 static void Crosstales.RTVoice.EditorExt.EditorHelper.NoVoicesUI () [static]

Shows the "no voices found"-UI.

5.20.2.3 static void Crosstales.RTVoice.EditorExt.EditorHelper.SeparatorUI (int space = 20) [static]

Shows a separator-UI.

5.20.3 Member Data Documentation

5.20.3.1 const int Crosstales.RTVoice.EditorExt.EditorHelper.MENU_ID = 2000

Start index inside the "Tools"-menu.

5.20.4 Property Documentation

5.20.4.1 `bool Crosstales.RTVoice.EditorExt.EditorHelper.isRTVoiceInScene` `[static], [get]`

Checks if the 'RTVoice'-prefab is in the scene.

Returns

True if the 'RTVoice'-prefab is in the scene.


The documentation for this class was generated from the following file:

- `D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/crosstales/RTVoice/Plugins/↔ Editor/EditorHelper.cs`

5.21 Crosstales.RTVoice.Demo.FFTAnalyzer Class Reference

FFT analyzer for an audio channel.

Inheritance diagram for `Crosstales.RTVoice.Demo.FFTAnalyzer`:



Public Attributes

- `float[] Samples = new float[256]`
- `int Channel = 0`
- `FFTWindow FFTMode = FFTWindow.BlackmanHarris`

5.21.1 Detailed Description

FFT analyzer for an audio channel.


The documentation for this class was generated from the following file:

- `D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/crosstales/RTVoice/Demo/↔ Scripts/Util/FFTAnalyzer.cs`

5.22 Crosstales.RTVoice.Demo.GUIAudioFilter Class Reference

[Simple](#) GUI for audio filters.

Inheritance diagram for Crosstales.RTVoice.Demo.GUIAudioFilter:



Public Member Functions

- void **ResetFilters** ()
- void **ReverbFilterDropdownChanged** (Int32 index)
- void **ChorusFilterEnabled** (bool enabled)
- void **EchoFilterEnabled** (bool enabled)
- void **DistortionFilterEnabled** (bool enabled)
- void **DistortionFilterChanged** (float value)
- void **LowPassFilterEnabled** (bool enabled)
- void **LowPassFilterChanged** (float value)
- void **HighPassFilterEnabled** (bool enabled)
- void **HighPassFilterChanged** (float value)
- void **VolumeChanged** (float value)
- void **PitchChanged** (float value)

Public Attributes

- AudioSource **Source**
- AudioReverbFilter **ReverbFilter**
- AudioChorusFilter **ChorusFilter**
- AudioEchoFilter **EchoFilter**
- AudioDistortionFilter **DistortionFilter**
- AudioLowPassFilter **LowPassFilter**
- AudioHighPassFilter **HighPassFilter**
- Text **Distortion**
- Text **Lowpass**
- Text **Highpass**
- Text **Volume**
- Text **Pitch**

5.22.1 Detailed Description

[Simple](#) GUI for audio filters.


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/crosstales/RTVoice/Demo/↔ Scripts/GUIAudioFilter.cs

5.23 Crosstales.RTVoice.Demo.GUIDialog Class Reference

[Simple](#) GUI for runtime dialogs with all available OS voices.

Inheritance diagram for Crosstales.RTVoice.Demo.GUIDialog:



Public Member Functions

- void **Start** ()
- void **Update** ()
- void **StartDialog** ()
- void **Silence** ()
- void **ChangeRateA** (float value)
- void **ChangeRateB** (float value)
- void **ChangeVolumeA** (float value)
- void **ChangeVolumeB** (float value)

Public Attributes

- [Dialog](#) **DialogScript**
- Image **PanelPersonA**
- Image **PanelPersonB**
- Text **PersonA**
- Text **PersonB**
- Color32 **SpeakerColor** = new Color32(0, 255, 0, 192)

5.23.1 Detailed Description

[Simple](#) GUI for runtime dialogs with all available OS voices.


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/crosstales/RTVoice/Demo/↔ Scripts/GUIDialog.cs

5.24 Crosstales.RTVoice.Demo.GUIMain Class Reference

Main GUI component for all demo scenes.

Inheritance diagram for Crosstales.RTVoice.Demo.GUIMain:



Public Member Functions

- void **OpenAssetURL** ()
- void **OpenCTURL** ()
- void **Silence** ()
- void **Quit** ()

Public Attributes

- Text **Version**
- Text **Scene**
- GameObject **NoVoices**
- Text **Errors**

5.24.1 Detailed Description

Main GUI component for all demo scenes.


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/crosstales/RTVoice/Demo/↔ Scripts/GUIMain.cs

5.25 Crosstales.RTVoice.Demo.GUIMultiAudioFilter Class Reference

Simple GUI for audio filters on multiple objects.

Inheritance diagram for Crosstales.RTVoice.Demo.GUIMultiAudioFilter:



Public Member Functions

- void **ResetFilters** ()
- void **ClearFilters** ()
- void **ReverbFilterDropdownChanged** (Int32 index)
- void **ChorusFilterEnabled** (bool enabled)
- void **EchoFilterEnabled** (bool enabled)
- void **DistortionFilterEnabled** (bool enabled)
- void **DistortionFilterChanged** (float value)
- void **LowPassFilterEnabled** (bool enabled)
- void **LowPassFilterChanged** (float value)
- void **HighPassFilterEnabled** (bool enabled)
- void **HighPassFilterChanged** (float value)
- void **VolumeChanged** (float value)
- void **PitchChanged** (float value)

Public Attributes

- List< AudioSource > **Sources** = new List<AudioSource>()
- List< AudioReverbFilter > **ReverbFilters** = new List<AudioReverbFilter>()
- List< AudioChorusFilter > **ChorusFilters** = new List<AudioChorusFilter>()
- List< AudioEchoFilter > **EchoFilters** = new List<AudioEchoFilter>()
- List< AudioDistortionFilter > **DistortionFilters** = new List<AudioDistortionFilter>()
- List< AudioLowPassFilter > **LowPassFilters** = new List<AudioLowPassFilter>()
- List< AudioHighPassFilter > **HighPassFilters** = new List<AudioHighPassFilter>()
- Text **Distortion**
- Text **Lowpass**
- Text **Highpass**
- Text **Volume**
- Text **Pitch**

5.25.1 Detailed Description

[Simple](#) GUI for audio filters on multiple objects.


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/crosstaes/RTVoice/Demo/↔ Scripts/GUIMultiAudioFilter.cs

5.26 Crosstaes.RTVoice.Demo.GUIScenes Class Reference

Main GUI scene manager for all demo scenes.

Inheritance diagram for Crosstaes.RTVoice.Demo.GUIScenes:



Public Member Functions

- void **LoadPrevoiusScene** ()
- void **LoadNextScene** ()

Public Attributes

- string **PreviousScene**
- string **NextScene**

5.26.1 Detailed Description

Main GUI scene manager for all demo scenes.


The documentation for this class was generated from the following file:

- `D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/crosstales/RTVoice/Demo/Scripts/GUIScenes.cs`

5.27 Crosstales.RTVoice.Demo.GUISpeech Class Reference

Simple GUI for runtime TTS with all available OS voices.

Inheritance diagram for Crosstales.RTVoice.Demo.GUISpeech:



Public Member Functions

- void **Silence** ()
- void **ChangeRate** (float rate)
- void **ChangeVolume** (float volume)
- void **ChangePitch** (float pitch)
- void **ChangeNative** (bool native)

Public Attributes

- GameObject **ItemPrefab**
- GameObject **Target**
- Scrollbar **Scroll**
- int **ColumnCount** = 1
- Vector2 **SpaceWidth** = new Vector2(8, 8)
- Vector2 **SpaceHeight** = new Vector2(8, 8)
- InputField **Input**
- InputField **Culture**
- Text **Cultures**
- bool **StartAsNative** = false
- [GUIMultiAudioFilter](#) **AudioFilter**

Static Public Attributes

- static float **Rate** = 1f
- static float **Pitch** = 1f
- static float **Volume** = 1f
- static bool **isNative** = false

5.27.1 Detailed Description

[Simple](#) GUI for runtime TTS with all available OS voices.


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/crosstaes/RTVoice/Demo/↔ Scripts/GUISpeech.cs

5.28 Crosstaes.RTVoice.Demo.GUISpeechMobile Class Reference

[Simple](#) GUI for runtime TTS with all available OS voices.

Inheritance diagram for Crosstaes.RTVoice.Demo.GUISpeechMobile:



Public Member Functions

- void **Silence** ()
- void **ChangeRate** (float rate)
- void **ChangeVolume** (float volume)
- void **ChangePitch** (float pitch)
- void **ChangeNative** (bool native)

Public Attributes

- GameObject **ItemPrefab**
- GameObject **Target**
- Scrollbar **Scroll**
- int **ColumnCount** = 1
- Vector2 **SpaceWidth** = new Vector2(8, 8)
- Vector2 **SpaceHeight** = new Vector2(8, 8)
- InputField **Input**
- InputField **Culture**
- Text **Cultures**

Static Public Attributes

- static float **Rate** = 1f
- static float **Pitch** = 1f
- static float **Volume** = 1f
- static bool **isNative** = false

5.28.1 Detailed Description

Simple GUI for runtime TTS with all available OS voices.

The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/crosstales/RTVoice/Demo/↔ Scripts/GUISpeechMobile.cs

5.29 Crosstales.RTVoice.Util.Helper Class Reference

Various helper functions.

Static Public Member Functions

- static string [CleanText](#) (string text, bool removePunctuation=true)
Cleans a given text to contain only letters or digits.
- static string [ClearSpaces](#) (string text)
Cleans a given text from multiple spaces.
- static string [ValidatePath](#) (string path)
Validates a given path and add missing slash.
- static List< string > [SplitStringToLines](#) (string text)
Split the given text to lines and return it as list.
- static Color [HSVToRGB](#) (float h, float s, float v, float a=1f)
Generate nice HSV colors. Based on <https://gist.github.com/rje/6206099>
- static string [MarkSpokenText](#) (string[] speechTextArray, int wordIndex, bool markAllSpokenWords=false, string markPrefix="<color=green>", string markPostfix="</color>")
Marks the current word or all spoken words from a given text array.
- static string [CTDump< T >](#) (this T[] array)
Extension method for Arrays. Dumps an array to a string.
- static string [CTDump< T >](#) (this List< T > list)
Extension method for Lists. Dumps a list to a string.

Properties

- static bool [isWindowsPlatform](#) [get]
Checks if the current platform is Windows.
- static bool [isMacOSPlatform](#) [get]
Checks if the current platform is OSX.
- static bool [isAndroidPlatform](#) [get]
Checks if the current platform is Android.
- static bool [isIOSPlatform](#) [get]
Checks if the current platform is iOS.
- static bool [isEditorMode](#) [get]
Checks if we are in Editor mode.
- static bool [isSupportedPlatform](#) [get]
Checks if the current platform is supported.

5.29.1 Detailed Description

Various helper functions.

5.29.2 Member Function Documentation

5.29.2.1 `static string Crosstales.RTVoice.Util.Helper.CleanText (string text, bool removePunctuation =true) [static]`

Cleans a given text to contain only letters or digits.

Parameters

<i>text</i>	Text to clean.
<i>removePunctuation</i>	Remove punctuation from text (default: true, optional).

Returns

Clean text with only letters and digits.

5.29.2.2 `static string Crosstales.RTVoice.Util.Helper.ClearSpaces (string text) [static]`

Cleans a given text from multiple spaces.

Parameters

<i>text</i>	Text to clean.
-------------	----------------

Returns

Clean text without multiple spaces.

5.29.2.3 `static string Crosstales.RTVoice.Util.Helper.CTDump< T > (this T[] array) [static]`

Extension method for Arrays. Dumps an array to a string.

Parameters

<i>array</i>	Array to dump.
--------------	----------------

Returns

String with lines for all array entries.

5.29.2.4 static string Crosstales.RTVoice.Util.Helper.CTDump< T > (this List< T > list) [static]

Extension method for Lists. Dumps a list to a string.

Parameters

<i>list</i>	List to dump.
-------------	---------------

Returns

String with lines for all list entries.

5.29.2.5 static Color Crosstales.RTVoice.Util.Helper.HSVToRGB (float h, float s, float v, float a = 1f) [static]

Generate nice HSV colors. Based on <https://gist.github.com/rje/6206099>

Parameters

<i>h</i>	Hue
<i>s</i>	Saturation
<i>v</i>	Value
<i>a</i>	Alpha (optional)

Returns

True if the current platform is supported.

5.29.2.6 static string Crosstales.RTVoice.Util.Helper.MarkSpokenText (string[] speechTextArray, int wordIndex, bool markAllSpokenWords = false, string markPrefix = "<color=green>", string markPostfix = "</color>") [static]

Marks the current word or all spoken words from a given text array.

Parameters

<i>speechTextArray</i>	Array with all text fragments
<i>wordIndex</i>	Current word index
<i>markAllSpokenWords</i>	Mark the spoken words (default: false, optional)
<i>markPrefix</i>	Prefix for every marked word (default: green, optional)
<i>markPostfix</i>	Postfix for every marked word (default: green, optional)

Returns

Marked current word or all spoken words.

5.29.2.7 `static List<string> Crosstales.RTVoice.Util.Helper.SplitStringToLines (string text) [static]`

Split the given text to lines and return it as list.

Parameters

<i>text</i>	Complete text fragment
-------------	------------------------

Returns

Splitted lines as array

5.29.2.8 `static string Crosstales.RTVoice.Util.Helper.ValidatePath (string path) [static]`

Validates a given path and add missing slash.

Parameters

<i>path</i>	Path to validate
-------------	------------------

Returns

Valid path

5.29.3 Property Documentation

5.29.3.1 `bool Crosstales.RTVoice.Util.Helper.isAndroidPlatform [static], [get]`

Checks if the current platform is Android.

Returns

True if the current platform is Android.

5.29.3.2 `bool Crosstales.RTVoice.Util.Helper.isEditorMode [static], [get]`

Checks if we are in Editor mode.

Returns

True if in Editor mode.

5.29.3.3 `bool Crosstales.RTVoice.Util.Helper.isIOSPlatform` `[static], [get]`

Checks if the current platform is iOS.

Returns

True if the current platform is iOS.

5.29.3.4 `bool Crosstales.RTVoice.Util.Helper.isMacOSPlatform` `[static], [get]`

Checks if the current platform is OSX.

Returns

True if the current platform is OSX.

5.29.3.5 `bool Crosstales.RTVoice.Util.Helper.isSupportedPlatform` `[static], [get]`

Checks if the current platform is supported.

Returns

True if the current platform is supported.

5.29.3.6 `bool Crosstales.RTVoice.Util.Helper.isWindowsPlatform` `[static], [get]`

Checks if the current platform is Windows.

Returns

True if the current platform is Windows.


The documentation for this class was generated from the following file:

- `D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/crosstales/RTVoice/Plugins/↵ Scripts/Util/Helper.cs`

5.30 Crosstales.RTVoice.LiveSpeaker Class Reference

Wrapper of the main component from [RTVoice](#) for MonoBehaviour-access (like "SendMessage").

Inheritance diagram for Crosstales.RTVoice.LiveSpeaker:



Public Member Functions

- void [SpeakNative](#) ([WrapperNative](#) wrapper)
Speaks a text with a given wrapper -> native mode.
- void [SpeakNative](#) (string args)
Speaks a text with a given array of arguments (native mode).
- void [SpeakNative](#) (string[] args)
Speaks a text with a given array of arguments (native mode).
- void [Speak](#) ([Wrapper](#) wrapper)
Speaks a text with a given wrapper.
- void [Speak](#) (string args)
Speaks a text with a given array of arguments.
- void [Speak](#) (string[] args)
Speaks a text with a given array of arguments.
- void [Silence](#) ()
Silence all active TTS-voices.

5.30.1 Detailed Description

Wrapper of the main component from [RTVoice](#) for MonoBehaviour-access (like "SendMessage").

5.30.2 Member Function Documentation

5.30.2.1 void Crosstales.RTVoice.LiveSpeaker.Silence ()

Silence all active TTS-voices.

5.30.2.2 void Crosstales.RTVoice.LiveSpeaker.Speak ([Wrapper](#) wrapper)

Speaks a text with a given wrapper.

Parameters

<i>wrapper</i>	Wrapper with the speech details.
----------------	----------------------------------

5.30.2.3 void Crosstales.RTVoice.LiveSpeaker.Speak (string args)

Speaks a text with a given array of arguments.

Important: you can't specify the AudioSource with this method!

Parameters

<i>args</i>	Argument string delimited by ';': 0 = text, 1 = culture (optional), 2 = voiceName (optional), 3 = rate (optional), 4 = volume (optional), 5 = pitch (optional).
-------------	---

5.30.2.4 void Crosstales.RTVoice.LiveSpeaker.Speak (string[] args)

Speaks a text with a given array of arguments.

Important: you can't specify the AudioSource with this method!

Parameters

<i>args</i>	Argument index: 0 = text, 1 = culture (optional), 2 = voiceName (optional), 3 = rate (optional), 4 = volume (optional), 5 = pitch (optional).
-------------	---

5.30.2.5 void Crosstales.RTVoice.LiveSpeaker.SpeakNative (WrapperNative wrapper)

Speaks a text with a given wrapper -> native mode.

Parameters

<i>wrapper</i>	Wrapper with the speech details.
----------------	----------------------------------

5.30.2.6 void Crosstales.RTVoice.LiveSpeaker.SpeakNative (string args)

Speaks a text with a given array of arguments (native mode).

Parameters

<i>args</i>	Argument string delimited by ';': 0 = text, 1 = culture (optional), 2 = voiceName (optional), 3 = rate (optional), 4 = volume (optional), 5 = pitch (optional).
-------------	---

5.30.2.7 void Crosstales.RTVoice.LiveSpeaker.SpeakNative (string[] args)

Speaks a text with a given array of arguments (native mode).

Parameters

<i>args</i>	Argument index: 0 = text, 1 = culture (optional), 2 = voiceName (optional), 3 = rate (optional), 4 = volume (optional), 5 = pitch (optional).
-------------	---


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/crosstales/RTVoice/Plugins/↵ Scripts/LiveSpeaker.cs

5.31 Crosstales.RTVoice.Tool.Loudspeaker Class Reference

[Loudspeaker](#) for an AudioSource.

Inheritance diagram for Crosstales.RTVoice.Tool.Loudspeaker:



Public Attributes

- AudioSource [Source](#)
Origin AudioSource.
- bool [Synchronized](#) = true
Synchronized with the origin (default: on).
- bool [SilenceSource](#) = false
Silence the origin (default: off).

5.31.1 Detailed Description

[Loudspeaker](#) for an AudioSource.

5.31.2 Member Data Documentation

5.31.2.1 bool Crosstales.RTVoice.Tool.Loudspeaker.SilenceSource = false

Silence the origin (default: off).

5.31.2.2 AudioSource Crosstales.RTVoice.Tool.Loudspeaker.Source

Origin AudioSource.

5.31.2.3 bool Crosstales.RTVoice.Tool.Loudspeaker.Synchronized = true

Synchronized with the origin (default: on).


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/crosstales/RTVoice/Plugins/↔ Scripts/Tool/Loudspeaker.cs

5.32 Crosstales.RTVoice.Demo.Util.MaterialChanger Class Reference

Changes the material of a renderer while an AudioSource is playing.

Inheritance diagram for Crosstales.RTVoice.Demo.Util.MaterialChanger:



Public Attributes

- AudioSource **Source**
- Material **ActiveMaterial**

5.32.1 Detailed Description

Changes the material of a renderer while an AudioSource is playing.


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/crosstales/RTVoice/Demo/Scripts/Util/MaterialChanger.cs

5.33 Crosstales.RTVoice.Demo.NativeAudio Class Reference

[Simple](#) example with native audio for exact timing.

Inheritance diagram for Crosstales.RTVoice.Demo.NativeAudio:



Public Member Functions

- void **StartTTS** ()
- void **Silence** ()

Public Attributes

- string **SpeechText** = "This is an example with native audio for exact timing (e.g. animations)."
- bool **PlayOnStart** = false
- float **Delay** = 1f

5.33.1 Detailed Description


[Simple](#) example with native audio for exact timing.

The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/crosstales/RTVoice/Demo/↔ Scripts/NativeAudio.cs

5.34 Crosstales.RTVoice.Demo.NativeDisabler Class Reference

Inheritance diagram for Crosstales.RTVoice.Demo.NativeDisabler:



Public Attributes

- `GameObject[]` **Objects**


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/crosstales/RTVoice/Demo/↔ Scripts/NativeDisabler.cs

5.35 Crosstales.RTVoice.Demo.Util.PlatformEnabler Class Reference

Enables game objects for a given platform.

Inheritance diagram for Crosstales.RTVoice.Demo.Util.PlatformEnabler:



Public Attributes

- `List< Platform >` **EnabledPlatforms**
- `GameObject[]` **Objects**

5.35.1 Detailed Description

Enables game objects for a given platform.


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/crosstales/RTVoice/Demo/↔ Scripts/Util/PlatformEnabler.cs

5.36 Crosstales.RTVoice.Demo.PreGeneratedAudio Class Reference

[Simple](#) example with pre-generated audio for exact timing.

Inheritance diagram for Crosstales.RTVoice.Demo.PreGeneratedAudio:



Public Member Functions

- void **Play** ()
- void **Silence** ()
- void **Stop** ()

Public Attributes

- string **SpeechText** = "This is an example with pre-generated audio for exact timing (e.g. animations)."
- bool **PlayOnStart** = false

5.36.1 Detailed Description

[Simple](#) example with pre-generated audio for exact timing.


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/crosstales/RTVoice/Demo/↔ Scripts/PreGeneratedAudio.cs

5.37 Crosstales.RTVoice.Demo.Util.RandomColor Class Reference

Random color changer.

Inheritance diagram for Crosstales.RTVoice.Demo.Util.RandomColor:



Public Attributes

- Vector2 **ChangeInterval** = new Vector2(5, 15)

5.37.1 Detailed Description

Random color changer.


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/crosstales/RTVoice/Demo/↔ Scripts/Util/RandomColor.cs

5.38 Crosstales.RTVoice.Demo.Util.RandomRotator Class Reference

Random rotation changer.

Inheritance diagram for Crosstales.RTVoice.Demo.Util.RandomRotator:



Public Attributes

- Vector3 **Speed**
- Vector2 **ChangeInterval** = new Vector2(10, 45)

5.38.1 Detailed Description

Random rotation changer.


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/crosstales/RTVoice/Demo/↔ Scripts/Util/RandomRotator.cs

5.39 Crosstales.RTVoice.Demo.Util.RandomScaler Class Reference

Random scale changer.

Inheritance diagram for Crosstales.RTVoice.Demo.Util.RandomScaler:



Public Attributes

- Vector3 **ScaleMin** = Vector3.zero
- Vector3 **ScaleMax** = Vector3.one
- bool **Uniform** = false
- Vector2 **ChangeInterval** = new Vector2(10, 45)

5.39.1 Detailed Description


Random scale changer.

The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/crosstales/RTVoice/Demo/Scripts/Util/RandomScaler.cs

5.40 PixelCrushers.DialogueSystem.RTVoiceActor Class Reference

Inheritance diagram for PixelCrushers.DialogueSystem.RTVoiceActor:



Classes

- class [VoicePreference](#)

Public Types

- enum **Gender** { **Female**, **Male** }

Public Member Functions

- virtual void **Awake** ()
- void **OnConversationLine** (Subtitle subtitle)
When a conversation line is spoken, speak it through RT-Voice.
- void **OnBarkLine** (Subtitle subtitle)
When a bark line is spoken, speak it through RT-Voice.
- void **SpeakSubtitle** (Subtitle subtitle, bool wait)
- virtual void **Speak** (string text)
Speak the specified text using RT-Voice. You can override this if you need to do anything extra.
- **Voice GetVoice** ()
Gets the system's closest match voice to the preferred voice for the current language.

Public Attributes

- **VoicePreference[] voicePreferences** = new **VoicePreference**[0]
The voice preferences to try to match.
- bool **waitForVoiceInConversations** = true
In conversations, make the dialogue entry wait until RT-Voice is done playing.

Protected Member Functions

- bool **MatchesVoicePreference** (**Voice** voice, **VoicePreference** voicePreference)
- string **StripRichText** (string s)

Protected Attributes

- AudioSource **myAudioSource** = null

5.40.1 Member Function Documentation

5.40.1.1 **Voice** PixelCrushers.DialogueSystem.RTVoiceActor.GetVoice ()

Gets the system's closest match voice to the preferred voice for the current language.

Returns

The voice.

5.40.1.2 void PixelCrushers.DialogueSystem.RTVoiceActor.OnBarkLine (Subtitle subtitle)

When a bark line is spoken, speak it through RT-Voice.

Parameters

<i>subtitle</i>	Subtitle.
-----------------	-----------

5.40.1.3 void PixelCrushers.DialogueSystem.RTVoiceActor.OnConversationLine (Subtitle *subtitle*)

When a conversation line is spoken, speak it through RT-Voice.

Parameters

<i>subtitle</i>	Subtitle.
-----------------	-----------

5.40.1.4 virtual void PixelCrushers.DialogueSystem.RTVoiceActor.Speak (string *text*) [virtual]

Speak the specified text using RT-Voice. You can override this if you need to do anything extra.

Parameters

<i>text</i>	Text.
-------------	-------

5.40.2 Member Data Documentation

5.40.2.1 VoicePreference [] PixelCrushers.DialogueSystem.RTVoiceActor.voicePreferences = new VoicePreference[0]

The voice preferences to try to match.

5.40.2.2 bool PixelCrushers.DialogueSystem.RTVoiceActor.waitForVoiceInConversations = true


In conversations, make the dialogue entry wait until RT-Voice is done playing.

The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/crosstailes/RTVoice/3rd party/Dialogue System/Scripts/RTVoiceActor.cs

5.41 RTVoiceIOSBridge Class Reference

Inheritance diagram for RTVoiceIOSBridge:



Instance Methods

- (void) - [setVoices](#)
- (void) - [speak:rate:pitch:volume:culture:](#)
- (void) - [stop](#)

5.41.1 Method Documentation

5.41.1.1 - (void) setVoices

Collects and sends all voices to RTVoice.

5.41.1.2 - (void) speak: (NSString *) text rate:(float) rate pitch:(float) pitch volume:(float) volume culture:(NSString *) culture

Speaks the string with a given rate, pitch, volume and culture.

Parameters

<i>text</i>	Text to speak
<i>rate</i>	Speech rate of the speaker in percent
<i>pitch</i>	Pitch of the speech in percent
<i>volume</i>	Volume of the speaker in percent
<i>culture</i>	Culture of the voice to speak

5.41.1.3 - (void) stop


Stops speaking

The documentation for this class was generated from the following files:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/crosstales/RTVoice/RTVoiceIOSBridge.h
- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/crosstales/RTVoice/RTVoiceIOSBridge.mm

5.42 RTVoiceIOSBridge() Category Reference

Inheritance diagram for RTVoiceIOSBridge():



Properties

- AVSpeechSynthesizer * **synthesizer**

The documentation for this category was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/crosstales/RTVoice/RTVoiceIOSBridge.mm

5.43 Crosstales.RTVoice.EditorExt.RTVoiceMenu Class Reference

Editor component for adding the various prefabs.

5.43.1 Detailed Description

Editor component for adding the various prefabs.


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/crosstales/RTVoice/Plugins/↔ Editor/RTVoiceMenu.cs

5.44 Crosstales.RTVoice.Demo.Util.ScrollRectHandler Class Reference

Changes the sensitivity of ScrollRects under various platforms.

Inheritance diagram for Crosstales.RTVoice.Demo.Util.ScrollRectHandler:



Public Attributes

- ScrollRect **Scroll**

5.44.1 Detailed Description

Changes the sensitivity of ScrollRects under various platforms.


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/crosstales/RTVoice/Demo/↔ Scripts/Util/ScrollRectHandler.cs

5.45 Crosstales.RTVoice.Demo.SendMessage Class Reference

[Simple](#) "SendMessage" example.

Inheritance diagram for Crosstales.RTVoice.Demo.SendMessage:



Public Member Functions

- void **Play** ()
- void **SpeakerA** ()
- IEnumerator **SpeakerB** ()
- void **Silence** ()

Public Attributes

- string **TextA** = "RT-Voice works great with PlayMaker, SALSA, Localized Dialogs/Cutscenes, Dialogue System for Unity and THE Dialogue Engine - that's awesome!"
- string **TextB** = "Absolutely true! RT-Voice is fantastic."
- float **DelayTextB** = 12.2f
- bool **PlayOnStart** = false

5.45.1 Detailed Description

[Simple](#) "SendMessage" example.

The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/crosstales/RTVoice/Demo/← Scripts/SendMessage.cs

5.46 Crosstales.RTVoice.Model.Sequence Class Reference

[Model](#) for a sequence.

Public Member Functions

- override string **ToString** ()

Public Attributes

- string **Text**
Text to speak.
- string **RTVoiceNameWindows** = string.Empty
Name of the RT-Voice under Windows (optional).
- string **RTVoiceNameMac** = string.Empty
Name of the RT-Voice under macOS (optional).
- string **RTVoiceNameAndroid** = string.Empty
Name of the RT-Voice under Android.
- string **RTVoiceNameIOS** = string.Empty
Name of the RT-Voice under iOS.
- **SpeakMode Mode** = SpeakMode.Speak
Speak mode (default = 'Speak').
- AudioSource **Source**
AudioSource for the output (optional).
- float **Rate** = 1f
<summary>Speech rate of the speaker in percent (1 = 100%, default: 1, optional).
- float **Pitch** = 1f
Speech pitch of the speaker in percent (1 = 100%, default: 1, optional, mobile only).
- float **Volume** = 1f
Volume of the speaker in percent (1 = 100%, default: 1, optional, Windows only).
- bool **initialized** = false

Properties

- string `RTVoiceName` [get]
Name of the RT-Voice.

5.46.1 Detailed Description

`Model` for a sequence.

5.46.2 Member Data Documentation

5.46.2.1 `SpeakMode` `Crosstales.RTVoice.Model.Sequence.Mode = SpeakMode.Speak`

Speak mode (default = 'Speak').

5.46.2.2 `float` `Crosstales.RTVoice.Model.Sequence.Pitch = 1f`

Speech pitch of the speaker in percent (1 = 100%, default: 1, optional, mobile only).

5.46.2.3 `float` `Crosstales.RTVoice.Model.Sequence.Rate = 1f`

<summarySpeech rate of the speaker in percent (1 = 100%, default: 1, optional).

5.46.2.4 `string` `Crosstales.RTVoice.Model.Sequence.RTVoiceNameAndroid = string.Empty`

Name of the RT-Voice under Android.

5.46.2.5 `string` `Crosstales.RTVoice.Model.Sequence.RTVoiceNameIOS = string.Empty`

Name of the RT-Voice under iOS.

5.46.2.6 `string` `Crosstales.RTVoice.Model.Sequence.RTVoiceNameMac = string.Empty`

Name of the RT-Voice under macOS (optional).

5.46.2.7 `string` `Crosstales.RTVoice.Model.Sequence.RTVoiceNameWindows = string.Empty`

Name of the RT-Voice under Windows (optional).

5.46.2.8 `AudioSource` `Crosstales.RTVoice.Model.Sequence.Source`

`AudioSource` for the output (optional).

5.46.2.9 string Crosstales.RTVoice.Model.Sequence.Text

Text to speak.

5.46.2.10 float Crosstales.RTVoice.Model.Sequence.Volume = 1f

Volume of the speaker in percent (1 = 100%, default: 1, optional, Windows only).

5.46.3 Property Documentation

5.46.3.1 string Crosstales.RTVoice.Model.Sequence.RTVoiceName [get]

Name of the RT-Voice.


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/crosstales/RTVoice/Plugins/↔ Scripts/Model/Sequence.cs

5.47 Crosstales.RTVoice.Demo.SequenceCaller Class Reference

[Simple](#) Sequence caller example.

Inheritance diagram for Crosstales.RTVoice.Demo.SequenceCaller:



Public Attributes

- GameObject **receiver**
- int **NumberOfSequences**
- float **SequenceDelay** = 1f

5.47.1 Detailed Description

[Simple](#) Sequence caller example.


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/crosstales/RTVoice/Demo/↔ Scripts/SequenceCaller.cs

5.48 Crosstales.RTVoice.Tool.Sequencer Class Reference

Simple sequencer.

Inheritance diagram for Crosstales.RTVoice.Tool.Sequencer:



Public Member Functions

- void [PlaySequence](#) (int index=0)
Plays a Sequence with a given index.
- void [PlayNextSequence](#) ()
Plays the next Sequence in the array.
- void [PlayAllSequences](#) ()
Plays all Sequences.
- void [StopAllSequences](#) ()
Stops and silences all active Sequences.

Public Attributes

- [Sequence\[\] Sequences](#)
All available sequences.
- string [Culture](#)
Fallback culture for all sequences (e.g. 'en', optional).
- float [Delay](#) = 0f
Delay in seconds before the [Sequencer](#) starts processing (default: 0).
- bool [PlayOnStart](#) = false
Run the [Sequencer](#) on start on/off (default: off).

Properties

- [Sequence CurrentSequence](#) [get]
Returns the current Sequence.

5.48.1 Detailed Description

Simple sequencer.

5.48.2 Member Function Documentation

5.48.2.1 void Crosstales.RTVoice.Tool.Sequencer.PlayAllSequences ()

Plays all Sequences.

5.48.2.2 void Crosstales.RTVoice.Tool.Sequencer.PlayNextSequence ()

Plays the next Sequence in the array.

5.48.2.3 void Crosstales.RTVoice.Tool.Sequencer.PlaySequence (int *index* = 0)

Plays a Sequence with a given index.

Parameters

<i>index</i>	Index of the Sequence (default: 0, optional).
--------------	---

5.48.2.4 void Crosstales.RTVoice.Tool.Sequencer.StopAllSequences ()

Stops and silences all active Sequences.

5.48.3 Member Data Documentation

5.48.3.1 string Crosstales.RTVoice.Tool.Sequencer.Culture

Fallback culture for all sequences (e.g. 'en', optional).

5.48.3.2 float Crosstales.RTVoice.Tool.Sequencer.Delay = 0f

Delay in seconds before the [Sequencer](#) starts processing (default: 0).

5.48.3.3 bool Crosstales.RTVoice.Tool.Sequencer.PlayOnStart = false

Run the [Sequencer](#) on start on/off (default: off).

5.48.3.4 Sequence [] Crosstales.RTVoice.Tool.Sequencer.Sequences

All available sequences.

5.48.4 Property Documentation

5.48.4.1 Sequence Crosstales.RTVoice.Tool.Sequencer.CurrentSequence [get]

Returns the current Sequence.


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/crosstales/RTVoice/Plugins/↔ Scripts/Tool/Sequencer.cs

5.49 PixelCrushers.DialogueSystem.SequencerCommands.SequencerCommandRTVoiceWait Class Reference

Sequencer command RTVoiceWait(). Waits for the current RT-Voice audio clip to finish.

Inheritance diagram for PixelCrushers.DialogueSystem.SequencerCommands.SequencerCommandRTVoiceWait:



Public Member Functions

- IEnumerator **Start** ()
- void **OnDestroy** ()

5.49.1 Detailed Description

Sequencer command RTVoiceWait(). Waits for the current RT-Voice audio clip to finish.


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/crosstailes/RTVoice/3rd party/Dialogue System/Scripts/SequencerCommandRTVoiceWait.cs

5.50 Crosstailes.RTVoice.EditorExt.SequencerEditor Class Reference

Custom editor for the 'Sequencer'-class.

Inheritance diagram for Crosstailes.RTVoice.EditorExt.SequencerEditor:



Public Member Functions

- override void **OnInspectorGUI** ()

5.50.1 Detailed Description

Custom editor for the 'Sequencer'-class.


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/crosstailes/RTVoice/Plugins/↔ Editor/SequencerEditor.cs

5.51 HutongGames.PlayMaker.Actions.Silence Class Reference

Silence-action for [PlayMaker](#).

Inheritance diagram for HutongGames.PlayMaker.Actions.Silence:



Public Member Functions

- override void **OnEnter** ()

5.51.1 Detailed Description

Silence-action for [PlayMaker](#).


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/crosstailes/RTVoice/3rd party/PlayMaker/Scripts/Silence.cs

5.52 Crosstailes.RTVoice.Demo.Simple Class Reference

[Simple](#) TTS example.

Inheritance diagram for Crosstailes.RTVoice.Demo.Simple:



Public Member Functions

- void **Play** ()
- void **SpeakerA** ()
- void **SpeakerB** ()
- void **Silence** ()

Public Attributes

- AudioSource **SourceA**
- AudioSource **SourceB**
- Text **TextSpeakerA**
- Text **TextSpeakerB**
- Text **PhonemeSpeakerA**
- Text **PhonemeSpeakerB**
- Text **VisemeSpeakerA**
- Text **VisemeSpeakerB**
- float **RateSpeakerA** = 1.25f
- float **RateSpeakerB** = 1.75f
- bool **PlayOnStart** = false

5.52.1 Detailed Description

[Simple](#) TTS example.


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/crosstales/RTVoice/Demo/↔ Scripts/Simple.cs

5.53 Crosstales.RTVoice.Demo.SimpleNative Class Reference

[Simple](#) native TTS example.

Inheritance diagram for Crosstales.RTVoice.Demo.SimpleNative:



Public Member Functions

- void **Play** ()
- void **SpeakerA** ()
- void **SpeakerB** ()
- void **SpeakerC** ()
- void **Silence** ()

Public Attributes

- Text **TextSpeakerA**
- Text **TextSpeakerB**
- Text **TextSpeakerC**
- Text **PhonemeSpeakerA**
- Text **PhonemeSpeakerB**
- Text **PhonemeSpeakerC**
- Text **VisemeSpeakerA**
- Text **VisemeSpeakerB**
- Text **VisemeSpeakerC**
- float **RateSpeakerA** = 1.25f
- float **RateSpeakerB** = 1.75f
- float **RateSpeakerC** = 2.5f
- bool **PlayOnStart** = false

5.53.1 Detailed Description

[Simple](#) native TTS example.


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd_party/RTVoice_3rd_party/Assets/crosstales/RTVoice/Demo/Scripts/SimpleNative.cs

5.54 HutongGames.PlayMaker.Actions.Speak Class Reference

Speak-action for [PlayMaker](#).

Inheritance diagram for HutongGames.PlayMaker.Actions.Speak:



Public Member Functions

- override void **OnEnter** ()

Public Attributes

- FsmString `Text` = "Hello world!"
Text to speak.
- FsmString `RTVoiceNameWindows` = "Microsoft David Desktop"
Name of the RT-Voice under Windows.
- FsmString `RTVoiceNameMac` = "Alex"
Name of the RT-Voice under macOS.
- FsmString `RTVoiceNameAndroid` = string.Empty
Name of the RT-Voice under Android.
- FsmString `RTVoiceNameIOS` = "Daniel"
Name of the RT-Voice under iOS.
- FsmString `Culture` = "en"
Fallback culture (e.g. 'en', optional).

Additional Inherited Members

5.54.1 Detailed Description

Speak-action for [PlayMaker](#).

5.54.2 Member Data Documentation

5.54.2.1 FsmString HutongGames.PlayMaker.Actions.Speak.Culture = "en"

Fallback culture (e.g. 'en', optional).

5.54.2.2 FsmString HutongGames.PlayMaker.Actions.Speak.RTVoiceNameAndroid = string.Empty

Name of the RT-Voice under Android.

5.54.2.3 FsmString HutongGames.PlayMaker.Actions.Speak.RTVoiceNameIOS = "Daniel"

Name of the RT-Voice under iOS.

5.54.2.4 FsmString HutongGames.PlayMaker.Actions.Speak.RTVoiceNameMac = "Alex"

Name of the RT-Voice under macOS.

5.54.2.5 FsmString HutongGames.PlayMaker.Actions.Speak.RTVoiceNameWindows = "Microsoft David Desktop"

Name of the RT-Voice under Windows.

5.54.2.6 FsmString HutongGames.PlayMaker.Actions.Speak.Text = "Hello world!"


Text to speak.

The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/crosstaes/RTVoice/3rd party/PlayMaker/Scripts/Speak.cs

5.55 Crosstaes.RTVoice.SALSA.Speak Class Reference

Inheritance diagram for Crosstaes.RTVoice.SALSA.Speak:



Public Member Functions

- void **Talk** ()

Public Attributes

- AudioSource **Source**
- Salsa3D **Salsa**
- InputField **EnterText**
- Slider **RateSlider**
- Slider **PitchSlider**


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/crosstaes/RTVoice/3rd party/SALSA/Scripts/Speak.cs

5.56 HutongGames.PlayMaker.Actions.SpeakBase Class Reference

Base for Speak-actions in [PlayMaker](#).

Inheritance diagram for HutongGames.PlayMaker.Actions.SpeakBase:



Public Member Functions

- override void **OnEnter** ()

Public Attributes

- FsmEvent **sendEvent**
- [SpeakMode](#) **Mode**
[Speak](#) mode (default = [Speak](#)).
- FsmGameObject [AudioSource](#)
AudioSource for the output (optional).
- FsmFloat [Rate](#) = 1
Speech rate of the speaker in percent (1 = 100%, default: 1, optional).
- FsmFloat [Pitch](#) = 1f
Speech pitch of the speaker in percent (1 = 100%, default: 1, optional, mobile only).
- FsmFloat [Volume](#) = 1
Volume of the speaker in percent (1 = 100%, default: 1, optional).

Protected Member Functions

- void **subscribeEvents** ()
- void **unsubscribeEvents** ()

Protected Attributes

- Guid **uid**

5.56.1 Detailed Description

Base for Speak-actions in [PlayMaker](#).

5.56.2 Member Data Documentation

5.56.2.1 FsmGameObject HutongGames.PlayMaker.Actions.SpeakBase.AudioSource

AudioSource for the output (optional).

5.56.2.2 [SpeakMode](#) HutongGames.PlayMaker.Actions.SpeakBase.Mode

[Speak](#) mode (default = [Speak](#)).

5.56.2.3 FsmFloat HutongGames.PlayMaker.Actions.SpeakBase.Pitch = 1f

Speech pitch of the speaker in percent (1 = 100%, default: 1, optional, mobile only).

5.56.2.4 FsmFloat HutongGames.PlayMaker.Actions.SpeakBase.Rate = 1

Speech rate of the speaker in percent (1 = 100%, default: 1, optional).

5.56.2.5 FsmFloat HutongGames.PlayMaker.Actions.SpeakBase.Volume = 1

Volume of the speaker in percent (1 = 100%, default: 1, optional).


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/crosstailes/RTVoice/3rd party/PlayMaker/Scripts/SpeakBase.cs

5.57 Crosstailes.RTVoice.PlayMaker.SpeakEditor Class Reference

Custom editor for the Speak-action.

Inheritance diagram for Crosstailes.RTVoice.PlayMaker.SpeakEditor:



Public Member Functions

- override void **OnEnable** ()
- override bool **OnGUI** ()

5.57.1 Detailed Description

Custom editor for the Speak-action.


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/crosstailes/RTVoice/3rd party/PlayMaker/Editor/SpeakEditor.cs

5.58 Crosstailes.RTVoice.Speaker Class Reference

Main component of [RTVoice](#).

Inheritance diagram for Crosstailes.RTVoice.Speaker:



Public Member Functions

- delegate void **SpeakNativeCurrentWord** (object sender, [CurrentWordEventArgs](#) e)
- delegate void **SpeakNativeCurrentPhoneme** (object sender, [CurrentPhonemeEventArgs](#) e)
- delegate void **SpeakNativeCurrentViseme** (object sender, [CurrentVisemeEventArgs](#) e)
- delegate void **SpeakNativeStart** (object sender, [SpeakNativeEventArgs](#) e)
- delegate void **SpeakNativeComplete** (object sender, [SpeakNativeEventArgs](#) e)
- delegate void **SpeakStart** (object sender, [SpeakEventArgs](#) e)
- delegate void **SpeakComplete** (object sender, [SpeakEventArgs](#) e)
- delegate void **SpeakAudioGenerationStart** (object sender, [SpeakEventArgs](#) e)
- delegate void **SpeakAudioGenerationComplete** (object sender, [SpeakEventArgs](#) e)
- delegate void **ErrorInfo** (string info)

Static Public Member Functions

- static float [ApproximateSpeechLength](#) (string text, float rate=1f, float wordsPerMinute=175f, float time←Factor=0.9f)
Approximates the speech length in seconds of a given text and rate. Note: This is an experimental method and doesn't provide an exact value; +/- 15% is "normal"!
- static List< [Voice](#) > [VoicesForCulture](#) (string culture)
Get all available voices for a given culture from the current TTS-system.
- static [Voice](#) [VoiceForCulture](#) (string culture, int index=0)
Get a voice from for a given culture and otional index from the current TTS-system.
- static [Voice](#) [VoiceForName](#) (string name)
Get a voice for a given name from the current TTS-system.
- static Guid [SpeakNative](#) (string text, [Voice](#) voice=null, float rate=1f, float volume=1f, float pitch=1f)
Speaks a text with a given voice (native mode).
- static void [SpeakNativeWithUID](#) ([WrapperNative](#) wrapper)
Speaks a text with a given voice (native mode).
- static Guid [SpeakNative](#) ([WrapperNative](#) wrapper)
Speaks a text with a given wrapper (native mode).
- static Guid [Speak](#) (string text, AudioSource source=null, [Voice](#) voice=null, bool speakImmediately=true, float rate=1f, float volume=1f, string outputFile="", float pitch=1f)
Speaks a text with a given voice.
- static void [SpeakWithUID](#) ([Wrapper](#) wrapper)
Speaks a text with a given voice.
- static Guid [Speak](#) ([Wrapper](#) wrapper)
Speaks a text with a given wrapper.
- static void [SpeakMarkedWordsWithUID](#) (Guid uid, string text, AudioSource source, [Voice](#) voice=null, float rate=1f, float pitch=1f)
Speaks a text with a given voice and tracks the word position.
- static void [Silence](#) ()
Silence all active TTS-voices.
- static void [Silence](#) (Guid uid)
Silence an active TTS-voice with a UID.

Properties

- static string [AudioFileExtension](#) [get]
Returns the extension of the generated audio files.
- static List< [Voice](#) > [Voices](#) [get]
Get all available voices from the current TTS-system.
- static List< string > [Cultures](#) [get]
Get all available cultures from the current TTS-system..
- static bool [isTTSAvailable](#) [get]
Checks if TTS is available on this system.

Events

- static SpeakNativeCurrentWord [OnSpeakNativeCurrentWord](#)
An event triggered whenever a new word is spoken (native mode).
- static SpeakNativeCurrentPhoneme [OnSpeakNativeCurrentPhoneme](#)
An event triggered whenever a new phoneme is spoken (native mode).
- static SpeakNativeCurrentViseme [OnSpeakNativeCurrentViseme](#)
An event triggered whenever a new viseme is spoken (native mode).
- static SpeakNativeStart [OnSpeakNativeStart](#)
An event triggered whenever a native speak is started.
- static SpeakNativeComplete [OnSpeakNativeComplete](#)
An event triggered whenever a native speak is completed.
- static SpeakStart [OnSpeakStart](#)
An event triggered whenever a speak is started.
- static SpeakComplete [OnSpeakComplete](#)
An event triggered whenever a native speak is completed.
- static SpeakAudioGenerationStart [OnSpeakAudioGenerationStart](#)
An event triggered whenever a speak audio generation is started.
- static SpeakAudioGenerationComplete [OnSpeakAudioGenerationComplete](#)
An event triggered whenever a speak audio generation is completed.
- static ErrorInfo [OnErrorInfo](#)
An event triggered whenever an error occurs.

5.58.1 Detailed Description

Main component of [RTVoice](#).

5.58.2 Member Function Documentation

- 5.58.2.1 static float [Crosstales.RTVoice.Speaker.ApproximateSpeechLength](#) (string *text*, float *rate* = 1f, float *wordsPerMinute* = 175f, float *timeFactor* = 0.9f) [static]

Approximates the speech length in seconds of a given text and rate. Note: This is an experimental method and doesn't provide an exact value; +/- 15% is "normal"!

Parameters

<i>text</i>	Text for the length approximation.
<i>rate</i>	Speech rate of the speaker in percent for the length approximation (1 = 100%, default: 1, optional).
<i>wordsPerMinute</i>	Words per minute (default: 175, optional).
<i>timeFactor</i>	Time factor for the calculated value (default: 0.9, optional).

Returns

Approximated speech length in seconds of the given text and rate.

5.58.2.2 static void Crosstales.RTVoice.Speaker.Silence () [static]

Silence all active TTS-voices.

5.58.2.3 static void Crosstales.RTVoice.Speaker.Silence (Guid uid) [static]

Silence an active TTS-voice with a UID.

Parameters

<i>uid</i>	UID of the speaker
------------	--------------------

5.58.2.4 static Guid Crosstales.RTVoice.Speaker.Speak (string text, AudioSource source = null, Voice voice = null, bool speakImmediately = true, float rate = 1f, float volume = 1f, string outputFile = "", float pitch = 1f) [static]

Speaks a text with a given voice.

Parameters

<i>text</i>	Text to speak.
<i>source</i>	AudioSource for the output (optional).
<i>voice</i>	Voice to speak (optional).
<i>speakImmediately</i>	Speak the text immediately (default: true).
<i>rate</i>	Speech rate of the speaker in percent (1 = 100%, default: 1, optional).
<i>pitch</i>	Pitch of the speech (1 = 100%, default: 1, optional).
<i>volume</i>	Volume of the speaker in percent (1 = 100%, default: 1, optional).

///

Parameters

<i>outputFile</i>	Saves the generated audio to an output file (optional).
<i>pitch</i>	Pitch of the speech in percent (1 = 100%, default: 1, optional).

Returns

UID of the speaker.

5.58.2.5 static Guid Crosstales.RTVoice.Speaker.Speak (Wrapper wrapper) [static]

Speaks a text with a given wrapper.

Parameters

<i>wrapper</i>	Speak wrapper.
----------------	----------------

Returns

UID of the speaker.

5.58.2.6 static void Crosstales.RTVoice.Speaker.SpeakMarkedWordsWithUID (Guid uid, string text, AudioSource source, Voice voice = null, float rate = 1f, float pitch = 1f) [static]

Speaks a text with a given voice and tracks the word position.

Parameters

<i>uid</i>	UID of the speaker
<i>text</i>	Text to speak.
<i>source</i>	AudioSource for the output.
<i>voice</i>	Voice to speak (optional).
<i>rate</i>	Speech rate of the speaker in percent (1 = 100%, default: 1, optional).
<i>pitch</i>	Pitch of the speech in percent (1 = 100%, default: 1, optional).

5.58.2.7 static Guid Crosstales.RTVoice.Speaker.SpeakNative (string text, Voice voice = null, float rate = 1f, float volume = 1f, float pitch = 1f) [static]

Speaks a text with a given voice (native mode).

Parameters

<i>text</i>	Text to speak.
<i>voice</i>	Voice to speak (optional).
<i>rate</i>	Speech rate of the speaker in percent (1 = 100%, default: 1, optional).
<i>volume</i>	Volume of the speaker in percent (1 = 100%, default: 1, optional).
<i>pitch</i>	Pitch of the speech in percent (1 = 100%, default: 1, optional).

Returns

UID of the speaker.

5.58.2.8 static Guid Crosstales.RTVoice.Speaker.SpeakNative (WrapperNative *wrapper*) [static]

Speaks a text with a given wrapper (native mode).

Parameters

<i>wrapper</i>	Speak wrapper.
----------------	----------------

Returns

UID of the speaker.

5.58.2.9 static void Crosstales.RTVoice.Speaker.SpeakNativeWithUID (WrapperNative *wrapper*) [static]

Speaks a text with a given voice (native mode).

Parameters

<i>wrapper</i>	Speak wrapper.
----------------	----------------

5.58.2.10 static void Crosstales.RTVoice.Speaker.SpeakWithUID (Wrapper *wrapper*) [static]

Speaks a text with a given voice.

Parameters

<i>wrapper</i>	Speak wrapper.
----------------	----------------

5.58.2.11 static Voice Crosstales.RTVoice.Speaker.VoiceForCulture (string *culture*, int *index* = 0) [static]

Get a voice from for a given culture and otional index from the current TTS-system.

Parameters

<i>culture</i>	Culture of the voice (e.g. "en")
<i>index</i>	Index of the voice (default = 0, optional)

Returns

Voice for the given culture and index.

5.58.2.12 static Voice Crosstales.RTVoice.Speaker.VoiceForName (string *name*) [static]

Get a voice for a given name from the current TTS-system.

Parameters

<i>name</i>	Name of the voice (e.g. "Alex")
-------------	---------------------------------

Returns

Voice for the given name or null if not found.

5.58.2.13 `static List<Voice> Crosstales.RTVoice.Speaker.VoicesForCulture (string culture) [static]`

Get all available voices for a given culture from the current TTS-system.

Parameters

<i>culture</i>	Culture of the voice (e.g. "en")
----------------	----------------------------------

Returns

All available voices (alphabetically ordered by 'Name') for a given culture as a list.

5.58.3 Property Documentation

5.58.3.1 `string Crosstales.RTVoice.Speaker.AudioFileExtension [static], [get]`

Returns the extension of the generated audio files.

Returns

Extension of the generated audio files.

5.58.3.2 `List<string> Crosstales.RTVoice.Speaker.Cultures [static], [get]`

Get all available cultures from the current TTS-system..

Returns

All available cultures (alphabetically ordered by 'Culture') as a list.

5.58.3.3 `bool Crosstales.RTVoice.Speaker.isTTSAvailable [static], [get]`

Checks if TTS is available on this system.

Returns

True if TTS is available on this system.

5.58.3.4 List<Voice> Crosstales.RTVoice.Speaker.Voices [static], [get]

Get all available voices from the current TTS-system.

Returns

All available voices (alphabetically ordered by 'Name') as a list.

5.58.4 Event Documentation

5.58.4.1 ErrorInfo Crosstales.RTVoice.Speaker.OnErrorInfo [static]

An event triggered whenever an error occurs.

5.58.4.2 SpeakAudioGenerationComplete Crosstales.RTVoice.Speaker.OnSpeakAudioGenerationComplete [static]

An event triggered whenever a speak audio generation is completed.

5.58.4.3 SpeakAudioGenerationStart Crosstales.RTVoice.Speaker.OnSpeakAudioGenerationStart [static]

An event triggered whenever a speak audio generation is started.

5.58.4.4 SpeakComplete Crosstales.RTVoice.Speaker.OnSpeakComplete [static]

An event triggered whenever a native speak is completed.

5.58.4.5 SpeakNativeComplete Crosstales.RTVoice.Speaker.OnSpeakNativeComplete [static]

An event triggered whenever a native speak is completed.

5.58.4.6 SpeakNativeCurrentPhoneme Crosstales.RTVoice.Speaker.OnSpeakNativeCurrentPhoneme [static]

An event triggered whenever a new phoneme is spoken (native mode).

5.58.4.7 SpeakNativeCurrentViseme Crosstales.RTVoice.Speaker.OnSpeakNativeCurrentViseme [static]

An event triggered whenever a new viseme is spoken (native mode).

5.58.4.8 SpeakNativeCurrentWord Crosstales.RTVoice.Speaker.OnSpeakNativeCurrentWord [static]

An event triggered whenever a new word is spoken (native mode).

5.58.4.9 `SpeakNativeStart` `Crosstales.RTVoice.Speaker.OnSpeakNativeStart` [static]

An event triggered whenever a native speak is started.

5.58.4.10 `SpeakStart` `Crosstales.RTVoice.Speaker.OnSpeakStart` [static]

An event triggered whenever a speak is started.


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/crosstales/RTVoice/Plugins/↔ Scripts/Speaker.cs

5.59 `Crosstales.RTVoice.EditorExt.SpeakerEditor` Class Reference

Custom editor for the '[Speaker](#)'-class.

Inheritance diagram for `Crosstales.RTVoice.EditorExt.SpeakerEditor`:



Public Member Functions

- override void **OnInspectorGUI** ()

5.59.1 Detailed Description

Custom editor for the '[Speaker](#)'-class.


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/crosstales/RTVoice/Plugins/↔ Editor/SpeakerEditor.cs

5.60 `Crosstales.RTVoice.Model.Event.SpeakEventArgs` Class Reference

EventArgs and base class for all speaker events.

Inheritance diagram for `Crosstales.RTVoice.Model.Event.SpeakEventArgs`:



Public Member Functions

- **SpeakEventArgs** ([Wrapper](#) wrapper)
- override string **ToString** ()

Public Attributes

- [Wrapper](#) [Wrapper](#)
[Wrapper](#) with "Speak"-function call.

5.60.1 Detailed Description

EventArgs and base class for all speaker events.

5.60.2 Member Data Documentation

5.60.2.1 [Wrapper](#) Crosstales.RTVoice.Model.Event.SpeakEventArgs.Wrapper

[Wrapper](#) with "Speak"-function call.


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/crosstales/RTVoice/Plugins/↔ Scripts/Model/Event/SpeakEventArgs.cs

5.61 Crosstales.RTVoice.Model.Event.SpeakNativeEventArgs Class Reference

EventArgs and base class for all speaker (native) events.

Inheritance diagram for Crosstales.RTVoice.Model.Event.SpeakNativeEventArgs:



Public Member Functions

- **SpeakNativeEventArgs** ([WrapperNative](#) wrapper)
- override string **ToString** ()

Public Attributes

- [WrapperNative](#) [Wrapper](#)
[Wrapper](#) with "SpeakNative"-function call.

5.61.1 Detailed Description

EventArgs and base class for all speaker (native) events.

5.61.2 Member Data Documentation

5.61.2.1 WrapperNative Crosstales.RTVoice.Model.Event.SpeakNativeEventArgs.Wrapper

[Wrapper](#) with "SpeakNative"-function call.


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/crosstales/RTVoice/Plugins/↔ Scripts/Model/Event/SpeakNativeEventArgs.cs

5.62 HutongGames.PlayMaker.Actions.SpeakUI Class Reference

Speak-action for UI-components in [PlayMaker](#).

Inheritance diagram for HutongGames.PlayMaker.Actions.SpeakUI:



Public Member Functions

- override void **OnEnter** ()

Public Attributes

- InputField [Text](#)
Text to speak.
- InputField [RTVoiceName](#)
Name of the RT-Voice.
- FsmString [Culture](#) = "en"
Fallback culture (e.g. 'en', optional).

Additional Inherited Members

5.62.1 Detailed Description

Speak-action for UI-components in [PlayMaker](#).

5.62.2 Member Data Documentation

5.62.2.1 FsmString HutongGames.PlayMaker.Actions.SpeakUI.Culture = "en"

Fallback culture (e.g. 'en', optional).

5.62.2.2 InputField HutongGames.PlayMaker.Actions.SpeakUI.RTVoiceName

Name of the RT-Voice.

5.62.2.3 InputField HutongGames.PlayMaker.Actions.SpeakUI.Text

Text to speak.


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/crosstales/RTVoice/3rd party/PlayMaker/Scripts/SpeakUI.cs

5.63 Crosstales.RTVoice.PlayMaker.SpeakUIEditor Class Reference

Custom editor for the SpeakUI-action.

Inheritance diagram for Crosstales.RTVoice.PlayMaker.SpeakUIEditor:



Public Member Functions

- override void **OnEnable** ()
- override bool **OnGUI** ()

5.63.1 Detailed Description

Custom editor for the SpeakUI-action.


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/crosstales/RTVoice/3rd party/PlayMaker/Editor/SpeakUIEditor.cs

5.64 Crosstales.RTVoice.Demo.SpeakWrapper Class Reference

Warapper for the dynamic speakers.

Inheritance diagram for Crosstales.RTVoice.Demo.SpeakWrapper:



Public Member Functions

- void **Start** ()
- void **Speak** ()

Public Attributes

- Voice **SpeakerVoice**
- InputField **Input**
- Text **Label**
- AudioSource **Audio**

5.64.1 Detailed Description

Warapper for the dynamic speakers.


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/crosstales/RTVoice/Demo/↔ Scripts/SpeakWrapper.cs

5.65 Crosstales.RTVoice.Tool.SpeechText Class Reference

Allows to speak and store generated audio.

Inheritance diagram for Crosstales.RTVoice.Tool.SpeechText:



Public Member Functions

- void **Speak** ()
- void **Silence** ()

Public Attributes

- string **Text** = "Hello world!"
Text to speak.
- string **RTVoiceNameWindows** = "Microsoft David Desktop"
Name of the RT-Voice under Windows (optional).
- string **RTVoiceNameMac** = "Alex"
Name of the RT-Voice under macOS (optional).
- string **RTVoiceNameAndroid** = string.Empty
Name of the RT-Voice under Android.
- string **RTVoiceNameIOS** = "Daniel"
Name of the RT-Voice under iOS.
- **SpeakMode Mode** = SpeakMode.Speak
Speak mode (default = Speak).
- string **Culture** = "en"
Fallback culture for the text (e.g. 'en', optional).
- AudioSource **Source**
AudioSource for the output (optional).
- float **Rate** = 1f
Speech rate of the speaker in percent (1 = 100%, default: 1, optional).
- float **Pitch** = 1f
Speech pitch of the speaker in percent (1 = 100%, default: 1, optional, mobile only).
- float **Volume** = 1f
Volume of the speaker in percent (1 = 100%, default: 1, optional, Windows only).
- bool **PlayOnStart** = false
Speak this text on start on/off (default: off).
- bool **GenerateAudioFile** = false
Generate audio file on/off (default: off).
- string **FilePath** = @"_generatedAudio/"
File path for the generated audio.
- string **FileName** = "RTVGeneratedAudio"
File name of the generated audio.
- bool **FileInsideAssets** = true
Is the generated file path inside the Assets-folder (current project)? If this option is enabled, it prefixes the path with 'Application.dataPath'.

Properties

- string **RTVoiceName** [get]
Name of the RT-Voice.

5.65.1 Detailed Description

Allows to speak and store generated audio.

5.65.2 Member Data Documentation

5.65.2.1 `string Crosstales.RTVoice.Tool.SpeechText.Culture = "en"`

Fallback culture for the text (e.g. 'en', optional).

5.65.2.2 `bool Crosstales.RTVoice.Tool.SpeechText.FileInsideAssets = true`

Is the generated file path inside the Assets-folder (current project)? If this option is enabled, it prefixes the path with 'Application.dataPath'.

5.65.2.3 `string Crosstales.RTVoice.Tool.SpeechText.FileName = "RTVGeneratedAudio"`

File name of the generated audio.

5.65.2.4 `string Crosstales.RTVoice.Tool.SpeechText.FilePath = @"_generatedAudio/"`

File path for the generated audio.

5.65.2.5 `bool Crosstales.RTVoice.Tool.SpeechText.GenerateAudioFile = false`

Generate audio file on/off (default: off).

5.65.2.6 `SpeakMode Crosstales.RTVoice.Tool.SpeechText.Mode = SpeakMode.Speak`

Speak mode (default = Speak).

5.65.2.7 `float Crosstales.RTVoice.Tool.SpeechText.Pitch = 1f`

Speech pitch of the speaker in percent (1 = 100%, default: 1, optional, mobile only).

5.65.2.8 `bool Crosstales.RTVoice.Tool.SpeechText.PlayOnStart = false`

Speak this text on start on/off (default: off).

5.65.2.9 `float Crosstales.RTVoice.Tool.SpeechText.Rate = 1f`

Speech rate of the speaker in percent (1 = 100%, default: 1, optional).

5.65.2.10 `string Crosstales.RTVoice.Tool.SpeechText.RTVoiceNameAndroid = string.Empty`

Name of the RT-Voice under Android.

5.65.2.11 `string Crosstales.RTVoice.Tool.SpeechText.RTVoiceNameIOS = "Daniel"`

Name of the RT-Voice under iOS.

5.65.2.12 `string Crosstales.RTVoice.Tool.SpeechText.RTVoiceNameMac = "Alex"`

Name of the RT-Voice under macOS (optional).

5.65.2.13 `string Crosstales.RTVoice.Tool.SpeechText.RTVoiceNameWindows = "Microsoft David Desktop"`

Name of the RT-Voice under Windows (optional).

5.65.2.14 `AudioSource Crosstales.RTVoice.Tool.SpeechText.Source`

AudioSource for the output (optional).

5.65.2.15 `string Crosstales.RTVoice.Tool.SpeechText.Text = "Hello world!"`

Text to speak.

5.65.2.16 `float Crosstales.RTVoice.Tool.SpeechText.Volume = 1f`

Volume of the speaker in percent (1 = 100%, default: 1, optional, Windows only).

5.65.3 Property Documentation

5.65.3.1 `string Crosstales.RTVoice.Tool.SpeechText.RTVoiceName` `[get]`

Name of the RT-Voice.


The documentation for this class was generated from the following file:

- `D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/crosstales/RTVoice/Plugins/Scripts/Tool/SpeechText.cs`

5.66 Crosstales.RTVoice.EditorExt.SpeechTextEditor Class Reference

Custom editor for the 'SpeechText'-class.

Inheritance diagram for Crosstales.RTVoice.EditorExt.SpeechTextEditor:



Public Member Functions

- override void **OnInspectorGUI** ()

5.66.1 Detailed Description

Custom editor for the 'SpeechText'-class.


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/crosstales/RTVoice/Plugins/Editor/SpeechTextEditor.cs

5.67 Crosstales.RTVoice.UDEA2.UDEAConnector Class Reference

Connects UDEA and RT-Voice. Must be placed on a dialogue prefab.

Inheritance diagram for Crosstales.RTVoice.UDEA2.UDEAConnector:



Public Member Functions

- void **SpeakRT** ()

Public Attributes

- [UDEAVoiceWrapper\[\] Voices](#)
Voices for the UDEA-characters (optional).
- string [Culture](#)
Fallback culture for all sequences (e.g. 'en', optional).

5.67.1 Detailed Description

Connects UDEA and RT-Voice. Must be placed on a dialogue prefab.

5.67.2 Member Data Documentation

5.67.2.1 string Crosstales.RTVoice.UDEA2.UDEAConnector.Culture

Fallback culture for all sequences (e.g. 'en', optional).

5.67.2.2 UDEAVoiceWrapper [] Crosstales.RTVoice.UDEA2.UDEAConnector.Voices

Voices for the UDEA-characters (optional).


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/crosstales/RTVoice/3rd party/THE Dialogue Engine/Scripts/UDEAConnector.cs

5.68 Crosstales.RTVoice.UDEA2.UDEAConnectorEditor Class Reference

Custom editor for the '[UDEAConnector](#)'-class.

Inheritance diagram for Crosstales.RTVoice.UDEA2.UDEAConnectorEditor:



Public Member Functions

- override void **OnInspectorGUI** ()

5.68.1 Detailed Description

Custom editor for the '[UDEAConnector](#)'-class.

The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/crosstales/RTVoice/3rd party/THE Dialogue Engine/Editor/UDEAConnectorEditor.cs

5.69 Crosstales.RTVoice.UDEA2.UDEAVoiceWrapper Class Reference

Wrapper for an UDEA-character to an RT-Voice.

Public Member Functions

- override string **ToString** ()

Public Attributes

- string `UDEAVoiceName` = string.Empty
"Name of the UDEA-character on-screen."
- string `RTVoiceNameWindows` = string.Empty
"Name of the RT-Voice under Windows."
- string `RTVoiceNameMac` = string.Empty
Name of the RT-Voice under macOS.
- string `RTVoiceNameAndroid` = string.Empty
Name of the RT-Voice under Android.
- string `RTVoiceNameiOS` = string.Empty
Name of the RT-Voice under iOS.
- AudioSource `Source`
Origin AudioSource (optional).
- float `Rate` = 1f
Speech rate of the speaker in percent (1 = 100%, default: 1, optional).
- float `Pitch` = 1f
Speech pitch of the speaker in percent (1 = 100%, default: 1, optional, mobile only).
- float `Volume` = 1f
Volume of the speaker in percent (1 = 100%, default: 1, optional).
- bool `IgnoreCharacter` = false
Ignore this character (default: off).
- bool `initialized` = false

Properties

- string `RTVoiceName` [get]
Name of the RT-Voice.

5.69.1 Detailed Description

Wrapper for an UDEA-character to an RT-Voice.

5.69.2 Member Data Documentation

5.69.2.1 bool Crosstales.RTVoice.UDEA2.UDEAVoiceWrapper.IgnoreCharacter = false

Ignore this character (default: off).

5.69.2.2 float Crosstales.RTVoice.UDEA2.UDEAVoiceWrapper.Pitch = 1f

Speech pitch of the speaker in percent (1 = 100%, default: 1, optional, mobile only).

5.69.2.3 float Crosstales.RTVoice.UDEA2.UDEAVoiceWrapper.Rate = 1f

Speech rate of the speaker in percent (1 = 100%, default: 1, optional).

5.69.2.4 `string Crosstales.RTVoice.UDEA2.UDEAVoiceWrapper.RTVoiceNameAndroid = string.Empty`

Name of the RT-Voice under Android.

5.69.2.5 `string Crosstales.RTVoice.UDEA2.UDEAVoiceWrapper.RTVoiceNameIOS = string.Empty`

Name of the RT-Voice under iOS.

5.69.2.6 `string Crosstales.RTVoice.UDEA2.UDEAVoiceWrapper.RTVoiceNameMac = string.Empty`

Name of the RT-Voice under macOS.

5.69.2.7 `string Crosstales.RTVoice.UDEA2.UDEAVoiceWrapper.RTVoiceNameWindows = string.Empty`

"Name of the RT-Voice under Windows.

5.69.2.8 `AudioSource Crosstales.RTVoice.UDEA2.UDEAVoiceWrapper.Source`

Origin AudioSource (optional).

5.69.2.9 `string Crosstales.RTVoice.UDEA2.UDEAVoiceWrapper.UDEAVoiceName = string.Empty`

"Name of the UDEA-character on-screen.

5.69.2.10 `float Crosstales.RTVoice.UDEA2.UDEAVoiceWrapper.Volume = 1f`

Volume of the speaker in percent (1 = 100%, default: 1, optional).

5.69.3 Property Documentation

5.69.3.1 `string Crosstales.RTVoice.UDEA2.UDEAVoiceWrapper.RTVoiceName` [get]

Name of the RT-Voice.

The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/crosstales/RTVoice/3rd party/THE Dialogue Engine/Scripts/UDEAVoiceWrapper.cs

5.70 Crosstales.RTVoice.EditorExt.UpdateCheck Class Reference

Checks for updates of the asset.

Static Public Member Functions

- static void **UpdateCheckForEditor** (out string result)

Public Attributes

- const string **TEXT_NOT_CHECKED** = "Not checked."
- const string **TEXT_NO_UPDATE** = "No update available - you are using the latest version."

5.70.1 Detailed Description

Checks for updates of the asset.

The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/crosstales/RTVoice/Plugins/↔ Editor/UpdateCheck.cs

5.71 Crosstales.RTVoice.Model.Voice Class Reference

[Model](#) for a voice.

Public Member Functions

- [Voice](#) (string name, string description, string gender, string age, string culture)
Instantiate the class.
- [Voice](#) (string name, string description, string culture)
Instantiate the class.
- string [ToShortString](#) ()
Returns a short ToString()-variant.
- override string **ToString** ()

Public Attributes

- string [Name](#)
Name of the RT-Voice.
- string [Description](#) = string.Empty
Description of the RT-Voice.
- string [Gender](#) = string.Empty
Gender of the RT-Voice (Windows only).
- string [Age](#) = string.Empty
Age of the RT-Voice (Windows only).
- string [Culture](#) = string.Empty
Culture of the RT-Voice.

5.71.1 Detailed Description

[Model](#) for a voice.

5.71.2 Constructor & Destructor Documentation

5.71.2.1 Crosstales.RTVoice.Model.Voice.Voice (string name, string description, string gender, string age, string culture)

Instantiate the class.

Parameters

<i>name</i>	Name of the RT-Voice.
<i>description</i>	Description of the RT-Voice.
<i>gender</i>	Gender of the RT-Voice (Windows only).
<i>age</i>	Age of the RT-Voice (Windows only).
<i>culture</i>	Culture of the RT-Voice.

5.71.2.2 Crosstales.RTVoice.Model.Voice.Voice (*string name*, *string description*, *string culture*)

Instantiate the class.

Parameters

<i>name</i>	Name of the RT-Voice.
<i>description</i>	Description of the RT-Voice.
<i>culture</i>	Culture of the RT-Voice.

5.71.3 Member Function Documentation

5.71.3.1 *string* Crosstales.RTVoice.Model.Voice.ToShortString ()

Returns a short ToString()-variant.

Returns

Returns a short ToString()-variant.

5.71.4 Member Data Documentation

5.71.4.1 *string* Crosstales.RTVoice.Model.Voice.Age = *string.Empty*

Age of the RT-Voice (Windows only).

5.71.4.2 *string* Crosstales.RTVoice.Model.Voice.Culture = *string.Empty*

Culture of the RT-Voice.

5.71.4.3 *string* Crosstales.RTVoice.Model.Voice.Description = *string.Empty*

Description of the RT-Voice.

5.71.4.4 string Crosstales.RTVoice.Model.Voice.Gender = string.Empty

Gender of the RT-Voice (Windows only).

5.71.4.5 string Crosstales.RTVoice.Model.Voice.Name

Name of the RT-Voice.

The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/crosstales/RTVoice/Plugins/Scripts/Model/Voice.cs

5.72 PixelCrushers.DialogueSystem.RTVoiceActor.VoicePreference Class Reference

Public Attributes

- string **language**
- string **name**
- Gender **gender**
- int **minAge** = 0
- int **maxAge** = 100


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/crosstales/RTVoice/3rd party/Dialogue System/Scripts/RTVoiceActor.cs

5.73 Crosstales.RTVoice.Provider.VoiceProviderAndroid Class Reference

Android voice provider.

Inheritance diagram for Crosstales.RTVoice.Provider.VoiceProviderAndroid:



Public Member Functions

- override IEnumerator **SpeakNative** ([WrapperNative](#) wrapper)
The current provider speaks a text with a given voice (native mode).
- override IEnumerator **Speak** ([Wrapper](#) wrapper)
The current provider speaks a text with a given voice.
- override void **Silence** ()
Silence all active TTS-providers.
- void **ShutdownTTS** ()

Properties

- override string **AudioFileExtension** [get]
- override List< [Voice](#) > **Voices** [get]

Additional Inherited Members

5.73.1 Detailed Description

Android voice provider.

5.73.2 Member Function Documentation

5.73.2.1 override void Crosstales.RTVoice.Provider.VoiceProviderAndroid.Silence () [virtual]

Silence all active TTS-providers.

Reimplemented from [Crosstales.RTVoice.Provider.BaseVoiceProvider](#).

5.73.2.2 override IEnumerator Crosstales.RTVoice.Provider.VoiceProviderAndroid.Speak (*Wrapper wrapper*) [virtual]

The current provider speaks a text with a given voice.

Parameters

<i>wrapper</i>	Wrapper containing the data.
----------------	------------------------------

Implements [Crosstales.RTVoice.Provider.BaseVoiceProvider](#).

5.73.2.3 override IEnumerator Crosstales.RTVoice.Provider.VoiceProviderAndroid.SpeakNative (*WrapperNative wrapper*) [virtual]

The current provider speaks a text with a given voice (native mode).

Parameters

<i>wrapper</i>	Wrapper containing the data.
----------------	------------------------------

Implements [Crosstales.RTVoice.Provider.BaseVoiceProvider](#).


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/crosstales/RTVoice/Plugins/↔ Scripts/Provider/VoiceProviderAndroid.cs

5.74 Crosstales.RTVoice.Provider.VoiceProviderIOS Class Reference

iOS voice provider.

Inheritance diagram for Crosstales.RTVoice.Provider.VoiceProviderIOS:



Public Member Functions

- override void [Silence](#) ()
Silence all active TTS-providers.
- override IEnumerator [SpeakNative](#) ([WrapperNative](#) wrapper)
The current provider speaks a text with a given voice (native mode).
- override IEnumerator [Speak](#) ([Wrapper](#) wrapper)
The current provider speaks a text with a given voice.

Static Public Member Functions

- static void [Stop](#) ()
Silence the current TTS-provider (native mode).
- static void [GetVoices](#) ()
Silence the current TTS-provider (native mode).
- static void [Speak](#) (string gameObject, string text, float rate=0.5f, float pitch=1f, float volume=1f, string culture="")
Bridge to the native tts system
- static void [SetVoices](#) (string voicesText)
Receives all voices
- static void [SetState](#) (string state)
Receives the state of the speaker.
- static void [WordSpoken](#) ()
Called everytime a new word is spoken.

Properties

- override string **AudioFileExtension** [get]
- override List< [Voice](#) > **Voices** [get]

Additional Inherited Members

5.74.1 Detailed Description

iOS voice provider.

5.74.2 Member Function Documentation

5.74.2.1 `static void Crosstales.RTVoice.Provider.VoiceProviderIOS.GetVoices () [static]`

Silence the current TTS-provider (native mode).

5.74.2.2 `static void Crosstales.RTVoice.Provider.VoiceProviderIOS.SetState (string state) [static]`

Receives the state of the speaker.

Parameters

<i>state</i>	The state of the speaker.
--------------	---------------------------

5.74.2.3 `static void Crosstales.RTVoice.Provider.VoiceProviderIOS.SetVoices (string voicesText) [static]`

Receives all voices

Parameters

<i>voicesText</i>	All voices as text string.
-------------------	----------------------------

5.74.2.4 `override void Crosstales.RTVoice.Provider.VoiceProviderIOS.Silence () [virtual]`

Silence all active TTS-providers.

Reimplemented from [Crosstales.RTVoice.Provider.BaseVoiceProvider](#).

5.74.2.5 `static void Crosstales.RTVoice.Provider.VoiceProviderIOS.Speak (string gameObject, string text, float rate = 0.5f, float pitch = 1f, float volume = 1f, string culture = " ") [static]`

Bridge to the native tts system

Parameters

<i>gameObject</i>	Receiving gameobject for the messages from iOS
<i>text</i>	Text to speak.
<i>rate</i>	Speech rate of the speaker in percent (default: 0.5, optional).
<i>pitch</i>	Pitch of the speech in percent (default: 1, optional).
<i>volume</i>	Volume of the speaker in percent (default: 1, optional).
<i>culture</i>	Culture of the voice to speak (optional).

5.74.2.6 override IEnumerator `Crosstales.RTVoice.Provider.VoiceProviderIOS.Speak (Wrapper wrapper)` [virtual]

The current provider speaks a text with a given voice.

Parameters

<i>wrapper</i>	Wrapper containing the data.
----------------	------------------------------

Implements [Crosstales.RTVoice.Provider.BaseVoiceProvider](#).

5.74.2.7 override IEnumerator `Crosstales.RTVoice.Provider.VoiceProviderIOS.SpeakNative (WrapperNative wrapper)` [virtual]

The current provider speaks a text with a given voice (native mode).

Parameters

<i>wrapper</i>	Wrapper containing the data.
----------------	------------------------------

Implements [Crosstales.RTVoice.Provider.BaseVoiceProvider](#).

5.74.2.8 static void `Crosstales.RTVoice.Provider.VoiceProviderIOS.Stop ()` [static]

Silence the current TTS-provider (native mode).

5.74.2.9 static void `Crosstales.RTVoice.Provider.VoiceProviderIOS.WordSpoken ()` [static]

Called everytime a new word is spoken.


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/crosstales/RTVoice/Plugins/↔ Scripts/Provider/VoiceProviderIOS.cs

5.75 Crosstales.RTVoice.Provider.VoiceProviderMacOS Class Reference

MacOS voice provider.

Inheritance diagram for `Crosstales.RTVoice.Provider.VoiceProviderMacOS`:



Public Member Functions

- override IEnumerator [SpeakNative](#) ([WrapperNative](#) wrapper)
The current provider speaks a text with a given voice (native mode).
- override IEnumerator [Speak](#) ([Wrapper](#) wrapper)
The current provider speaks a text with a given voice.

Properties

- override string **AudioFileExtension** [get]
- override List< [Voice](#) > **Voices** [get]

Additional Inherited Members

5.75.1 Detailed Description

MacOS voice provider.

5.75.2 Member Function Documentation

5.75.2.1 override IEnumerator Crosstales.RTVoice.Provider.VoiceProviderMacOS.Speak ([Wrapper](#) wrapper) [virtual]

The current provider speaks a text with a given voice.

Parameters

<i>wrapper</i>	Wrapper containing the data.
----------------	------------------------------

Implements [Crosstales.RTVoice.Provider.BaseVoiceProvider](#).

5.75.2.2 override IEnumerator Crosstales.RTVoice.Provider.VoiceProviderMacOS.SpeakNative ([WrapperNative](#) wrapper) [virtual]

The current provider speaks a text with a given voice (native mode).

Parameters

<i>wrapper</i>	Wrapper containing the data.
----------------	------------------------------

Implements [Crosstales.RTVoice.Provider.BaseVoiceProvider](#).


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/crosstales/RTVoice/Plugins/↔ Scripts/Provider/VoiceProviderMacOS.cs

5.76 Crosstales.RTVoice.Provider.VoiceProviderWindows Class Reference

Windows voice provider.

Inheritance diagram for Crosstales.RTVoice.Provider.VoiceProviderWindows:



Public Member Functions

- override IEnumerator [SpeakNative](#) ([WrapperNative](#) wrapper)
The current provider speaks a text with a given voice (native mode).
- override IEnumerator [Speak](#) ([Wrapper](#) wrapper)
The current provider speaks a text with a given voice.

Properties

- override string **AudioFileExtension** [get]
- override List< [Voice](#) > **Voices** [get]

Additional Inherited Members

5.76.1 Detailed Description

Windows voice provider.

5.76.2 Member Function Documentation

- 5.76.2.1 override IEnumerator Crosstales.RTVoice.Provider.VoiceProviderWindows.Speak ([Wrapper](#) wrapper)
 [virtual]

The current provider speaks a text with a given voice.

Parameters

<i>wrapper</i>	Wrapper containing the data.
----------------	------------------------------

Implements [Crosstales.RTVoice.Provider.BaseVoiceProvider](#).

5.76.2.2 override IEnumerator Crosstales.RTVoice.Provider.VoiceProviderWindows.SpeakNative (WrapperNative wrapper)
[virtual]

The current provider speaks a text with a given voice (native mode).

Parameters

<i>wrapper</i>	Wrapper containing the data.
----------------	------------------------------

Implements [Crosstales.RTVoice.Provider.BaseVoiceProvider](#).

The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/crosstales/RTVoice/Plugins/↔ Scripts/Provider/VoiceProviderWindows.cs

5.77 Crosstales.RTVoice.Model.Wrapper Class Reference

[Wrapper](#) for "Speak"-function calls.

Public Member Functions

- [Wrapper](#) (string text, AudioSource source=null, [Voice](#) voice=null, bool speakImmediately=true, float rate=1f, float pitch=1f, float volume=1f, string outputFile="")
Instantiate the class.
- [Wrapper](#) (Guid uid, string text, AudioSource source=null, [Voice](#) voice=null, bool speakImmediately=true, float rate=1f, float pitch=1f, float volume=1f, string outputFile="")
Instantiate the class.
- override string **ToString** ()

Public Attributes

- Guid [Uid](#)
UID of the speech.
- string [Text](#)
Text for the speech.
- AudioSource [Source](#)
AudioSource for the speech.
- [Voice](#) [Voice](#)
Voice for the speech.
- bool [SpeakImmediately](#)
Speak immediatlly after the audio generation.
- string [OutputFile](#)
Output file for the generated audio.

Properties

- float [Rate](#) [get, set]
Rate of the speech (values: 0-3).
- float [Pitch](#) [get, set]
Pitch of the speech (values: 0-2).
- float [Volume](#) [get, set]
Volume of the speech (values: 0-1).

5.77.1 Detailed Description

[Wrapper](#) for "Speak"-function calls.

5.77.2 Constructor & Destructor Documentation

5.77.2.1 `Crosstales.RTVoice.Model.Wrapper.Wrapper (string text, AudioSource source = null, Voice voice = null, bool speakImmediately = true, float rate = 1f, float pitch = 1f, float volume = 1f, string outputFile = " ")`

Instantiate the class.

Parameters

<i>text</i>	Text for the speech.
<i>source</i>	AudioSource for the speech.
<i>voice</i>	Voice for the speech.
<i>speakImmediately</i>	>Speak immediatlely after the audio generation.
<i>rate</i>	Rate of the speech (values: 0-3).
<i>pitch</i>	Pitch of the speech (values: 0-2).
<i>volume</i>	Volume of the speech (values: 0-1, Windows only).
<i>outputFile</i>	Output file for the generated audio.

5.77.2.2 `Crosstales.RTVoice.Model.Wrapper.Wrapper (Guid uid, string text, AudioSource source = null, Voice voice = null, bool speakImmediately = true, float rate = 1f, float pitch = 1f, float volume = 1f, string outputFile = " ")`

Instantiate the class.

Parameters

<i>uid</i>	UID of the speech.
<i>text</i>	Text for the speech.
<i>source</i>	AudioSource for the speech.
<i>voice</i>	Voice for the speech.
<i>speakImmediately</i>	>Speak immediatlely after the audio generation.
<i>rate</i>	Rate of the speech (values: 0-3).
<i>pitch</i>	Pitch of the speech (values: 0-2).
<i>volume</i>	Volume of the speech (values: 0-1, Windows only).
<i>outputFile</i>	Output file for the generated audio.

5.77.3 Member Data Documentation

5.77.3.1 string Crosstales.RTVoice.Model.Wrapper.OutputFile

Output file for the generated audio.

5.77.3.2 AudioSource Crosstales.RTVoice.Model.Wrapper.Source

AudioSource for the speech.

5.77.3.3 bool Crosstales.RTVoice.Model.Wrapper.SpeakImmediately

Speak immediately after the audio generation.

5.77.3.4 string Crosstales.RTVoice.Model.Wrapper.Text

Text for the speech.

5.77.3.5 Guid Crosstales.RTVoice.Model.Wrapper.Uid

UID of the speech.

5.77.3.6 Voice Crosstales.RTVoice.Model.Wrapper.Voice

Voice for the speech.

5.77.4 Property Documentation

5.77.4.1 float Crosstales.RTVoice.Model.Wrapper.Pitch [get], [set]

Pitch of the speech (values: 0-2).

5.77.4.2 float Crosstales.RTVoice.Model.Wrapper.Rate [get], [set]

Rate of the speech (values: 0-3).

5.77.4.3 float Crosstales.RTVoice.Model.Wrapper.Volume [get], [set]

Volume of the speech (values: 0-1).

The documentation for this class was generated from the following file:

- D:/slauberberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/crosstales/RTVoice/Plugins/Scripts/Model/Wrapper.cs

5.78 Crosstales.RTVoice.Model.WrapperNative Class Reference

[Wrapper](#) (native mode) for "SpeakNative"-function calls.

Public Member Functions

- [WrapperNative](#) (string text, [Voice](#) voice=null, float rate=1f, float pitch=1f, float volume=1f)
Instantiate the class.
- [WrapperNative](#) (Guid uid, string text, [Voice](#) voice=null, float rate=1f, float pitch=1f, float volume=1f)
Instantiate the class.
- override string **ToString** ()

Public Attributes

- Guid [Uid](#)
UID of the speech.
- string [Text](#)
Text for the speech.
- [Voice](#) [Voice](#)
[Voice](#) for the speech.

Properties

- float [Rate](#) [get, set]
Rate of the speech (values: 0-3).
- float [Pitch](#) [get, set]
Pitch of the speech (values: 0-2).
- float [Volume](#) [get, set]
Volume of the speech (values: 0-1).

5.78.1 Detailed Description

[Wrapper](#) (native mode) for "SpeakNative"-function calls.

5.78.2 Constructor & Destructor Documentation

5.78.2.1 Crosstales.RTVoice.Model.WrapperNative.WrapperNative (string text, [Voice](#) voice = null, float rate = 1f, float pitch = 1f, float volume = 1f)

Instantiate the class.

Parameters

<i>text</i>	Text for the speech.
<i>voice</i>	Voice for the speech.
<i>rate</i>	Rate of the speech (values: 0-3).
<i>pitch</i>	Pitch of the speech (values: 0-2).
<i>volume</i>	Volume of the speech (values: 0-1, Windows only).

5.78.2.2 `Crosstales.RTVoice.Model.WrapperNative.WrapperNative (Guid uid, string text, Voice voice = null, float rate = 1f, float pitch = 1f, float volume = 1f)`

Instantiate the class.

Parameters

<i>uid</i>	UID of the speech.
<i>text</i>	Text for the speech.
<i>voice</i>	Voice for the speech.
<i>rate</i>	Rate of the speech (values: 0-3).
<i>pitch</i>	Pitch of the speech (values: 0-2).
<i>volume</i>	Volume of the speech (values: 0-1, Windows only).

5.78.3 Member Data Documentation

5.78.3.1 `string Crosstales.RTVoice.Model.WrapperNative.Text`

Text for the speech.

5.78.3.2 `Guid Crosstales.RTVoice.Model.WrapperNative.Uid`

UID of the speech.

5.78.3.3 `Voice Crosstales.RTVoice.Model.WrapperNative.Voice`

Voice for the speech.

5.78.4 Property Documentation

5.78.4.1 `float Crosstales.RTVoice.Model.WrapperNative.Pitch` `[get], [set]`

Pitch of the speech (values: 0-2).

5.78.4.2 `float Crosstales.RTVoice.Model.WrapperNative.Rate` `[get], [set]`

Rate of the speech (values: 0-3).

5.78.4.3 `float Crosstales.RTVoice.Model.WrapperNative.Volume` `[get], [set]`

Volume of the speech (values: 0-1).

The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/crosstales/RTVoice/Plugins/↔ Scripts/Model/WrapperNative.cs

Index

- ACVoiceName
 - Crosstales::RTVoice::AdventureCreator::AC↔VoiceWrapper, [20](#)
- ASSET_API_URL
 - Crosstales::RTVoice::Util::Constants, [32](#)
- ASSET_AUTHOR_URL
 - Crosstales::RTVoice::Util::Constants, [32](#)
- ASSET_AUTHOR
 - Crosstales::RTVoice::Util::Constants, [32](#)
- ASSET_BUILD
 - Crosstales::RTVoice::Util::Constants, [32](#)
- ASSET_CHANGED
 - Crosstales::RTVoice::Util::Constants, [32](#)
- ASSET_CONTACT
 - Crosstales::RTVoice::Util::Constants, [32](#)
- ASSET_CREATED
 - Crosstales::RTVoice::Util::Constants, [32](#)
- ASSET_CT_URL
 - Crosstales::RTVoice::Util::Constants, [32](#)
- ASSET_FORUM_URL
 - Crosstales::RTVoice::Util::Constants, [32](#)
- ASSET_MANUAL_URL
 - Crosstales::RTVoice::Util::Constants, [32](#)
- ASSET_NAME
 - Crosstales::RTVoice::Util::Constants, [33](#)
- ASSET_UID
 - Crosstales::RTVoice::Util::Constants, [33](#)
- ASSET_UPDATE_CHECK_URL
 - Crosstales::RTVoice::Util::Constants, [33](#)
- ASSET_URL
 - Crosstales::RTVoice::Util::Constants, [33](#)
- ASSET_VERSION
 - Crosstales::RTVoice::Util::Constants, [33](#)
- AUDIOFILE_AUTOMATIC_DELETE
 - Crosstales::RTVoice::Util::Constants, [33](#)
- AUDIOFILE_PATH
 - Crosstales::RTVoice::Util::Constants, [33](#)
- AddRTVoice
 - Crosstales::RTVoice::EditorExt::EditorHelper, [39](#)
- Age
 - Crosstales::RTVoice::Model::Voice, [97](#)
- ApproximateSpeechLength
 - Crosstales::RTVoice::Speaker, [78](#)
- AudioFileExtension
 - Crosstales::RTVoice::Provider::BaseVoice↔Provider, [26](#)
 - Crosstales::RTVoice::Speaker, [82](#)
- AudioSource
 - HutongGames::PlayMaker::Actions::SpeakBase, [75](#)
- CTDump< T >
 - Crosstales::RTVoice::Util::Helper, [48](#)
- CallOnStopSpeech
 - Crosstales::RTVoice::AdventureCreator::AC↔Connector, [17](#)
- CleanText
 - Crosstales::RTVoice::Util::Helper, [48](#)
- ClearSpaces
 - Crosstales::RTVoice::Util::Helper, [48](#)
- Crosstales, [9](#)
- Crosstales.RTVoice, [9](#)
- Crosstales.RTVoice.AdventureCreator, [9](#)
- Crosstales.RTVoice.AdventureCreator.ACConnector, [17](#)
- Crosstales.RTVoice.AdventureCreator.ACConnector↔Editor, [18](#)
- Crosstales.RTVoice.AdventureCreator.ACConnector↔Menu, [18](#)
- Crosstales.RTVoice.AdventureCreator.ACScene↔Switcher, [19](#)
- Crosstales.RTVoice.AdventureCreator.ACVoice↔Wrapper, [19](#)
- Crosstales.RTVoice.Demo, [10](#)
- Crosstales.RTVoice.Demo.Dialog, [38](#)
- Crosstales.RTVoice.Demo.FFTAnalyzer, [40](#)
- Crosstales.RTVoice.Demo.GUIAudioFilter, [41](#)
- Crosstales.RTVoice.Demo.GUIDialog, [42](#)
- Crosstales.RTVoice.Demo.GUIMain, [42](#)
- Crosstales.RTVoice.Demo.GUIMultiAudioFilter, [43](#)
- Crosstales.RTVoice.Demo.GUIScenes, [44](#)
- Crosstales.RTVoice.Demo.GUISpeech, [45](#)
- Crosstales.RTVoice.Demo.GUISpeechMobile, [46](#)
- Crosstales.RTVoice.Demo.NativeAudio, [55](#)
- Crosstales.RTVoice.Demo.NativeDisabler, [56](#)
- Crosstales.RTVoice.Demo.PreGeneratedAudio, [57](#)
- Crosstales.RTVoice.Demo.SendMessage, [63](#)
- Crosstales.RTVoice.Demo.SequenceCaller, [66](#)
- Crosstales.RTVoice.Demo.Simple, [70](#)
- Crosstales.RTVoice.Demo.SimpleNative, [71](#)
- Crosstales.RTVoice.Demo.SpeakWrapper, [88](#)
- Crosstales.RTVoice.Demo.Util, [10](#)
- Crosstales.RTVoice.Demo.Util.AudioVisualizer, [22](#)
- Crosstales.RTVoice.Demo.Util.MaterialChanger, [55](#)
- Crosstales.RTVoice.Demo.Util.PlatformEnabler, [56](#)
- Crosstales.RTVoice.Demo.Util.RandomColor, [58](#)
- Crosstales.RTVoice.Demo.Util.RandomRotator, [58](#)
- Crosstales.RTVoice.Demo.Util.RandomScaler, [59](#)
- Crosstales.RTVoice.Demo.Util.ScrollRectHandler, [63](#)
- Crosstales.RTVoice.EditorExt, [11](#)

- Crosstales.RTVoice.EditorExt.AutoInitalize, 22
- Crosstales.RTVoice.EditorExt.BuildPostprocessor, 27
- Crosstales.RTVoice.EditorExt.ConfigBase, 28
- Crosstales.RTVoice.EditorExt.ConfigLoader, 28
- Crosstales.RTVoice.EditorExt.ConfigPreferences, 29
- Crosstales.RTVoice.EditorExt.ConfigWindow, 29
- Crosstales.RTVoice.EditorExt.EditorHelper, 38
- Crosstales.RTVoice.EditorExt.RTVoiceMenu, 63
- Crosstales.RTVoice.EditorExt.SequencerEditor, 69
- Crosstales.RTVoice.EditorExt.SpeakerEditor, 84
- Crosstales.RTVoice.EditorExt.SpeechTextEditor, 91
- Crosstales.RTVoice.EditorExt.UpdateCheck, 95
- Crosstales.RTVoice.LiveSpeaker, 51
- Crosstales.RTVoice.Model, 12
- Crosstales.RTVoice.Model.Event, 12
- Crosstales.RTVoice.Model.Event.CurrentPhoneme↔
 - EventArgs, 35
- Crosstales.RTVoice.Model.Event.CurrentViseme↔
 - EventArgs, 36
- Crosstales.RTVoice.Model.Event.CurrentWordEvent↔
 - Args, 36
- Crosstales.RTVoice.Model.Event.SpeakEventArgs, 84
- Crosstales.RTVoice.Model.Event.SpeakNativeEvent↔
 - Args, 85
- Crosstales.RTVoice.Model.Sequence, 64
- Crosstales.RTVoice.Model.Voice, 96
- Crosstales.RTVoice.Model.Wrapper, 105
- Crosstales.RTVoice.Model.WrapperNative, 108
- Crosstales.RTVoice.PlayMaker, 13
- Crosstales.RTVoice.PlayMaker.SpeakEditor, 76
- Crosstales.RTVoice.PlayMaker.SpeakUIEditor, 87
- Crosstales.RTVoice.Provider, 13
- Crosstales.RTVoice.Provider.BaseVoiceProvider, 23
- Crosstales.RTVoice.Provider.VoiceProviderAndroid, 98
- Crosstales.RTVoice.Provider.VoiceProviderIOS, 100
- Crosstales.RTVoice.Provider.VoiceProviderMacOS, 102
- Crosstales.RTVoice.Provider.VoiceProviderWindows, 104
- Crosstales.RTVoice.SALSA.Speak, 74
- Crosstales.RTVoice.SALSA, 13
- Crosstales.RTVoice.SLATE.CutSceneStart, 37
- Crosstales.RTVoice.SLATE, 13
- Crosstales.RTVoice.Speaker, 76
- Crosstales.RTVoice.Tool, 13
- Crosstales.RTVoice.Tool.Loudspeaker, 53
- Crosstales.RTVoice.Tool.Sequencer, 67
- Crosstales.RTVoice.Tool.SpeechText, 88
- Crosstales.RTVoice.UDEA2, 14
- Crosstales.RTVoice.UDEA2.UDEAConnector, 92
- Crosstales.RTVoice.UDEA2.UDEAConnectorEditor, 93
- Crosstales.RTVoice.UDEA2.UDEAVoiceWrapper, 93
- Crosstales.RTVoice.Util, 14
- Crosstales.RTVoice.Util.Constants, 30
- Crosstales.RTVoice.Util.Helper, 47
- Crosstales::RTVoice::AdventureCreator::ACConnector
 - CallOnStopSpeech, 17
 - Culture, 17
 - SimulateSkipSpeech, 18
- Voices, 18
- Crosstales::RTVoice::AdventureCreator::ACVoice↔
 - Wrapper
 - ACVoiceName, 20
 - IgnoreCharacter, 20
 - Pitch, 20
 - RTVoiceName, 22
 - RTVoiceNameAndroid, 21
 - RTVoiceNameIOS, 21
 - RTVoiceNameMac, 21
 - RTVoiceNameWindows, 21
 - Rate, 21
 - Source, 21
 - UseSpeechAudioSource, 21
 - Volume, 21
- Crosstales::RTVoice::Demo::Util
 - Platform, 11
- Crosstales::RTVoice::EditorExt::EditorHelper
 - AddRTVoice, 39
 - isRTVoiceInScene, 40
 - MENU_ID, 39
 - NoVoicesUI, 39
 - SeparatorUI, 39
- Crosstales::RTVoice::LiveSpeaker
 - Silence, 52
 - Speak, 52, 53
 - SpeakNative, 53
- Crosstales::RTVoice::Model
 - SpeakMode, 12
- Crosstales::RTVoice::Model::Event::CurrentPhoneme↔
 - EventArgs
 - Phoneme, 35
- Crosstales::RTVoice::Model::Event::CurrentViseme↔
 - EventArgs
 - Viseme, 36
- Crosstales::RTVoice::Model::Event::CurrentWord↔
 - EventArgs
 - SpeechTextArray, 37
 - WordIndex, 37
- Crosstales::RTVoice::Model::Event::SpeakEventArgs
 - Wrapper, 85
- Crosstales::RTVoice::Model::Event::SpeakNative↔
 - EventArgs
 - Wrapper, 86
- Crosstales::RTVoice::Model::Sequence
 - Mode, 65
 - Pitch, 65
 - RTVoiceName, 66
 - RTVoiceNameAndroid, 65
 - RTVoiceNameIOS, 65
 - RTVoiceNameMac, 65
 - RTVoiceNameWindows, 65
 - Rate, 65
 - Source, 65
 - Text, 65
 - Volume, 66
- Crosstales::RTVoice::Model::Voice
 - Age, 97

- Culture, [97](#)
- Description, [97](#)
- Gender, [97](#)
- Name, [98](#)
- ToShortString, [97](#)
- Voice, [96](#), [97](#)
- Crosstales::RTVoice::Model::Wrapper
 - OutputFile, [107](#)
 - Pitch, [107](#)
 - Rate, [107](#)
 - Source, [107](#)
 - SpeakImmediately, [107](#)
 - Text, [107](#)
 - Uid, [107](#)
 - Voice, [107](#)
 - Volume, [107](#)
 - Wrapper, [106](#)
- Crosstales::RTVoice::Model::WrapperNative
 - Pitch, [109](#)
 - Rate, [109](#)
 - Text, [109](#)
 - Uid, [109](#)
 - Voice, [109](#)
 - Volume, [109](#)
 - WrapperNative, [108](#), [109](#)
- Crosstales::RTVoice::Provider::BaseVoiceProvider
 - AudioFileExtension, [26](#)
 - OnErrorInfo, [26](#)
 - OnSpeakAudioGenerationComplete, [26](#)
 - OnSpeakAudioGenerationStart, [26](#)
 - OnSpeakComplete, [26](#)
 - OnSpeakNativeComplete, [26](#)
 - OnSpeakNativeCurrentPhoneme, [26](#)
 - OnSpeakNativeCurrentViseme, [27](#)
 - OnSpeakNativeCurrentWord, [27](#)
 - OnSpeakNativeStart, [27](#)
 - OnSpeakStart, [27](#)
 - Silence, [25](#)
 - Speak, [25](#)
 - SpeakNative, [25](#)
 - Voices, [26](#)
- Crosstales::RTVoice::Provider::VoiceProviderAndroid
 - Silence, [99](#)
 - Speak, [99](#)
 - SpeakNative, [99](#)
- Crosstales::RTVoice::Provider::VoiceProviderIOS
 - GetVoices, [101](#)
 - SetState, [101](#)
 - SetVoices, [101](#)
 - Silence, [101](#)
 - Speak, [101](#)
 - SpeakNative, [102](#)
 - Stop, [102](#)
 - WordSpoken, [102](#)
- Crosstales::RTVoice::Provider::VoiceProviderMacOS
 - Speak, [103](#)
 - SpeakNative, [103](#)
- Crosstales::RTVoice::Provider::VoiceProviderWindows
 - Speak, [104](#)
 - SpeakNative, [104](#)
- Crosstales::RTVoice::Speaker
 - ApproximateSpeechLength, [78](#)
 - AudioFileExtension, [82](#)
 - Cultures, [82](#)
 - isTTSAvailable, [82](#)
 - OnErrorInfo, [83](#)
 - OnSpeakAudioGenerationComplete, [83](#)
 - OnSpeakAudioGenerationStart, [83](#)
 - OnSpeakComplete, [83](#)
 - OnSpeakNativeComplete, [83](#)
 - OnSpeakNativeCurrentPhoneme, [83](#)
 - OnSpeakNativeCurrentViseme, [83](#)
 - OnSpeakNativeCurrentWord, [83](#)
 - OnSpeakNativeStart, [83](#)
 - OnSpeakStart, [84](#)
 - Silence, [79](#)
 - Speak, [79](#), [80](#)
 - SpeakMarkedWordsWithUID, [80](#)
 - SpeakNative, [80](#)
 - SpeakNativeWithUID, [81](#)
 - SpeakWithUID, [81](#)
 - VoiceForCulture, [81](#)
 - VoiceForName, [81](#)
 - Voices, [82](#)
 - VoicesForCulture, [82](#)
- Crosstales::RTVoice::Tool::Loudspeaker
 - SilenceSource, [54](#)
 - Source, [54](#)
 - Synchronized, [54](#)
- Crosstales::RTVoice::Tool::Sequencer
 - Culture, [68](#)
 - CurrentSequence, [68](#)
 - Delay, [68](#)
 - PlayAllSequences, [67](#)
 - PlayNextSequence, [67](#)
 - PlayOnStart, [68](#)
 - PlaySequence, [68](#)
 - Sequences, [68](#)
 - StopAllSequences, [68](#)
- Crosstales::RTVoice::Tool::SpeechText
 - Culture, [90](#)
 - FileInsideAssets, [90](#)
 - FileName, [90](#)
 - FilePath, [90](#)
 - GenerateAudioFile, [90](#)
 - Mode, [90](#)
 - Pitch, [90](#)
 - PlayOnStart, [90](#)
 - RTVoiceName, [91](#)
 - RTVoiceNameAndroid, [90](#)
 - RTVoiceNameIOS, [90](#)
 - RTVoiceNameMac, [91](#)
 - RTVoiceNameWindows, [91](#)
 - Rate, [90](#)
 - Source, [91](#)
 - Text, [91](#)

- Volume, [91](#)
- Crosstales::RTVoice::UDEA2::UDEAConnector
 - Culture, [92](#)
 - Voices, [92](#)
- Crosstales::RTVoice::UDEA2::UDEAVoiceWrapper
 - IgnoreCharacter, [94](#)
 - Pitch, [94](#)
 - RTVoiceName, [95](#)
 - RTVoiceNameAndroid, [94](#)
 - RTVoiceNameIOS, [95](#)
 - RTVoiceNameMac, [95](#)
 - RTVoiceNameWindows, [95](#)
 - Rate, [94](#)
 - Source, [95](#)
 - UDEAVoiceName, [95](#)
 - Volume, [95](#)
- Crosstales::RTVoice::Util::Constants
 - ASSET_API_URL, [32](#)
 - ASSET_AUTHOR_URL, [32](#)
 - ASSET_AUTHOR, [32](#)
 - ASSET_BUILD, [32](#)
 - ASSET_CHANGED, [32](#)
 - ASSET_CONTACT, [32](#)
 - ASSET_CREATED, [32](#)
 - ASSET_CT_URL, [32](#)
 - ASSET_FORUM_URL, [32](#)
 - ASSET_MANUAL_URL, [32](#)
 - ASSET_NAME, [33](#)
 - ASSET_UID, [33](#)
 - ASSET_UPDATE_CHECK_URL, [33](#)
 - ASSET_URL, [33](#)
 - ASSET_VERSION, [33](#)
 - AUDIOFILE_AUTOMATIC_DELETE, [33](#)
 - AUDIOFILE_PATH, [33](#)
 - DEBUG, [33](#)
 - ENFORCE_32BIT_WINDOWS, [33](#)
 - PREFAB_AUTOLOAD, [33](#)
 - PREFAB_PATH, [34](#)
 - RTVOICE_SCENE_OBJECT_NAME, [34](#)
 - TTS_KILL_TIME, [34](#)
 - TTS_MACOS, [34](#)
 - TTS_WINDOWS_BUILD_x86, [34](#)
 - TTS_WINDOWS_BUILD, [34](#)
 - TTS_WINDOWS_EDITOR_x86, [34](#)
 - TTS_WINDOWS_EDITOR, [34](#)
 - UPDATE_CHECK, [34](#)
 - UPDATE_OPEN_UAS, [34](#)
- Crosstales::RTVoice::Util::Helper
 - CTDump< T >, [48](#)
 - CleanText, [48](#)
 - ClearSpaces, [48](#)
 - HSVToRGB, [49](#)
 - isAndroidPlatform, [50](#)
 - isEditorMode, [50](#)
 - isIOSPlatform, [50](#)
 - isMacOSPlatform, [51](#)
 - isSupportedPlatform, [51](#)
 - isWindowsPlatform, [51](#)
 - MarkSpokenText, [49](#)
 - SplitStringToLines, [49](#)
 - ValidatePath, [50](#)
- Culture
 - Crosstales::RTVoice::AdventureCreator::AC↔Connector, [17](#)
 - Crosstales::RTVoice::Model::Voice, [97](#)
 - Crosstales::RTVoice::Tool::Sequencer, [68](#)
 - Crosstales::RTVoice::Tool::SpeechText, [90](#)
 - Crosstales::RTVoice::UDEA2::UDEAConnector, [92](#)
 - HutongGames::PlayMaker::Actions::Speak, [73](#)
 - HutongGames::PlayMaker::Actions::SpeakUI, [87](#)
- Cultures
 - Crosstales::RTVoice::Speaker, [82](#)
- CurrentSequence
 - Crosstales::RTVoice::Tool::Sequencer, [68](#)
- DEBUG
 - Crosstales::RTVoice::Util::Constants, [33](#)
- Delay
 - Crosstales::RTVoice::Tool::Sequencer, [68](#)
- Description
 - Crosstales::RTVoice::Model::Voice, [97](#)
- ENFORCE_32BIT_WINDOWS
 - Crosstales::RTVoice::Util::Constants, [33](#)
- FileInsideAssets
 - Crosstales::RTVoice::Tool::SpeechText, [90](#)
- FileName
 - Crosstales::RTVoice::Tool::SpeechText, [90](#)
- FilePath
 - Crosstales::RTVoice::Tool::SpeechText, [90](#)
- Gender
 - Crosstales::RTVoice::Model::Voice, [97](#)
- GenerateAudioFile
 - Crosstales::RTVoice::Tool::SpeechText, [90](#)
- GetVoice
 - PixelCrushers::DialogueSystem::RTVoiceActor, [60](#)
- GetVoices
 - Crosstales::RTVoice::Provider::VoiceProviderIOS, [101](#)
- HSVToRGB
 - Crosstales::RTVoice::Util::Helper, [49](#)
- HutongGames, [14](#)
- HutongGames.PlayMaker, [14](#)
- HutongGames.PlayMaker.Actions, [14](#)
- HutongGames.PlayMaker.Actions.Silence, [70](#)
- HutongGames.PlayMaker.Actions.Speak, [72](#)
- HutongGames.PlayMaker.Actions.SpeakBase, [74](#)
- HutongGames.PlayMaker.Actions.SpeakUI, [86](#)
- HutongGames::PlayMaker::Actions::Speak
 - Culture, [73](#)
 - RTVoiceNameAndroid, [73](#)
 - RTVoiceNameIOS, [73](#)
 - RTVoiceNameMac, [73](#)
 - RTVoiceNameWindows, [73](#)

- Text, [73](#)
- HutongGames::PlayMaker::Actions::SpeakBase
 - AudioSource, [75](#)
 - Mode, [75](#)
 - Pitch, [75](#)
 - Rate, [75](#)
 - Volume, [76](#)
- HutongGames::PlayMaker::Actions::SpeakUI
 - Culture, [87](#)
 - RTVoiceName, [87](#)
 - Text, [87](#)
- IgnoreCharacter
 - Crosstales::RTVoice::AdventureCreator::AC↔
 - VoiceWrapper, [20](#)
 - Crosstales::RTVoice::UDEA2::UDEAVoice↔
 - Wrapper, [94](#)
- isAndroidPlatform
 - Crosstales::RTVoice::Util::Helper, [50](#)
- isEditorMode
 - Crosstales::RTVoice::Util::Helper, [50](#)
- isIOSPlatform
 - Crosstales::RTVoice::Util::Helper, [50](#)
- isMacOSPlatform
 - Crosstales::RTVoice::Util::Helper, [51](#)
- isRTVoiceInScene
 - Crosstales::RTVoice::EditorExt::EditorHelper, [40](#)
- isSupportedPlatform
 - Crosstales::RTVoice::Util::Helper, [51](#)
- isTTSAvailable
 - Crosstales::RTVoice::Speaker, [82](#)
- isWindowsPlatform
 - Crosstales::RTVoice::Util::Helper, [51](#)
- MENU_ID
 - Crosstales::RTVoice::EditorExt::EditorHelper, [39](#)
- MarkSpokenText
 - Crosstales::RTVoice::Util::Helper, [49](#)
- Mode
 - Crosstales::RTVoice::Model::Sequence, [65](#)
 - Crosstales::RTVoice::Tool::SpeechText, [90](#)
 - HutongGames::PlayMaker::Actions::SpeakBase, [75](#)
- Name
 - Crosstales::RTVoice::Model::Voice, [98](#)
- NoVoicesUI
 - Crosstales::RTVoice::EditorExt::EditorHelper, [39](#)
- OnBarkLine
 - PixelCrushers::DialogueSystem::RTVoiceActor, [60](#)
- OnConversationLine
 - PixelCrushers::DialogueSystem::RTVoiceActor, [61](#)
- OnErrorInfo
 - Crosstales::RTVoice::Provider::BaseVoice↔
 - Provider, [26](#)
 - Crosstales::RTVoice::Speaker, [83](#)
- OnSpeakAudioGenerationComplete
 - Crosstales::RTVoice::Provider::BaseVoice↔
 - Provider, [26](#)
 - Crosstales::RTVoice::Speaker, [83](#)
- OnSpeakAudioGenerationStart
 - Crosstales::RTVoice::Provider::BaseVoice↔
 - Provider, [26](#)
 - Crosstales::RTVoice::Speaker, [83](#)
- OnSpeakComplete
 - Crosstales::RTVoice::Provider::BaseVoice↔
 - Provider, [26](#)
 - Crosstales::RTVoice::Speaker, [83](#)
- OnSpeakNativeComplete
 - Crosstales::RTVoice::Provider::BaseVoice↔
 - Provider, [26](#)
 - Crosstales::RTVoice::Speaker, [83](#)
- OnSpeakNativeCurrentPhoneme
 - Crosstales::RTVoice::Provider::BaseVoice↔
 - Provider, [26](#)
 - Crosstales::RTVoice::Speaker, [83](#)
- OnSpeakNativeCurrentViseme
 - Crosstales::RTVoice::Provider::BaseVoice↔
 - Provider, [27](#)
 - Crosstales::RTVoice::Speaker, [83](#)
- OnSpeakNativeCurrentWord
 - Crosstales::RTVoice::Provider::BaseVoice↔
 - Provider, [27](#)
 - Crosstales::RTVoice::Speaker, [83](#)
- OnSpeakNativeStart
 - Crosstales::RTVoice::Provider::BaseVoice↔
 - Provider, [27](#)
 - Crosstales::RTVoice::Speaker, [83](#)
- OnSpeakStart
 - Crosstales::RTVoice::Provider::BaseVoice↔
 - Provider, [27](#)
 - Crosstales::RTVoice::Speaker, [84](#)
- OutputFile
 - Crosstales::RTVoice::Model::Wrapper, [107](#)
- PREFAB_AUTOLOAD
 - Crosstales::RTVoice::Util::Constants, [33](#)
- PREFAB_PATH
 - Crosstales::RTVoice::Util::Constants, [34](#)
- Phoneme
 - Crosstales::RTVoice::Model::Event::Current↔
 - PhonemeEventArgs, [35](#)
- Pitch
 - Crosstales::RTVoice::AdventureCreator::AC↔
 - VoiceWrapper, [20](#)
 - Crosstales::RTVoice::Model::Sequence, [65](#)
 - Crosstales::RTVoice::Model::Wrapper, [107](#)
 - Crosstales::RTVoice::Model::WrapperNative, [109](#)
 - Crosstales::RTVoice::Tool::SpeechText, [90](#)
 - Crosstales::RTVoice::UDEA2::UDEAVoice↔
 - Wrapper, [94](#)
 - HutongGames::PlayMaker::Actions::SpeakBase, [75](#)
- PixelCrushers, [15](#)
- PixelCrushers.DialogueSystem, [15](#)
- PixelCrushers.DialogueSystem.RTVoiceActor, [59](#)

- PixelCrushers.DialogueSystem.RTVoiceActor.Voice↔
 - Preference, 98
- PixelCrushers.DialogueSystem.SequencerCommands, 15
- PixelCrushers.DialogueSystem.SequencerCommands.↔
 - SequencerCommandRTVoiceWait, 69
- PixelCrushers::DialogueSystem::RTVoiceActor
 - GetVoice, 60
 - OnBarkLine, 60
 - OnConversationLine, 61
 - Speak, 61
 - voicePreferences, 61
 - waitForVoiceInConversations, 61
- Platform
 - Crosstales::RTVoice::Demo::Util, 11
- PlayAllSequences
 - Crosstales::RTVoice::Tool::Sequencer, 67
- PlayNextSequence
 - Crosstales::RTVoice::Tool::Sequencer, 67
- PlayOnStart
 - Crosstales::RTVoice::Tool::Sequencer, 68
 - Crosstales::RTVoice::Tool::SpeechText, 90
- PlaySequence
 - Crosstales::RTVoice::Tool::Sequencer, 68
- RTVOICE_SCENE_OBJECT_NAME
 - Crosstales::RTVoice::Util::Constants, 34
- RTVoiceIOSBridge, 61
 - setVoices, 62
 - speak:rate:pitch:volume:culture:, 62
 - stop, 62
- RTVoiceIOSBridge(), 62
- RTVoiceName
 - Crosstales::RTVoice::AdventureCreator::AC↔
 - VoiceWrapper, 22
 - Crosstales::RTVoice::Model::Sequence, 66
 - Crosstales::RTVoice::Tool::SpeechText, 91
 - Crosstales::RTVoice::UDEA2::UDEAVoice↔
 - Wrapper, 95
 - HutongGames::PlayMaker::Actions::SpeakUI, 87
- RTVoiceNameAndroid
 - Crosstales::RTVoice::AdventureCreator::AC↔
 - VoiceWrapper, 21
 - Crosstales::RTVoice::Model::Sequence, 65
 - Crosstales::RTVoice::Tool::SpeechText, 90
 - Crosstales::RTVoice::UDEA2::UDEAVoice↔
 - Wrapper, 94
 - HutongGames::PlayMaker::Actions::Speak, 73
- RTVoiceNameIOS
 - Crosstales::RTVoice::AdventureCreator::AC↔
 - VoiceWrapper, 21
 - Crosstales::RTVoice::Model::Sequence, 65
 - Crosstales::RTVoice::Tool::SpeechText, 90
 - Crosstales::RTVoice::UDEA2::UDEAVoice↔
 - Wrapper, 95
 - HutongGames::PlayMaker::Actions::Speak, 73
- RTVoiceNameMac
 - Crosstales::RTVoice::AdventureCreator::AC↔
 - VoiceWrapper, 21
- Crosstales::RTVoice::Model::Sequence, 65
- Crosstales::RTVoice::Tool::SpeechText, 91
- Crosstales::RTVoice::UDEA2::UDEAVoice↔
 - Wrapper, 95
- HutongGames::PlayMaker::Actions::Speak, 73
- RTVoiceNameWindows
 - Crosstales::RTVoice::AdventureCreator::AC↔
 - VoiceWrapper, 21
 - Crosstales::RTVoice::Model::Sequence, 65
 - Crosstales::RTVoice::Tool::SpeechText, 91
 - Crosstales::RTVoice::UDEA2::UDEAVoice↔
 - Wrapper, 95
 - HutongGames::PlayMaker::Actions::Speak, 73
- Rate
 - Crosstales::RTVoice::AdventureCreator::AC↔
 - VoiceWrapper, 21
 - Crosstales::RTVoice::Model::Sequence, 65
 - Crosstales::RTVoice::Model::Wrapper, 107
 - Crosstales::RTVoice::Model::WrapperNative, 109
 - Crosstales::RTVoice::Tool::SpeechText, 90
 - Crosstales::RTVoice::UDEA2::UDEAVoice↔
 - Wrapper, 94
 - HutongGames::PlayMaker::Actions::SpeakBase, 75
- SeparatorUI
 - Crosstales::RTVoice::EditorExt::EditorHelper, 39
- Sequences
 - Crosstales::RTVoice::Tool::Sequencer, 68
- SetState
 - Crosstales::RTVoice::Provider::VoiceProviderIOS, 101
- SetVoices
 - Crosstales::RTVoice::Provider::VoiceProviderIOS, 101
- setVoices
 - RTVoiceIOSBridge, 62
- Silence
 - Crosstales::RTVoice::LiveSpeaker, 52
 - Crosstales::RTVoice::Provider::BaseVoice↔
 - Provider, 25
 - Crosstales::RTVoice::Provider::VoiceProvider↔
 - Android, 99
 - Crosstales::RTVoice::Provider::VoiceProviderIOS, 101
 - Crosstales::RTVoice::Speaker, 79
- SilenceSource
 - Crosstales::RTVoice::Tool::Loudspeaker, 54
- SimulateSkipSpeech
 - Crosstales::RTVoice::AdventureCreator::AC↔
 - Connector, 18
- Source
 - Crosstales::RTVoice::AdventureCreator::AC↔
 - VoiceWrapper, 21
 - Crosstales::RTVoice::Model::Sequence, 65
 - Crosstales::RTVoice::Model::Wrapper, 107
 - Crosstales::RTVoice::Tool::Loudspeaker, 54
 - Crosstales::RTVoice::Tool::SpeechText, 91

- Crosstales::RTVoice::UDEA2::UDEAVoice↔
Wrapper, 95
- Speak
 - Crosstales::RTVoice::LiveSpeaker, 52, 53
 - Crosstales::RTVoice::Provider::BaseVoice↔
Provider, 25
 - Crosstales::RTVoice::Provider::VoiceProvider↔
Android, 99
 - Crosstales::RTVoice::Provider::VoiceProviderIOS,
101
 - Crosstales::RTVoice::Provider::VoiceProvider↔
MacOS, 103
 - Crosstales::RTVoice::Provider::VoiceProvider↔
Windows, 104
 - Crosstales::RTVoice::Speaker, 79, 80
 - PixelCrushers::DialogueSystem::RTVoiceActor, 61
- speak:rate:pitch:volume:culture:
RTVoiceIOSBridge, 62
- SpeakImmediately
 - Crosstales::RTVoice::Model::Wrapper, 107
- SpeakMarkedWordsWithUID
 - Crosstales::RTVoice::Speaker, 80
- SpeakMode
 - Crosstales::RTVoice::Model, 12
- SpeakNative
 - Crosstales::RTVoice::LiveSpeaker, 53
 - Crosstales::RTVoice::Provider::BaseVoice↔
Provider, 25
 - Crosstales::RTVoice::Provider::VoiceProvider↔
Android, 99
 - Crosstales::RTVoice::Provider::VoiceProviderIOS,
102
 - Crosstales::RTVoice::Provider::VoiceProvider↔
MacOS, 103
 - Crosstales::RTVoice::Provider::VoiceProvider↔
Windows, 104
 - Crosstales::RTVoice::Speaker, 80
- SpeakNativeWithUID
 - Crosstales::RTVoice::Speaker, 81
- SpeakWithUID
 - Crosstales::RTVoice::Speaker, 81
- SpeechTextArray
 - Crosstales::RTVoice::Model::Event::Current↔
WordEventArgs, 37
- SplitStringToLines
 - Crosstales::RTVoice::Util::Helper, 49
- Stop
 - Crosstales::RTVoice::Provider::VoiceProviderIOS,
102
- stop
 - RTVoiceIOSBridge, 62
- StopAllSequences
 - Crosstales::RTVoice::Tool::Sequencer, 68
- Synchronized
 - Crosstales::RTVoice::Tool::Loudspeaker, 54
- TTS_KILL_TIME
 - Crosstales::RTVoice::Util::Constants, 34
- TTS_MACOS
 - Crosstales::RTVoice::Util::Constants, 34
- TTS_WINDOWS_BUILD_x86
 - Crosstales::RTVoice::Util::Constants, 34
- TTS_WINDOWS_BUILD
 - Crosstales::RTVoice::Util::Constants, 34
- TTS_WINDOWS_EDITOR_x86
 - Crosstales::RTVoice::Util::Constants, 34
- TTS_WINDOWS_EDITOR
 - Crosstales::RTVoice::Util::Constants, 34
- Text
 - Crosstales::RTVoice::Model::Sequence, 65
 - Crosstales::RTVoice::Model::Wrapper, 107
 - Crosstales::RTVoice::Model::WrapperNative, 109
 - Crosstales::RTVoice::Tool::SpeechText, 91
 - HutongGames::PlayMaker::Actions::Speak, 73
 - HutongGames::PlayMaker::Actions::SpeakUI, 87
- ToShortString
 - Crosstales::RTVoice::Model::Voice, 97
- UDEAVoiceName
 - Crosstales::RTVoice::UDEA2::UDEAVoice↔
Wrapper, 95
- UPDATE_CHECK
 - Crosstales::RTVoice::Util::Constants, 34
- UPDATE_OPEN_UAS
 - Crosstales::RTVoice::Util::Constants, 34
- Uid
 - Crosstales::RTVoice::Model::Wrapper, 107
 - Crosstales::RTVoice::Model::WrapperNative, 109
- UseSpeechAudioSource
 - Crosstales::RTVoice::AdventureCreator::AC↔
VoiceWrapper, 21
- ValidatePath
 - Crosstales::RTVoice::Util::Helper, 50
- Viseme
 - Crosstales::RTVoice::Model::Event::Current↔
VisemeEventArgs, 36
- Voice
 - Crosstales::RTVoice::Model::Voice, 96, 97
 - Crosstales::RTVoice::Model::Wrapper, 107
 - Crosstales::RTVoice::Model::WrapperNative, 109
- VoiceForCulture
 - Crosstales::RTVoice::Speaker, 81
- VoiceForName
 - Crosstales::RTVoice::Speaker, 81
- voicePreferences
 - PixelCrushers::DialogueSystem::RTVoiceActor, 61
- Voices
 - Crosstales::RTVoice::AdventureCreator::AC↔
Connector, 18
 - Crosstales::RTVoice::Provider::BaseVoice↔
Provider, 26
 - Crosstales::RTVoice::Speaker, 82
 - Crosstales::RTVoice::UDEA2::UDEAConnector, 92
- VoicesForCulture
 - Crosstales::RTVoice::Speaker, 82
- Volume

- Crosstales::RTVoice::AdventureCreator::AC↔
VoiceWrapper, [21](#)
- Crosstales::RTVoice::Model::Sequence, [66](#)
- Crosstales::RTVoice::Model::Wrapper, [107](#)
- Crosstales::RTVoice::Model::WrapperNative, [109](#)
- Crosstales::RTVoice::Tool::SpeechText, [91](#)
- Crosstales::RTVoice::UDEA2::UDEAVoice↔
Wrapper, [95](#)
- HutongGames::PlayMaker::Actions::SpeakBase,
[76](#)
- waitForVoiceInConversations
 - PixelCrushers::DialogueSystem::RTVoiceActor, [61](#)
- WordIndex
 - Crosstales::RTVoice::Model::Event::Current↔
WordEventArgs, [37](#)
- WordSpoken
 - Crosstales::RTVoice::Provider::VoiceProviderIOS,
[102](#)
- Wrapper
 - Crosstales::RTVoice::Model::Event::SpeakEvent↔
Args, [85](#)
 - Crosstales::RTVoice::Model::Event::Speak↔
NativeEventArgs, [86](#)
 - Crosstales::RTVoice::Model::Wrapper, [106](#)
- WrapperNative
 - Crosstales::RTVoice::Model::WrapperNative, [108](#),
[109](#)