

RT-Voice

Hearing is understanding



API

© 2015-2018 **crosstales** LLC
<https://www.crosstales.com>

Date: 08.01.2018
Version: 2.9.4

Contents

1	Namespace Index	1
1.1	Packages	1
2	Hierarchical Index	3
2.1	Class Hierarchy	3
3	Class Index	7
3.1	Class List	7
4	Namespace Documentation	11
4.1	Crosstales Namespace Reference	11
4.2	Crosstales.Common Namespace Reference	11
4.3	Crosstales.Common.EditorTask Namespace Reference	11
4.4	Crosstales.Common.EditorUtil Namespace Reference	11
4.5	Crosstales.Common.Util Namespace Reference	12
4.5.1	Enumeration Type Documentation	12
4.5.1.1	Platform	12
4.6	Crosstales.DJ Namespace Reference	12
4.7	Crosstales.DJ.Demo Namespace Reference	12
4.8	Crosstales.DJ.Demo.Util Namespace Reference	12
4.9	Crosstales.RTVoice Namespace Reference	13
4.10	Crosstales.RTVoice.Demo Namespace Reference	13
4.11	Crosstales.RTVoice.Demo.Util Namespace Reference	14
4.12	Crosstales.RTVoice.EditorExtension Namespace Reference	14
4.13	Crosstales.RTVoice.EditorIntegration Namespace Reference	14

4.14	Crosstales.RTVoice.EditorTask Namespace Reference	15
4.14.1	Enumeration Type Documentation	15
4.14.1.1	UpdateStatus	15
4.15	Crosstales.RTVoice.EditorUtil Namespace Reference	15
4.16	Crosstales.RTVoice.Model Namespace Reference	16
4.17	Crosstales.RTVoice.Model.Enum Namespace Reference	16
4.17.1	Enumeration Type Documentation	16
4.17.1.1	MaryTTSType	16
4.17.1.2	ProviderType	16
4.17.1.3	SpeakMode	16
4.18	Crosstales.RTVoice.PlayMaker Namespace Reference	17
4.19	Crosstales.RTVoice.Provider Namespace Reference	17
4.20	Crosstales.RTVoice.SALSA Namespace Reference	17
4.21	Crosstales.RTVoice.Tool Namespace Reference	18
4.22	Crosstales.RTVoice.UDEA2 Namespace Reference	18
4.23	Crosstales.RTVoice.Util Namespace Reference	18
4.24	Crosstales.UI Namespace Reference	19
4.25	Crosstales.UI.Util Namespace Reference	19
4.26	HutongGames Namespace Reference	19
4.27	HutongGames.PlayMaker Namespace Reference	19
4.28	HutongGames.PlayMaker.Actions Namespace Reference	19

5	Class Documentation	21
5.1	Crosstales.RTVoice.Tool.AudioFileGenerator Class Reference	21
5.1.1	Detailed Description	21
5.1.2	Member Function Documentation	22
5.1.2.1	Generate()	22
5.1.3	Member Data Documentation	22
5.1.3.1	FileInsideAssets	22
5.1.3.2	TextFiles	22
5.2	Crosstales.RTVoice.EditorExtension.AudioFileGeneratorEditor Class Reference	22
5.2.1	Detailed Description	22
5.3	Crosstales.UI.Util.AudioFilterController Class Reference	23
5.3.1	Detailed Description	24
5.3.2	Member Data Documentation	24
5.3.2.1	FindAllAudioFiltersOnStart	24
5.4	Crosstales.UI.Util.AudioSourceController Class Reference	24
5.4.1	Detailed Description	25
5.4.2	Member Data Documentation	25
5.4.2.1	AudioSources	25
5.4.2.2	FindAllAudioSourcesOnStart	25
5.4.2.3	Loop	25
5.4.2.4	Mute	25
5.4.2.5	Pitch	26
5.4.2.6	ResetAudioSourcesOnStart	26
5.4.2.7	StereoPan	26
5.4.2.8	Volume	26
5.5	Crosstales.RTVoice.EditorTask.AutoInitalize Class Reference	26
5.5.1	Detailed Description	26
5.6	Crosstales.Common.EditorTask.BaseCompileDefines Class Reference	26
5.6.1	Detailed Description	27
5.7	Crosstales.Common.Util.BaseConstants Class Reference	27

5.7.1	Detailed Description	28
5.7.2	Member Data Documentation	28
5.7.2.1	ASSET_3P_PLAYMAKER	28
5.7.2.2	ASSET_AUTHOR	29
5.7.2.3	ASSET_AUTHOR_URL	29
5.7.2.4	ASSET_CT_URL	29
5.7.2.5	ASSET_SOCIAL_FACEBOOK	29
5.7.2.6	ASSET_SOCIAL_LINKEDIN	29
5.7.2.7	ASSET_SOCIAL_TWITTER	29
5.7.2.8	ASSET_SOCIAL_XING	29
5.7.2.9	ASSET_SOCIAL_YOUTUBE	29
5.7.2.10	DEV_DEBUG	29
5.7.2.11	FACTOR_GB	30
5.7.2.12	FACTOR_KB	30
5.7.2.13	FACTOR_MB	30
5.7.2.14	FLOAT_32768	30
5.7.2.15	FORMAT_NO_DECIMAL_PLACES	30
5.7.2.16	FORMAT_PERCENT	30
5.7.2.17	FORMAT_TWO_DECIMAL_PLACES	30
5.7.2.18	PATH_DELIMITER_UNIX	30
5.7.2.19	PATH_DELIMITER_WINDOWS	30
5.8	Crosstales.Common.EditorUtil.BaseGAApi Class Reference	31
5.8.1	Detailed Description	31
5.8.2	Member Function Documentation	31
5.8.2.1	Event(string name, string version, string category, string action, string label="","", int value=0)	31
5.9	Crosstales.Common.Util.BaseHelper Class Reference	31
5.9.1	Detailed Description	33
5.9.2	Member Function Documentation	33
5.9.2.1	ClearLineEndings(string text)	33
5.9.2.2	ClearSpaces(string text)	34

5.9.2.3	ClearTags(string text)	34
5.9.2.4	FormatBytesToHRF(long bytes)	34
5.9.2.5	FormatSecondsToHourMinSec(double seconds)	34
5.9.2.6	HSVToRGB(float h, float s, float v, float a=1f)	34
5.9.2.7	IsValidURL(string url)	35
5.9.2.8	RemoteCertificateValidationCallback(System.Object sender, System.Security.Cryptography.X509Certificates.X509Certificate certificate, System.Security.Cryptography.X509Certificates.X509Chain chain, System.Net.Security.SslPolicyErrors sslPolicyErrors)	35
5.9.2.9	SplitStringToLines(string text, bool ignoreCommentedLines=true, int skipHeaderLines=0, int skipFooterLines=0)	35
5.9.2.10	ValidateFile(string path)	36
5.9.2.11	ValidatePath(string path, bool addEndDelimiter=true)	36
5.9.2.12	ValidURLFromFilePath(string path)	36
5.9.3	Property Documentation	36
5.9.3.1	isAndroidPlatform	36
5.9.3.2	isAppleBasedPlatform	37
5.9.3.3	isEditor	37
5.9.3.4	isEditorMode	37
5.9.3.5	isInternetAvailable	37
5.9.3.6	isIOSPlatform	37
5.9.3.7	isLinuxPlatform	37
5.9.3.8	isMacOSPlatform	38
5.9.3.9	isStandalonePlatform	38
5.9.3.10	isWebGLPlatform	38
5.9.3.11	isWebPlatform	38
5.9.3.12	isWebPlayerPlatform	38
5.9.3.13	isWindowsBasedPlatform	38
5.9.3.14	isWindowsPlatform	39
5.9.3.15	isWSAPlatform	39
5.10	Crosstales.Common.EditorTask.BaseSetupResources Class Reference	39
5.10.1	Detailed Description	39

5.11	Crosstales.RTVoice.Provider.BaseVoiceProvider Class Reference	40
5.11.1	Detailed Description	41
5.11.2	Constructor & Destructor Documentation	41
5.11.2.1	BaseVoiceProvider(MonoBehaviour obj)	41
5.11.3	Member Function Documentation	41
5.11.3.1	Generate(Model.Wrapper wrapper)	42
5.11.3.2	Silence()	42
5.11.3.3	Silence(string uid)	42
5.11.3.4	Speak(Model.Wrapper wrapper)	42
5.11.3.5	SpeakNative(Model.Wrapper wrapper)	42
5.11.4	Property Documentation	43
5.11.4.1	AudioFileExtension	43
5.11.4.2	OnErrorInfo	43
5.11.4.3	OnSpeakAudioGenerationComplete	43
5.11.4.4	OnSpeakAudioGenerationStart	43
5.11.4.5	OnSpeakComplete	43
5.11.4.6	OnSpeakCurrentPhoneme	43
5.11.4.7	OnSpeakCurrentViseme	44
5.11.4.8	OnSpeakCurrentWord	44
5.11.4.9	OnSpeakStart	44
5.11.4.10	OnVoicesReady	44
5.11.4.11	Voices	44
5.12	Crosstales.RTVoice.SALSA.Bots Class Reference	44
5.12.1	Detailed Description	45
5.13	Crosstales.RTVoice.EditorUtil.BuildPostprocessor Class Reference	45
5.13.1	Detailed Description	45
5.14	Crosstales.RTVoice.EditorTask.CompileDefines Class Reference	45
5.14.1	Detailed Description	46
5.15	Crosstales.RTVoice.Util.Config Class Reference	46
5.15.1	Detailed Description	47

5.15.2	Member Function Documentation	47
5.15.2.1	Load()	47
5.15.2.2	Reset()	47
5.15.2.3	Save()	47
5.15.3	Member Data Documentation	47
5.15.3.1	ASSET_PATH	47
5.15.3.2	AUDIOFILE_AUTOMATIC_DELETE	47
5.15.3.3	AUDIOFILE_PATH	47
5.15.3.4	DEBUG	48
5.15.3.5	ENFORCE_32BIT_WINDOWS	48
5.15.3.6	isLoadingd	48
5.15.3.7	TTS_MACOS	48
5.15.3.8	TTS_WINDOWS_BUILD	48
5.15.4	Property Documentation	48
5.15.4.1	TTS_WINDOWS_EDITOR	48
5.15.4.2	TTS_WINDOWS_EDITOR_x86	48
5.16	Crosstales.RTVoice.EditorIntegration.ConfigBase Class Reference	49
5.16.1	Detailed Description	49
5.17	Crosstales.RTVoice.EditorTask.ConfigLoader Class Reference	49
5.17.1	Detailed Description	49
5.18	Crosstales.RTVoice.EditorIntegration.ConfigPreferences Class Reference	50
5.18.1	Detailed Description	50
5.19	Crosstales.RTVoice.EditorIntegration.ConfigWindow Class Reference	50
5.19.1	Detailed Description	51
5.20	Crosstales.RTVoice.Util.Constants Class Reference	51
5.20.1	Detailed Description	53
5.20.2	Member Data Documentation	53
5.20.2.1	ASSET_3P_ADVENTURE_CREATOR	53
5.20.2.2	ASSET_3P_CINEMA_DIRECTOR	53
5.20.2.3	ASSET_3P_DIALOG_SYSTEM	54

5.20.2.4	ASSET_3P_DIALOGUE_ENGINE	54
5.20.2.5	ASSET_3P_LIPSYNC	54
5.20.2.6	ASSET_3P_LOCALIZED_DIALOGS	54
5.20.2.7	ASSET_3P_NPC_CHAT	54
5.20.2.8	ASSET_3P_REQUEST_SYSTEM	54
5.20.2.9	ASSET_3P_SALSA	54
5.20.2.10	ASSET_3P_SLATE	54
5.20.2.11	ASSET_3P_URL	54
5.20.2.12	ASSET_3P_USEQUENCER	55
5.20.2.13	ASSET_API_URL	55
5.20.2.14	ASSET_BUILD	55
5.20.2.15	ASSET_CHANGED	55
5.20.2.16	ASSET_CONTACT	55
5.20.2.17	ASSET_CREATED	55
5.20.2.18	ASSET_FORUM_URL	55
5.20.2.19	ASSET_MANUAL_URL	55
5.20.2.20	ASSET_NAME	55
5.20.2.21	ASSET_PRO_URL	56
5.20.2.22	ASSET_UPDATE_CHECK_URL	56
5.20.2.23	ASSET_VERSION	56
5.20.2.24	ASSET_VIDEO_PROMO	56
5.20.2.25	ASSET_VIDEO_TUTORIAL	56
5.20.2.26	ASSET_WEB_URL	56
5.20.2.27	isPro	56
5.20.2.28	RTVOICE_SCENE_OBJECT_NAME	56
5.20.2.29	TTS_WINDOWS_SUBPATH	56
5.20.2.30	TTS_WINDOWS_x86_SUBPATH	57
5.21	Crosstales.Common.Util.CTPlayerPrefs Class Reference	57
5.21.1	Detailed Description	57
5.21.2	Member Function Documentation	58

5.21.2.1	DeleteAll()	58
5.21.2.2	DeleteKey(string key)	58
5.21.2.3	GetBool(string key)	59
5.21.2.4	GetFloat(string key)	59
5.21.2.5	GetInt(string key)	59
5.21.2.6	GetString(string key)	59
5.21.2.7	HasKey(string key)	60
5.21.2.8	Save()	60
5.21.2.9	SetBool(string key, bool value)	60
5.21.2.10	SetFloat(string key, float value)	60
5.21.2.11	SetInt(string key, int value)	61
5.21.2.12	SetString(string key, string value)	61
5.22	Crosstales.Common.Util.CTWebClient Class Reference	61
5.22.1	Detailed Description	62
5.22.2	Property Documentation	62
5.22.2.1	ConnectionLimit	62
5.22.2.2	Timeout	62
5.23	Crosstales.RTVoice.Demo.Dialog Class Reference	62
5.23.1	Detailed Description	63
5.24	Crosstales.RTVoice.EditorUtil.EditorConfig Class Reference	63
5.24.1	Detailed Description	64
5.24.2	Member Function Documentation	64
5.24.2.1	Load()	64
5.24.2.2	Reset()	64
5.24.2.3	Save()	64
5.24.3	Member Data Documentation	64
5.24.3.1	HIERARCHY_ICON	64
5.24.3.2	isLoadingd	64
5.24.3.3	PREFAB_AUTOLOAD	64
5.24.3.4	REMINDER_CHECK	65

5.24.3.5	TELEMETRY	65
5.24.3.6	UPDATE_CHECK	65
5.24.4	Property Documentation	65
5.24.4.1	ASSET_PATH	65
5.24.4.2	PREFAB_PATH	65
5.25	Crosstales.RTVoice.EditorUtil.EditorConstants Class Reference	65
5.25.1	Detailed Description	66
5.25.2	Member Data Documentation	66
5.25.2.1	PREFAB_SUBPATH	66
5.25.3	Property Documentation	66
5.25.3.1	ASSET_UID	66
5.25.3.2	ASSET_URL	67
5.26	Crosstales.RTVoice.EditorUtil.EditorHelper Class Reference	67
5.26.1	Detailed Description	68
5.26.2	Member Function Documentation	68
5.26.2.1	InstantiatePrefab(string prefabName)	68
5.26.2.2	NoVoicesUI()	68
5.26.2.3	SeparatorUI(int space=12)	68
5.26.3	Member Data Documentation	69
5.26.3.1	GO_ID	69
5.26.3.2	MENU_ID	69
5.26.4	Property Documentation	69
5.26.4.1	isRTVoiceInScene	69
5.27	Crosstales.ExtensionMethods Class Reference	69
5.27.1	Detailed Description	70
5.27.2	Member Function Documentation	70
5.27.2.1	CTAddRange< T, S >(this System.Collections.Generic.Dictionary< T, S > source, System.Collections.Generic.Dictionary< T, S > collection)	70
5.27.2.2	CTContains(this string str, string toCheck, System.StringComparison comp=↵ System.StringComparison.OrdinalIgnoreCase)	71
5.27.2.3	CTContainsAll(this string str, string searchTerms, char splitChar= ' ')	71

5.27.2.4	CTContainsAny(this string str, string searchTerms, char splitChar= ' ')	71
5.27.2.5	CTDump< T >(this T[] array)	72
5.27.2.6	CTDump< T >(this System.Collections.Generic.List< T > list)	72
5.27.2.7	CTEquals(this string str, string toCheck, System.StringComparison comp=↔ System.StringComparison.OrdinalIgnoreCase)	72
5.27.2.8	CTReplace(this string str, string oldString, string newString, System.String↔ Comparison comp=System.StringComparison.OrdinalIgnoreCase)	72
5.27.2.9	CTShuffle< T >(this T[] array)	73
5.27.2.10	CTShuffle< T >(this System.Collections.Generic.IList< T > list)	73
5.27.2.11	CTToString< T >(this T[] array)	73
5.27.2.12	CTToString< T >(this System.Collections.Generic.List< T > list)	73
5.27.2.13	CTToTitleCase(this string str)	74
5.28	Crosstales.DJ.Demo.Util.FFTAnalyzer Class Reference	74
5.28.1	Detailed Description	75
5.29	Crosstales.UI.Util.FPSDisplay Class Reference	75
5.29.1	Detailed Description	75
5.30	Crosstales.RTVoice.EditorUtil.GAApi Class Reference	75
5.30.1	Detailed Description	76
5.30.2	Member Function Documentation	76
5.30.2.1	Event(string category, string action, string label="","", int value=0)	76
5.31	Crosstales.RTVoice.Demo.GUIAudioFilter Class Reference	76
5.31.1	Detailed Description	77
5.32	Crosstales.RTVoice.Demo.GUIDialog Class Reference	77
5.32.1	Detailed Description	78
5.33	Crosstales.RTVoice.Demo.GUIMain Class Reference	78
5.33.1	Detailed Description	79
5.34	Crosstales.RTVoice.Demo.GUIMultiAudioFilter Class Reference	79
5.34.1	Detailed Description	80
5.35	Crosstales.RTVoice.Demo.GUIScenes Class Reference	80
5.35.1	Detailed Description	81
5.36	Crosstales.RTVoice.Demo.GUISpeech Class Reference	81

5.36.1 Detailed Description	82
5.37 Crosstales.RTVoice.Util.Helper Class Reference	82
5.37.1 Detailed Description	82
5.37.2 Member Function Documentation	82
5.37.2.1 CleanText(string text, bool removeTags=true, bool clearSpaces=true, bool clear← LineEndings=true)	82
5.37.2.2 MarkSpokenText(string[] speechTextArray, int wordIndex, bool markAll← SpokenWords=false, string markPrefix=""<color=green>""", string mark← Postfix=""</color>""")	83
5.37.3 Property Documentation	83
5.37.3.1 CurrentProviderType	83
5.37.3.2 hasBuiltInTTS	83
5.38 Crosstales.RTVoice.Demo.Util.iOSController Class Reference	84
5.38.1 Detailed Description	84
5.39 Crosstales.RTVoice.EditorTask.Launch Class Reference	84
5.39.1 Detailed Description	84
5.40 Crosstales.RTVoice.LiveSpeaker Class Reference	84
5.40.1 Detailed Description	85
5.40.2 Member Function Documentation	85
5.40.2.1 SetState(string state)	85
5.40.2.2 SetVoices(string voices)	85
5.40.2.3 Silence()	86
5.40.2.4 Speak(Model.Wrapper wrapper)	86
5.40.2.5 Speak(string args)	86
5.40.2.6 Speak(string[] args)	86
5.40.2.7 SpeakNative(Model.Wrapper wrapper)	86
5.40.2.8 SpeakNative(string args)	87
5.40.2.9 SpeakNative(string[] args)	87
5.40.2.10 WordSpoken(string word)	87
5.41 Crosstales.RTVoice.Tool.Loudspeaker Class Reference	87
5.41.1 Detailed Description	88
5.41.2 Member Data Documentation	88

5.41.2.1	SilenceSource	88
5.41.2.2	Source	88
5.41.2.3	Synchronized	88
5.41.3	Property Documentation	89
5.41.3.1	isSilenceSource	89
5.41.3.2	isSynchronized	89
5.42	Crosstales.RTVoice.EditorExtension.LoudspeakerEditor Class Reference	89
5.42.1	Detailed Description	89
5.43	Crosstales.RTVoice.Demo.Util.MaterialChanger Class Reference	90
5.43.1	Detailed Description	90
5.44	Crosstales.RTVoice.Demo.NativeAudio Class Reference	90
5.44.1	Detailed Description	91
5.45	Crosstales.RTVoice.Demo.Util.NativeController Class Reference	91
5.45.1	Detailed Description	91
5.45.2	Member Data Documentation	91
5.45.2.1	Active	91
5.45.2.2	Objects	92
5.46	Crosstales.Common.EditorTask.NYCheck Class Reference	92
5.46.1	Detailed Description	92
5.47	Crosstales.Common.EditorTask.OCCheck Class Reference	92
5.47.1	Detailed Description	92
5.48	Crosstales.Common.Util.PlatformController Class Reference	92
5.48.1	Detailed Description	93
5.48.2	Member Data Documentation	93
5.48.2.1	Objects	93
5.48.2.2	Platforms	93
5.49	Crosstales.RTVoice.Demo.Util.PlatformController Class Reference	94
5.49.1	Detailed Description	94
5.50	Crosstales.RTVoice.Demo.PreGeneratedAudio Class Reference	94
5.50.1	Detailed Description	95

5.51	Crosstales.Common.Util.RandomColor Class Reference	95
5.51.1	Detailed Description	95
5.52	Crosstales.Common.Util.RandomRotator Class Reference	96
5.52.1	Detailed Description	96
5.53	Crosstales.Common.Util.RandomScaler Class Reference	96
5.53.1	Detailed Description	97
5.54	Crosstales.RTVoice.EditorTask.ReminderCheck Class Reference	97
5.54.1	Detailed Description	97
5.55	Crosstales.RTVoice.EditorIntegration.RTVoiceGameObject Class Reference	97
5.55.1	Detailed Description	97
5.56	RTVoiceIOSBridge Class Reference	98
5.56.1	Method Documentation	98
5.56.1.1	setVoices()	98
5.56.1.2	speak:text:rate:pitch:volume:(NSString *name,[text] NSString *text,[rate] float rate,[pitch] float pitch,[volume] float volume)	98
5.56.1.3	stop()	98
5.57	RTVoiceIOSBridge() Category Reference	99
5.58	Crosstales.RTVoice.EditorIntegration.RTVoiceMenu Class Reference	99
5.58.1	Detailed Description	99
5.59	Crosstales.UI.Util.ScrollRectHandler Class Reference	99
5.59.1	Detailed Description	100
5.60	Crosstales.RTVoice.Demo.SendMessage Class Reference	100
5.60.1	Detailed Description	101
5.61	Crosstales.RTVoice.Model.Sequence Class Reference	101
5.61.1	Detailed Description	102
5.61.2	Member Data Documentation	102
5.61.2.1	Mode	102
5.61.2.2	Pitch	102
5.61.2.3	Rate	102
5.61.2.4	RTVoiceNameAndroid	102
5.61.2.5	RTVoiceNameIOS	102

5.61.2.6	RTVoiceNameMac	102
5.61.2.7	RTVoiceNameWindows	102
5.61.2.8	RTVoiceNameWSA	102
5.61.2.9	Source	102
5.61.2.10	Text	103
5.61.2.11	Volume	103
5.61.3	Property Documentation	103
5.61.3.1	RTVoiceName	103
5.62	Crosstales.RTVoice.Demo.SequenceCaller Class Reference	103
5.62.1	Detailed Description	104
5.63	Crosstales.RTVoice.Tool.Sequencer Class Reference	104
5.63.1	Detailed Description	105
5.63.2	Member Function Documentation	105
5.63.2.1	PlayAllSequences()	105
5.63.2.2	PlayNextSequence()	105
5.63.2.3	PlaySequence(int index=0)	105
5.63.2.4	StopAllSequences()	105
5.63.3	Member Data Documentation	105
5.63.3.1	Culture	105
5.63.3.2	Delay	105
5.63.3.3	PlayOnStart	106
5.63.3.4	Sequences	106
5.63.4	Property Documentation	106
5.63.4.1	CurrentCulture	106
5.63.4.2	CurrentSequence	106
5.64	Crosstales.RTVoice.EditorExtension.SequencerEditor Class Reference	106
5.64.1	Detailed Description	107
5.65	Crosstales.Common.Util.SerializeDeSerialize< T > Class Template Reference	107
5.65.1	Detailed Description	107
5.66	Crosstales.RTVoice.EditorTask.SetApiLevel Class Reference	107

5.66.1 Detailed Description	107
5.67 Crosstales.RTVoice.EditorTask.SetupResources Class Reference	108
5.67.1 Detailed Description	108
5.68 HutongGames.PlayMaker.Actions.Silence Class Reference	108
5.68.1 Detailed Description	109
5.69 Crosstales.RTVoice.PlayMaker.SilenceEditor Class Reference	109
5.69.1 Detailed Description	109
5.70 Crosstales.RTVoice.Demo.Simple Class Reference	109
5.70.1 Detailed Description	110
5.71 Crosstales.RTVoice.Demo.SimpleNative Class Reference	110
5.71.1 Detailed Description	111
5.72 Crosstales.UI.Social Class Reference	111
5.72.1 Detailed Description	112
5.73 HutongGames.PlayMaker.Actions.Speak Class Reference	112
5.73.1 Detailed Description	113
5.73.2 Member Data Documentation	113
5.73.2.1 Culture	113
5.73.2.2 RTVoiceNameAndroid	113
5.73.2.3 RTVoiceNameIOS	113
5.73.2.4 RTVoiceNameMac	113
5.73.2.5 RTVoiceNameMaryTTS	113
5.73.2.6 RTVoiceNameWindows	113
5.73.2.7 RTVoiceNameWSA	113
5.73.2.8 Text	113
5.74 Crosstales.RTVoice.SALSA.Speak Class Reference	114
5.75 Crosstales.RTVoice.SALSA.Speak2D Class Reference	114
5.76 HutongGames.PlayMaker.Actions.SpeakBase Class Reference	115
5.76.1 Detailed Description	116
5.76.2 Member Data Documentation	116
5.76.2.1 AudioSource	116

5.76.2.2	Mode	116
5.76.2.3	Pitch	116
5.76.2.4	Rate	116
5.76.2.5	Volume	116
5.77	Crosstales.RTVoice.PlayMaker.SpeakEditor Class Reference	117
5.77.1	Detailed Description	117
5.78	Crosstales.RTVoice.Speaker Class Reference	117
5.78.1	Detailed Description	120
5.78.2	Member Function Documentation	120
5.78.2.1	ApproximateSpeechLength(string text, float rate=1f, float wordsPerMinute=175f, float timeFactor=0.9f)	120
5.78.2.2	Generate(Model.Wrapper wrapper)	121
5.78.2.3	Generate(string text, string outputFile, Model.Voice voice=null, float rate=1f, float pitch=1f, float volume=1f)	121
5.78.2.4	isVoiceForCultureAvailable(string culture)	121
5.78.2.5	isVoiceForNameAvailable(string name)	121
5.78.2.6	Silence()	122
5.78.2.7	Silence(string uid)	122
5.78.2.8	Speak(string text, AudioSource source=null, Model.Voice voice=null, bool speakImmediately=true, float rate=1f, float pitch=1f, float volume=1f, string outputFile="")	122
5.78.2.9	Speak(Model.Wrapper wrapper)	122
5.78.2.10	SpeakMarkedWordsWithUID(Model.Wrapper wrapper)	123
5.78.2.11	SpeakMarkedWordsWithUID(string uid, string text, AudioSource source, Model.Voice voice=null, float rate=1f, float pitch=1f)	123
5.78.2.12	SpeakNative(string text, Model.Voice voice=null, float rate=1f, float pitch=1f, float volume=1f)	123
5.78.2.13	SpeakNative(Model.Wrapper wrapper)	124
5.78.2.14	SpeakNativeWithUID(Model.Wrapper wrapper)	124
5.78.2.15	SpeakWithUID(Model.Wrapper wrapper)	124
5.78.2.16	VoiceForCulture(string culture, int index=0, string fallbackCulture="")	124
5.78.2.17	VoiceForName(string name)	125
5.78.2.18	VoicesForCulture(string culture)	125

5.78.3	Member Data Documentation	125
5.78.3.1	AutoClearTags	125
5.78.3.2	DontDestroy	125
5.78.3.3	MaryTTSType	125
5.78.3.4	MaryTTSPassword	126
5.78.3.5	MaryTTSPort	126
5.78.3.6	MaryTTSType	126
5.78.3.7	MaryTTSType	126
5.78.3.8	MaryTTSType	126
5.78.3.9	SilenceOnDisable	126
5.78.3.10	SilenceOnFocustLost	126
5.78.4	Property Documentation	126
5.78.4.1	AudioFileExtension	126
5.78.4.2	Cultures	127
5.78.4.3	isAutoClearTags	127
5.78.4.4	isMaryMode	127
5.78.4.5	isSilenceOnDisable	127
5.78.4.6	isSilenceOnFocustLost	127
5.78.4.7	isSpeaking	127
5.78.4.8	isTTSAvailable	127
5.78.4.9	MaryPassword	127
5.78.4.10	MaryPort	128
5.78.4.11	MaryType	128
5.78.4.12	MaryUrl	128
5.78.4.13	MaryUser	128
5.78.4.14	OnErrorInfo	128
5.78.4.15	OnProviderChange	128
5.78.4.16	OnSpeakAudioGenerationComplete	128
5.78.4.17	OnSpeakAudioGenerationStart	128
5.78.4.18	OnSpeakComplete	128

5.78.4.19 OnSpeakCurrentPhoneme	128
5.78.4.20 OnSpeakCurrentViseme	129
5.78.4.21 OnSpeakCurrentWord	129
5.78.4.22 OnSpeakStart	129
5.78.4.23 OnVoicesReady	129
5.78.4.24 Voices	129
5.79 Crosstales.RTVoice.EditorExtension.SpeakerEditor Class Reference	129
5.79.1 Detailed Description	130
5.80 Crosstales.RTVoice.SALSA.SpeakSimple Class Reference	130
5.81 HutongGames.PlayMaker.Actions.SpeakUI Class Reference	130
5.81.1 Detailed Description	131
5.81.2 Member Data Documentation	131
5.81.2.1 Culture	131
5.81.2.2 RTVoiceName	131
5.81.2.3 Text	131
5.82 Crosstales.RTVoice.PlayMaker.SpeakUIEditor Class Reference	131
5.82.1 Detailed Description	132
5.83 Crosstales.RTVoice.Demo.SpeakWrapper Class Reference	132
5.83.1 Detailed Description	132
5.84 Crosstales.DJ.Demo.Util.SpectrumVisualizer Class Reference	133
5.84.1 Detailed Description	133
5.85 Crosstales.RTVoice.Tool.SpeechText Class Reference	133
5.85.1 Detailed Description	135
5.85.2 Member Function Documentation	135
5.85.2.1 Silence()	135
5.85.2.2 Speak()	135
5.85.3 Member Data Documentation	135
5.85.3.1 Culture	135
5.85.3.2 Delay	135
5.85.3.3 FileInsideAssets	135

5.85.3.4	FileName	136
5.85.3.5	FilePath	136
5.85.3.6	GenerateAudioFile	136
5.85.3.7	Mode	136
5.85.3.8	Pitch	136
5.85.3.9	PlayOnStart	136
5.85.3.10	Rate	136
5.85.3.11	RTVoiceNameAndroid	136
5.85.3.12	RTVoiceNameIOS	136
5.85.3.13	RTVoiceNameMac	136
5.85.3.14	RTVoiceNameMaryTTS	137
5.85.3.15	RTVoiceNameWindows	137
5.85.3.16	RTVoiceNameWSA	137
5.85.3.17	Source	137
5.85.3.18	Text	137
5.85.3.19	Volume	137
5.85.4	Property Documentation	137
5.85.4.1	CurrentCulture	137
5.85.4.2	CurrentPitch	137
5.85.4.3	CurrentRate	137
5.85.4.4	CurrentText	137
5.85.4.5	CurrentVolume	138
5.85.4.6	RTVoiceName	138
5.86	Crosstales.RTVoice.EditorExtension.SpeechTextEditor Class Reference	138
5.86.1	Detailed Description	138
5.87	Crosstales.UI.StaticManager Class Reference	139
5.87.1	Detailed Description	139
5.88	Crosstales.RTVoice.EditorTask.Telemetry Class Reference	139
5.88.1	Detailed Description	139
5.89	Crosstales.RTVoice.Tool.TextFileSpeaker Class Reference	140

5.89.1 Detailed Description	141
5.89.2 Member Function Documentation	141
5.89.2.1 Silence()	141
5.89.2.2 Speak()	141
5.89.2.3 SpeakText(int index=-1)	141
5.89.3 Member Data Documentation	142
5.89.3.1 Culture	142
5.89.3.2 Delay	142
5.89.3.3 Mode	142
5.89.3.4 Pitch	142
5.89.3.5 PlayOnStart	142
5.89.3.6 Rate	142
5.89.3.7 RTVoiceNameAndroid	142
5.89.3.8 RTVoiceNameIOS	142
5.89.3.9 RTVoiceNameMac	142
5.89.3.10 RTVoiceNameMaryTTS	143
5.89.3.11 RTVoiceNameWindows	143
5.89.3.12 RTVoiceNameWSA	143
5.89.3.13 Source	143
5.89.3.14 TextFiles	143
5.89.3.15 Volume	143
5.89.4 Property Documentation	143
5.89.4.1 CurrentCulture	143
5.89.4.2 CurrentPitch	143
5.89.4.3 CurrentRate	143
5.89.4.4 CurrentVolume	143
5.89.4.5 RTVoiceName	144
5.90 Crosstales.RTVoice.EditorExtension.TextFileSpeakerEditor Class Reference	144
5.90.1 Detailed Description	144
5.91 Crosstales.RTVoice.UDEA2.UDEAConnector Class Reference	144

5.91.1	Detailed Description	145
5.91.2	Member Data Documentation	145
5.91.2.1	Culture	145
5.91.2.2	Voices	145
5.92	Crosstales.RTVoice.UDEA2.UDEAConnectorEditor Class Reference	145
5.92.1	Detailed Description	146
5.93	Crosstales.RTVoice.UDEA2.UDEAVoiceWrapper Class Reference	146
5.93.1	Detailed Description	147
5.93.2	Member Data Documentation	147
5.93.2.1	IgnoreCharacter	147
5.93.2.2	Pitch	147
5.93.2.3	Rate	147
5.93.2.4	RTVoiceNameAndroid	147
5.93.2.5	RTVoiceNameIOS	147
5.93.2.6	RTVoiceNameMac	147
5.93.2.7	RTVoiceNameMaryTTS	147
5.93.2.8	RTVoiceNameWindows	147
5.93.2.9	RTVoiceNameWSA	148
5.93.2.10	Source	148
5.93.2.11	UDEAVoiceName	148
5.93.2.12	Volume	148
5.93.3	Property Documentation	148
5.93.3.1	RTVoiceName	148
5.94	Crosstales.UI.UIDrag Class Reference	148
5.94.1	Detailed Description	149
5.95	Crosstales.UI.UIFocus Class Reference	149
5.95.1	Detailed Description	149
5.96	Crosstales.UI.UIWindowManager Class Reference	150
5.96.1	Detailed Description	150
5.96.2	Member Data Documentation	150

5.96.2.1	Windows	150
5.97	Crosstales.RTVoice.EditorTask.UpdateCheck Class Reference	150
5.97.1	Detailed Description	151
5.98	Crosstales.RTVoice.Model.Voice Class Reference	151
5.98.1	Detailed Description	151
5.98.2	Constructor & Destructor Documentation	151
5.98.2.1	Voice(string name, string description, string gender, string age, string culture)	151
5.98.2.2	Voice(string name, string description, string culture)	152
5.98.3	Member Data Documentation	152
5.98.3.1	Age	152
5.98.3.2	Culture	152
5.98.3.3	Description	152
5.98.3.4	Gender	152
5.98.3.5	Name	152
5.99	Crosstales.RTVoice.Tool.VoiceInitializer Class Reference	153
5.99.1	Detailed Description	153
5.99.2	Member Data Documentation	153
5.99.2.1	AllVoices	153
5.99.2.2	DestroyWhenFinished	153
5.99.2.3	Provider	153
5.99.2.4	VoiceNames	154
5.100	Crosstales.RTVoice.EditorExtension.VoiceInitializerEditor Class Reference	154
5.100.1	Detailed Description	154
5.101	Crosstales.RTVoice.Provider.VoiceProviderAndroid Class Reference	154
5.101.1	Detailed Description	155
5.101.2	Constructor & Destructor Documentation	155
5.101.2.1	VoiceProviderAndroid(MonoBehaviour obj)	155
5.101.3	Member Function Documentation	155
5.101.3.1	Generate(Model.Wrapper wrapper)	155
5.101.3.2	Silence()	156

5.101.3.3 Speak(Model.Wrapper wrapper)	156
5.101.3.4 SpeakNative(Model.Wrapper wrapper)	156
5.102Crosstales.RTVoice.Provider.VoiceProviderIOS Class Reference	156
5.102.1 Detailed Description	157
5.102.2 Constructor & Destructor Documentation	157
5.102.2.1 VoiceProviderIOS(MonoBehaviour obj)	157
5.102.3 Member Function Documentation	157
5.102.3.1 Generate(Model.Wrapper wrapper)	158
5.102.3.2 SetState(string state)	158
5.102.3.3 SetVoices(string voicesText)	158
5.102.3.4 Silence()	158
5.102.3.5 Speak(Model.Wrapper wrapper)	158
5.102.3.6 SpeakNative(Model.Wrapper wrapper)	159
5.102.3.7 WordSpoken()	159
5.103Crosstales.RTVoice.Provider.VoiceProviderMacOS Class Reference	159
5.103.1 Detailed Description	160
5.103.2 Constructor & Destructor Documentation	160
5.103.2.1 VoiceProviderMacOS(MonoBehaviour obj)	160
5.103.3 Member Function Documentation	160
5.103.3.1 Generate(Model.Wrapper wrapper)	160
5.103.3.2 Speak(Model.Wrapper wrapper)	160
5.103.3.3 SpeakNative(Model.Wrapper wrapper)	160
5.104Crosstales.RTVoice.Provider.VoiceProviderMary Class Reference	161
5.104.1 Detailed Description	161
5.104.2 Constructor & Destructor Documentation	161
5.104.2.1 VoiceProviderMary(MonoBehaviour obj, string url, int port, string user, string password, Model.Enum.MaryTTSType type)	161
5.104.3 Member Function Documentation	162
5.104.3.1 Generate(Model.Wrapper wrapper)	162
5.104.3.2 Silence()	162
5.104.3.3 Speak(Model.Wrapper wrapper)	162

5.104.3.4 SpeakNative(Model.Wrapper wrapper)	162
5.105Crosstales.RTVoice.Provider.VoiceProviderWindows Class Reference	163
5.105.1 Detailed Description	163
5.105.2 Constructor & Destructor Documentation	163
5.105.2.1 VoiceProviderWindows(MonoBehaviour obj)	163
5.105.3 Member Function Documentation	164
5.105.3.1 Generate(Model.Wrapper wrapper)	164
5.105.3.2 Speak(Model.Wrapper wrapper)	164
5.105.3.3 SpeakNative(Model.Wrapper wrapper)	164
5.106Crosstales.RTVoice.Provider.VoiceProviderWSA Class Reference	165
5.106.1 Constructor & Destructor Documentation	165
5.106.1.1 VoiceProviderWSA(MonoBehaviour obj)	165
5.106.2 Member Function Documentation	165
5.106.2.1 Generate(Model.Wrapper wrapper)	165
5.106.2.2 Silence()	166
5.106.2.3 Speak(Model.Wrapper wrapper)	166
5.106.2.4 SpeakNative(Model.Wrapper wrapper)	166
5.107Crosstales.UI.WindowManager Class Reference	166
5.107.1 Detailed Description	167
5.107.2 Member Data Documentation	167
5.107.2.1 Dependencies	167
5.107.2.2 Speed	167
5.108Crosstales.RTVoice.Model.Wrapper Class Reference	167
5.108.1 Detailed Description	168
5.108.2 Constructor & Destructor Documentation	168
5.108.2.1 Wrapper()	168
5.108.2.2 Wrapper(string text, Voice voice=null, float rate=1f, float pitch=1f, float volume=1f, AudioSource source=null, bool speakImmediately=true, string outputFile="")	168
5.108.2.3 Wrapper(string uid, string text, Voice voice=null, float rate=1f, float pitch=1f, float volume=1f, AudioSource source=null, bool speakImmediately=true, string outputFile="")	169
5.108.3 Member Data Documentation	169
5.108.3.1 OutputFile	169
5.108.3.2 Source	169
5.108.3.3 SpeakImmediately	169
5.108.3.4 Uid	170
5.108.3.5 Voice	170
5.108.4 Property Documentation	170
5.108.4.1 Created	170
5.108.4.2 Pitch	170
5.108.4.3 Rate	170
5.108.4.4 Text	170
5.108.4.5 Volume	170

6	More information	171
6.1	Homepage	171
6.2	AssetStore	171
6.3	Forum	171
6.4	Documentation	171
6.5	Demos	171
6.5.1	WebGL	171
6.5.2	Windows	171
6.5.3	macOS	172
6.5.4	Android	172
6.6	Videos	172
6.6.1	Promotion	172
6.6.2	Tutorial	172
	Index	173

Chapter 1

Namespace Index

1.1 Packages

Here are the packages with brief descriptions (if available):

Crosstales	11
Crosstales.Common	11
Crosstales.Common.EditorTask	11
Crosstales.Common.EditorUtil	11
Crosstales.Common.Util	12
Crosstales.DJ	12
Crosstales.DJ.Demo	12
Crosstales.DJ.Demo.Util	12
Crosstales.RTVoice	13
Crosstales.RTVoice.Demo	13
Crosstales.RTVoice.Demo.Util	14
Crosstales.RTVoice.EditorExtension	14
Crosstales.RTVoice.EditorIntegration	14
Crosstales.RTVoice.EditorTask	15
Crosstales.RTVoice.EditorUtil	15
Crosstales.RTVoice.Model	16
Crosstales.RTVoice.Model.Enum	16
Crosstales.RTVoice.PlayMaker	17
Crosstales.RTVoice.Provider	17
Crosstales.RTVoice.SALSA	17
Crosstales.RTVoice.Tool	18
Crosstales.RTVoice.UDEA2	18
Crosstales.RTVoice.Util	18
Crosstales.UI	19
Crosstales.UI.Util	19
HutongGames	19
HutongGames.PlayMaker	19
HutongGames.PlayMaker.Actions	19

Chapter 2

Hierarchical Index

2.1 Class Hierarchy

This inheritance list is sorted roughly, but not completely, alphabetically:

Crosstales.RTVoice.EditorTask.AutoInitialize	26
<AVSpeechSynthesizerDelegate>	
RTVoiceIOSBridge()	99
Crosstales.Common.EditorTask.BaseCompileDefines	26
Crosstales.RTVoice.EditorTask.CompileDefines	45
Crosstales.Common.Util.BaseConstants	27
Crosstales.RTVoice.Util.Constants	51
Crosstales.Common.EditorUtil.BaseGAApi	31
Crosstales.RTVoice.EditorUtil.GAApi	75
Crosstales.Common.Util.BaseHelper	31
Crosstales.RTVoice.Util.Helper	82
Crosstales.Common.EditorTask.BaseSetupResources	39
Crosstales.RTVoice.EditorTask.SetupResources	108
Crosstales.RTVoice.Provider.BaseVoiceProvider	40
Crosstales.RTVoice.Provider.VoiceProviderAndroid	154
Crosstales.RTVoice.Provider.VoiceProviderIOS	156
Crosstales.RTVoice.Provider.VoiceProviderMacOS	159
Crosstales.RTVoice.Provider.VoiceProviderMary	161
Crosstales.RTVoice.Provider.VoiceProviderWindows	163
Crosstales.RTVoice.Provider.VoiceProviderWSA	165
Crosstales.RTVoice.EditorUtil.BuildPostprocessor	45
Crosstales.RTVoice.Util.Config	46
Crosstales.RTVoice.EditorTask.ConfigLoader	49
Crosstales.Common.Util.CTPlayerPrefs	57
CustomActionEditor	
Crosstales.RTVoice.PlayMaker.SilenceEditor	109
Crosstales.RTVoice.PlayMaker.SpeakEditor	117
Crosstales.RTVoice.PlayMaker.SpeakUIEditor	131
Editor	
Crosstales.RTVoice.EditorExtension.AudioFileGeneratorEditor	22
Crosstales.RTVoice.EditorExtension.LoudspeakerEditor	89
Crosstales.RTVoice.EditorExtension.SequencerEditor	106
Crosstales.RTVoice.EditorExtension.SpeakerEditor	129

Crosstales.RTVoice.EditorExtension.SpeechTextEditor	138
Crosstales.RTVoice.EditorExtension.TextFileSpeakerEditor	144
Crosstales.RTVoice.EditorExtension.VoiceInitializerEditor	154
Crosstales.RTVoice.UDEA2.UDEAConnectorEditor	145
Crosstales.RTVoice.EditorUtil.EditorConfig	63
Crosstales.RTVoice.EditorUtil.EditorConstants	65
Crosstales.RTVoice.EditorUtil.EditorHelper	67
EditorWindow	
Crosstales.RTVoice.EditorIntegration.ConfigBase	49
Crosstales.RTVoice.EditorIntegration.ConfigPreferences	50
Crosstales.RTVoice.EditorIntegration.ConfigWindow	50
Crosstales.ExtensionMethods	69
FsmStateAction	
HutongGames.PlayMaker.Actions.Silence	108
HutongGames.PlayMaker.Actions.SpeakBase	115
HutongGames.PlayMaker.Actions.Speak	112
HutongGames.PlayMaker.Actions.SpeakUI	130
Crosstales.RTVoice.EditorTask.Launch	84
MonoBehaviour	
Crosstales.Common.Util.PlatformController	92
Crosstales.RTVoice.Demo.Util.PlatformController	94
Crosstales.Common.Util.RandomColor	95
Crosstales.Common.Util.RandomRotator	96
Crosstales.Common.Util.RandomScaler	96
Crosstales.DJ.Demo.Util.FFTAnalyzer	74
Crosstales.DJ.Demo.Util.SpectrumVisualizer	133
Crosstales.RTVoice.Demo.Dialog	62
Crosstales.RTVoice.Demo.GUIAudioFilter	76
Crosstales.RTVoice.Demo.GUIDialog	77
Crosstales.RTVoice.Demo.GUIMain	78
Crosstales.RTVoice.Demo.GUIMultiAudioFilter	79
Crosstales.RTVoice.Demo.GUIScenes	80
Crosstales.RTVoice.Demo.GUISpeech	81
Crosstales.RTVoice.Demo.NativeAudio	90
Crosstales.RTVoice.Demo.PreGeneratedAudio	94
Crosstales.RTVoice.Demo.SendMessage	100
Crosstales.RTVoice.Demo.SequenceCaller	103
Crosstales.RTVoice.Demo.Simple	109
Crosstales.RTVoice.Demo.SimpleNative	110
Crosstales.RTVoice.Demo.SpeakWrapper	132
Crosstales.RTVoice.Demo.Util.iOSController	84
Crosstales.RTVoice.Demo.Util.MaterialChanger	90
Crosstales.RTVoice.Demo.Util.NativeController	91
Crosstales.RTVoice.EditorIntegration.RTVoiceGameObject	97
Crosstales.RTVoice.LiveSpeaker	84
Crosstales.RTVoice.SALSA.Bots	44
Crosstales.RTVoice.SALSA.Speak	114
Crosstales.RTVoice.SALSA.Speak2D	114
Crosstales.RTVoice.SALSA.SpeakSimple	130
Crosstales.RTVoice.Speaker	117
Crosstales.RTVoice.Tool.AudioFileGenerator	21
Crosstales.RTVoice.Tool.Loudspeaker	87
Crosstales.RTVoice.Tool.Sequencer	104
Crosstales.RTVoice.Tool.SpeechText	133
Crosstales.RTVoice.Tool.TextFileSpeaker	140
Crosstales.RTVoice.Tool.VoiceInitializer	153
Crosstales.RTVoice.UDEA2.UDEAConnector	144
Crosstales.UI.Social	111

Crosstales.UI.StaticManager	139
Crosstales.UI.UIDrag	148
Crosstales.UI.UIFocus	149
Crosstales.UI.UIWindowManager	150
Crosstales.UI.Util.AudioFilterController	23
Crosstales.UI.Util.AudioSourceController	24
Crosstales.UI.Util.FPSDisplay	75
Crosstales.UI.Util.ScrollRectHandler	99
Crosstales.UI.WindowManager	166
NSObject	
RTVoiceIOSBridge	98
Crosstales.Common.EditorTask.NYCheck	92
Crosstales.Common.EditorTask.OCCheck	92
Crosstales.RTVoice.EditorTask.ReminderCheck	97
Crosstales.RTVoice.EditorIntegration.RTVoiceMenu	99
Crosstales.RTVoice.Model.Sequence	101
Crosstales.Common.Util.SerializeDeSerialize< T >	107
Crosstales.RTVoice.EditorTask.SetApiLevel	107
Crosstales.RTVoice.EditorTask.Telemetry	139
Crosstales.RTVoice.UDEA2.UDEAVoiceWrapper	146
Crosstales.RTVoice.EditorTask.UpdateCheck	150
Crosstales.RTVoice.Model.Voice	151
WebClient	
Crosstales.Common.Util.CTWebClient	61
Crosstales.RTVoice.Model.Wrapper	167

Chapter 3

Class Index

3.1 Class List

Here are the classes, structs, unions and interfaces with brief descriptions:

Crosstales.RTVoice.Tool.AudioFileGenerator	21
Process files with configured speeches.	
Crosstales.RTVoice.EditorExtension.AudioFileGeneratorEditor	22
Custom editor for the 'SpeechText'-class.	
Crosstales.UI.Util.AudioFilterController	23
Controller for audio filters.	
Crosstales.UI.Util.AudioSourceController	24
Controller for AudioSources.	
Crosstales.RTVoice.EditorTask.AutoInitalize	26
Automatically adds the neccessary RTVoice-prefabs to the current scene.	
Crosstales.Common.EditorTask.BaseCompileDefines	26
Base for adding the given define symbols to PlayerSettings define symbols.	
Crosstales.Common.Util.BaseConstants	27
Base for collected constants of very general utility for the asset.	
Crosstales.Common.EditorUtil.BaseGAApi	31
Base GA-wrapper API.	
Crosstales.Common.Util.BaseHelper	31
Base for various helper functions.	
Crosstales.Common.EditorTask.BaseSetupResources	39
Base for copying all resources to 'Editor Default Resources'.	
Crosstales.RTVoice.Provider.BaseVoiceProvider	40
Base class for voice providers.	
Crosstales.RTVoice.SALSA.Bots	44
This is class for conversations between two SALSA-Bots.	
Crosstales.RTVoice.EditorUtil.BuildPostprocessor	45
BuildPostprocessor for Windows. Adds the TTS-wrapper to the build.	
Crosstales.RTVoice.EditorTask.CompileDefines	45
Adds the given define symbols to PlayerSettings define symbols.	
Crosstales.RTVoice.Util.Config	46
Configuration for the asset.	
Crosstales.RTVoice.EditorIntegration.ConfigBase	49
Base class for editor windows.	
Crosstales.RTVoice.EditorTask.ConfigLoader	49
Loads the configuration at startup.	
Crosstales.RTVoice.EditorIntegration.ConfigPreferences	50
Unity "Preferences" extension.	

Crosstales.RTVoice.EditorIntegration.ConfigWindow	
Editor window extension.	50
Crosstales.RTVoice.Util.Constants	
Collected constants of very general utility for the asset.	51
Crosstales.Common.Util.CTPlayerPrefs	
Wrapper for the PlayerPrefs.	57
Crosstales.Common.Util.CTWebClient	
Specialized WebClient.	61
Crosstales.RTVoice.Demo.Dialog	
Simple dialog system with TTS voices.	62
Crosstales.RTVoice.EditorUtil.EditorConfig	
Editor configuration for the asset.	63
Crosstales.RTVoice.EditorUtil.EditorConstants	
Collected constants of very general utility for the asset.	65
Crosstales.RTVoice.EditorUtil.EditorHelper	
Editor helper class.	67
Crosstales.ExtensionMethods	
Various extension methods.	69
Crosstales.DJ.Demo.Util.FFTAnalyzer	
FFT analyzer for an audio channel.	74
Crosstales.UI.Util.FPSDisplay	
Simple FPS-Counter.	75
Crosstales.RTVoice.EditorUtil.GAApi	
GA-wrapper API.	75
Crosstales.RTVoice.Demo.GUIAudioFilter	
Simple GUI for audio filters.	76
Crosstales.RTVoice.Demo.GUIDialog	
Simple GUI for runtime dialogs with all available OS voices.	77
Crosstales.RTVoice.Demo.GUIMain	
Main GUI component for all demo scenes.	78
Crosstales.RTVoice.Demo.GUIMultiAudioFilter	
Simple GUI for audio filters on multiple objects.	79
Crosstales.RTVoice.Demo.GUIScenes	
Main GUI scene manager for all demo scenes.	80
Crosstales.RTVoice.Demo.GUISpeech	
Simple GUI for runtime TTS with all available OS voices.	81
Crosstales.RTVoice.Util.Helper	
Various helper functions.	82
Crosstales.RTVoice.Demo.Util.iOSController	
Enables MaryTTS on iOS for specific scenes.	84
Crosstales.RTVoice.EditorTask.Launch	
Show the configuration window on the first launch.	84
Crosstales.RTVoice.LiveSpeaker	
Wrapper of the main component from RTVoice for MonoBehaviour-access (like "SendMessage").	84
Crosstales.RTVoice.Tool.Loudspeaker	
Loudspeaker for an AudioSource.	87
Crosstales.RTVoice.EditorExtension.LoudspeakerEditor	
Custom editor for the 'Loudspeaker'-class.	89
Crosstales.RTVoice.Demo.Util.MaterialChanger	
Changes the material of a render while an AudioSource is playing.	90
Crosstales.RTVoice.Demo.NativeAudio	
Simple example with native audio for exact timing.	90
Crosstales.RTVoice.Demo.Util.NativeController	
Enables or disable game objects for native mode.	91
Crosstales.Common.EditorTask.NYCheck	
Checks if a 'Happy new year'-message must be displayed.	92
Crosstales.Common.EditorTask.OCCheck	
Checks if 'Online Check' is installed.	92

Crosstales.Common.Util.PlatformController	
Enables or disable game objects for a given platform.	92
Crosstales.RTVoice.Demo.Util.PlatformController	
Enables or disable game objects for a given platform.	94
Crosstales.RTVoice.Demo.PreGeneratedAudio	
Simple example with pre-generated audio for exact timing.	94
Crosstales.Common.Util.RandomColor	
Random color changer.	95
Crosstales.Common.Util.RandomRotator	
Random rotation changer.	96
Crosstales.Common.Util.RandomScaler	
Random scale changer.	96
Crosstales.RTVoice.EditorTask.ReminderCheck	
Reminds the customer to create an UAS review.	97
Crosstales.RTVoice.EditorIntegration.RTVoiceGameObject	
Editor component for the "Hierarchy"-menu.	97
RTVoiceIOSBridge	98
RTVoiceIOSBridge()	99
Crosstales.RTVoice.EditorIntegration.RTVoiceMenu	
Editor component for the "Tools"-menu.	99
Crosstales.UI.Util.ScrollRectHandler	
Changes the sensitivity of ScrollRects under various platforms.	99
Crosstales.RTVoice.Demo.SendMessage	
Simple "SendMessage" example.	100
Crosstales.RTVoice.Model.Sequence	
Model for a sequence.	101
Crosstales.RTVoice.Demo.SequenceCaller	
Simple Sequence caller example.	103
Crosstales.RTVoice.Tool.Sequencer	
Simple sequencer for dialogues.	104
Crosstales.RTVoice.EditorExtension.SequencerEditor	
Custom editor for the 'Sequencer'-class.	106
Crosstales.Common.Util.SerializeDeSerialize< T >	
Serialize and deserialize objects to/from binary files.	107
Crosstales.RTVoice.EditorTask.SetApiLevel	
Sets the required API levels.	107
Crosstales.RTVoice.EditorTask.SetupResources	
Moves all needed resources to 'Editor Default Resources'.	108
HutongGames.PlayMaker.Actions.Silence	
Silence-action for PlayMaker	108
Crosstales.RTVoice.PlayMaker.SilenceEditor	
Custom editor for the Silence-action.	109
Crosstales.RTVoice.Demo.Simple	
Simple TTS example.	109
Crosstales.RTVoice.Demo.SimpleNative	
Simple native TTS example.	110
Crosstales.UI.Social	
Crosstales social media links.	111
HutongGames.PlayMaker.Actions.Speak	
Speak-action for PlayMaker	112
Crosstales.RTVoice.SALSA.Speak	114
Crosstales.RTVoice.SALSA.Speak2D	114
HutongGames.PlayMaker.Actions.SpeakBase	
Base for Speak-actions in PlayMaker	115
Crosstales.RTVoice.PlayMaker.SpeakEditor	
Custom editor for the Speak-action.	117
Crosstales.RTVoice.Speaker	
Main component of RTVoice	117

Crosstales.RTVoice.EditorExtension.SpeakerEditor	
Custom editor for the 'Speaker'-class.	129
Crosstales.RTVoice.SALSA.SpeakSimple	130
HutongGames.PlayMaker.Actions.SpeakUI	
Speak-action for UI-components in PlayMaker	130
Crosstales.RTVoice.PlayMaker.SpeakUIEditor	
Custom editor for the SpeakUI-action.	131
Crosstales.RTVoice.Demo.SpeakWrapper	
Wrapper for the dynamic speakers.	132
Crosstales.DJ.Demo.Util.SpectrumVisualizer	
Simple spectrum visualizer.	133
Crosstales.RTVoice.Tool.SpeechText	
Allows to speak and store generated audio.	133
Crosstales.RTVoice.EditorExtension.SpeechTextEditor	
Custom editor for the 'SpeechText'-class.	138
Crosstales.UI.StaticManager	
Static Button Manager.	139
Crosstales.RTVoice.EditorTask.Telemetry	
Gather some telemetry data for the asset.	139
Crosstales.RTVoice.Tool.TextFileSpeaker	
Allows to speak text files.	140
Crosstales.RTVoice.EditorExtension.TextFileSpeakerEditor	
Custom editor for the 'TextFileSpeaker'-class.	144
Crosstales.RTVoice.UDEA2.UDEAConnector	
Connects UDEA and RT-Voice. Must be placed on a dialogue prefab.	144
Crosstales.RTVoice.UDEA2.UDEAConnectorEditor	
Custom editor for the 'UDEAConnector'-class.	145
Crosstales.RTVoice.UDEA2.UDEAVoiceWrapper	
Wrapper for an UDEA-character to an RT-Voice.	146
Crosstales.UI.UIDrag	
Allow to Drag the Windows arround.	148
Crosstales.UI.UIFocus	
Change the Focus on from a Window.	149
Crosstales.UI.UIWindowManager	
Change the state of all Window panels.	150
Crosstales.RTVoice.EditorTask.UpdateCheck	
Checks for updates of the asset.	150
Crosstales.RTVoice.Model.Voice	
Model for a voice.	151
Crosstales.RTVoice.Tool.VoiceInitializer	
Allows to initialize voices (useful on Android).	153
Crosstales.RTVoice.EditorExtension.VoiceInitializerEditor	
Custom editor for the 'VoiceInitializer'-class.	154
Crosstales.RTVoice.Provider.VoiceProviderAndroid	
Android voice provider.	154
Crosstales.RTVoice.Provider.VoiceProviderIOS	
iOS voice provider.	156
Crosstales.RTVoice.Provider.VoiceProviderMacOS	
MacOS voice provider.	159
Crosstales.RTVoice.Provider.VoiceProviderMary	
MaryTTS voice provider.	161
Crosstales.RTVoice.Provider.VoiceProviderWindows	
Windows voice provider.	163
Crosstales.RTVoice.Provider.VoiceProviderWSA	
.	165
Crosstales.UI.WindowManager	
Manager for a Window.	166
Crosstales.RTVoice.Model.Wrapper	
Wrapper for "Speak"-function calls.	167

Chapter 4

Namespace Documentation

4.1 Crosstales Namespace Reference

Namespaces

Classes

- class [ExtensionMethods](#)
Various extension methods.

4.2 Crosstales.Common Namespace Reference

Namespaces

4.3 Crosstales.Common.EditorTask Namespace Reference

Classes

- class [BaseCompileDefines](#)
Base for adding the given define symbols to PlayerSettings define symbols.
- class [BaseSetupResources](#)
Base for copying all resources to 'Editor Default Resources'.
- class [NYCheck](#)
Checks if a 'Happy new year'-message must be displayed.
- class [OCCheck](#)
Checks if 'Online Check' is installed.

4.4 Crosstales.Common.EditorUtil Namespace Reference

Classes

- class [BaseGAApi](#)
Base GA-wrapper API.

4.5 Crosstales.Common.Util Namespace Reference

Classes

- class [BaseConstants](#)
Base for collected constants of very general utility for the asset.
- class [BaseHelper](#)
Base for various helper functions.
- class [CTPlayerPrefs](#)
Wrapper for the PlayerPrefs.
- class [CTWebClient](#)
Specialized WebClient.
- class [PlatformController](#)
Enables or disable game objects for a given platform.
- class [RandomColor](#)
Random color changer.
- class [RandomRotator](#)
Random rotation changer.
- class [RandomScaler](#)
Random scale changer.
- class [SerializeDeSerialize](#)
Serialize and deserialize objects to/from binary files.

Enumerations

- enum [Platform](#) {
 OSX, Windows, IOS, Android,
 WSA, MaryTTS, Web, Unsupported }
All available platforms.

4.5.1 Enumeration Type Documentation

4.5.1.1 enum **Crosstales.Common.Util.Platform** [strong]

All available platforms.

4.6 Crosstales.DJ Namespace Reference

Namespaces

4.7 Crosstales.DJ.Demo Namespace Reference

Namespaces

4.8 Crosstales.DJ.Demo.Util Namespace Reference

Classes

- class [FFTAnalyzer](#)
FFT analyzer for an audio channel.
- class [SpectrumVisualizer](#)
Simple spectrum visualizer.

4.9 Crosstales.RTVoice Namespace Reference

Namespaces

Classes

- class [LiveSpeaker](#)
Wrapper of the main component from [RTVoice](#) for MonoBehaviour-access (like "SendMessage").
- class [Speaker](#)
Main component of [RTVoice](#).

4.10 Crosstales.RTVoice.Demo Namespace Reference

Namespaces

Classes

- class [Dialog](#)
Simple dialog system with TTS voices.
- class [GUIAudioFilter](#)
Simple GUI for audio filters.
- class [GUIDialog](#)
Simple GUI for runtime dialogs with all available OS voices.
- class [GUIMain](#)
Main GUI component for all demo scenes.
- class [GUIMultiAudioFilter](#)
Simple GUI for audio filters on multiple objects.
- class [GUIScenes](#)
Main GUI scene manager for all demo scenes.
- class [GUISpeech](#)
Simple GUI for runtime TTS with all available OS voices.
- class [NativeAudio](#)
Simple example with native audio for exact timing.
- class [PreGeneratedAudio](#)
Simple example with pre-generated audio for exact timing.
- class [SendMessage](#)
Simple "SendMessage" example.
- class [SequenceCaller](#)
Simple Sequence caller example.
- class [Simple](#)
Simple TTS example.
- class [SimpleNative](#)
Simple native TTS example.
- class [SpeakWrapper](#)
Wrapper for the dynamic speakers.

4.11 Crosstales.RTVoice.Demo.Util Namespace Reference

Classes

- class [iOSController](#)
Enables MaryTTS on iOS for specific scenes.
- class [MaterialChanger](#)
Changes the material of a renderer while an AudioSource is playing.
- class [NativeController](#)
Enables or disable game objects for native mode.
- class [PlatformController](#)
Enables or disable game objects for a given platform.

4.12 Crosstales.RTVoice.EditorExtension Namespace Reference

Classes

- class [AudioFileGeneratorEditor](#)
Custom editor for the 'SpeechText'-class.
- class [LoudspeakerEditor](#)
Custom editor for the 'Loudspeaker'-class.
- class [SequencerEditor](#)
Custom editor for the 'Sequencer'-class.
- class [SpeakerEditor](#)
Custom editor for the 'Speaker'-class.
- class [SpeechTextEditor](#)
Custom editor for the 'SpeechText'-class.
- class [TextFileSpeakerEditor](#)
Custom editor for the 'TextFileSpeaker'-class.
- class [VoiceInitalizerEditor](#)
Custom editor for the 'VoiceInitalizer'-class.

4.13 Crosstales.RTVoice.EditorIntegration Namespace Reference

Classes

- class [ConfigBase](#)
Base class for editor windows.
- class [ConfigPreferences](#)
Unity "Preferences" extension.
- class [ConfigWindow](#)
Editor window extension.
- class [RTVoiceGameObject](#)
Editor component for the "Hierarchy"-menu.
- class [RTVoiceMenu](#)
Editor component for the "Tools"-menu.

4.14 Crosstales.RTVoice.EditorTask Namespace Reference

Classes

- class [AutoInitialize](#)
Automatically adds the necessary RTVoice-prefabs to the current scene.
- class [CompileDefines](#)
Adds the given define symbols to PlayerSettings define symbols.
- class [ConfigLoader](#)
Loads the configuration at startup.
- class [Launch](#)
Show the configuration window on the first launch.
- class [ReminderCheck](#)
Reminds the customer to create an UAS review.
- class [SetApiLevel](#)
Sets the required API levels.
- class [SetupResources](#)
Moves all needed resources to 'Editor Default Resources'.
- class [Telemetry](#)
Gather some telemetry data for the asset.
- class [UpdateCheck](#)
Checks for updates of the asset.

Enumerations

- enum [UpdateStatus](#) {
 NOT_CHECKED, **NO_UPDATE**, **UPDATE**, **UPDATE_PRO**,
 UPDATE_VERSION, **DEPRECATED** }
All possible update stati.

4.14.1 Enumeration Type Documentation

4.14.1.1 enum **Crosstales.RTVoice.EditorTask.UpdateStatus** [strong]

All possible update stati.

4.15 Crosstales.RTVoice.EditorUtil Namespace Reference

Classes

- class [BuildPostprocessor](#)
BuildPostprocessor for Windows. Adds the TTS-wrapper to the build.
- class [EditorConfig](#)
Editor configuration for the asset.
- class [EditorConstants](#)
Collected constants of very general utility for the asset.
- class [EditorHelper](#)
Editor helper class.
- class [GAApi](#)
GA-wrapper API.

4.16 Crosstales.RTVoice.Model Namespace Reference

Namespaces

Classes

- class [Sequence](#)
Model for a sequence.
- class [Voice](#)
Model for a voice.
- class [Wrapper](#)
Wrapper for "Speak"-function calls.

4.17 Crosstales.RTVoice.Model.Enum Namespace Reference

Enumerations

- enum [MaryTTSType](#) { **RAWMARYXML**, **EMOTIONML**, **SSML**, **TEXT** }
The different MaryTTS input types.
- enum [ProviderType](#) { **Windows**, **macOS**, **Android**, **iOS**, **WSA**, **MaryTTS** }
Available provider types.
- enum [SpeakMode](#) { **Speak**, **SpeakNative** }
Available Speak-modes.

4.17.1 Enumeration Type Documentation

4.17.1.1 enum **Crosstales.RTVoice.Model.Enum.MaryTTSType** [strong]

The different MaryTTS input types.

4.17.1.2 enum **Crosstales.RTVoice.Model.Enum.ProviderType** [strong]

Available provider types.

4.17.1.3 enum **Crosstales.RTVoice.Model.Enum.SpeakMode** [strong]

Available Speak-modes.

4.18 Crosstales.RTVoice.PlayMaker Namespace Reference

Classes

- class [SilenceEditor](#)
Custom editor for the Silence-action.
- class [SpeakEditor](#)
Custom editor for the Speak-action.
- class [SpeakUIEditor](#)
Custom editor for the SpeakUI-action.

4.19 Crosstales.RTVoice.Provider Namespace Reference

Classes

- class [BaseVoiceProvider](#)
Base class for voice providers.
- class [VoiceProviderAndroid](#)
Android voice provider.
- class [VoiceProviderIOS](#)
iOS voice provider.
- class [VoiceProviderMacOS](#)
MacOS voice provider.
- class [VoiceProviderMary](#)
MaryTTS voice provider.
- class [VoiceProviderWindows](#)
Windows voice provider.
- class [VoiceProviderWSA](#)

4.20 Crosstales.RTVoice.SALSA Namespace Reference

Classes

- class [Bots](#)
This is class for conversations between two SALSA-Bots.
- class [Speak](#)
- class [Speak2D](#)
- class [SpeakSimple](#)

4.21 Crosstales.RTVoice.Tool Namespace Reference

Classes

- class [AudioFileGenerator](#)
Process files with configured speeches.
- class [Loudspeaker](#)
Loudspeaker for an AudioSource.
- class [Sequencer](#)
Simple sequencer for dialogues.
- class [SpeechText](#)
Allows to speak and store generated audio.
- class [TextFileSpeaker](#)
Allows to speak text files.
- class [VoiceInitializer](#)
Allows to initialize voices (useful on Android).

4.22 Crosstales.RTVoice.UDEA2 Namespace Reference

Classes

- class [UDEAConnector](#)
Connects UDEA and RT-Voice. Must be placed on a dialogue prefab.
- class [UDEAConnectorEditor](#)
Custom editor for the 'UDEAConnector'-class.
- class [UDEAVoiceWrapper](#)
Wrapper for an UDEA-character to an RT-Voice.

4.23 Crosstales.RTVoice.Util Namespace Reference

Classes

- class [Config](#)
Configuration for the asset.
- class [Constants](#)
Collected constants of very general utility for the asset.
- class [Helper](#)
Various helper functions.

4.24 Crosstales.UI Namespace Reference

Namespaces

Classes

- class [Social](#)
Crosstales social media links.
- class [StaticManager](#)
Static Button Manager.
- class [UIDrag](#)
Allow to Drag the Windows around.
- class [UIFocus](#)
Change the Focus on from a Window.
- class [UIWindowManager](#)
Change the state of all Window panels.
- class [WindowManager](#)
Manager for a Window.

4.25 Crosstales.UI.Util Namespace Reference

Classes

- class [AudioFilterController](#)
Controller for audio filters.
- class [AudioSourceController](#)
Controller for AudioSources.
- class [FPSDisplay](#)
Simple FPS-Counter.
- class [ScrollRectHandler](#)
Changes the sensitivity of ScrollRects under various platforms.

4.26 HutongGames Namespace Reference

Namespaces

4.27 HutongGames.PlayMaker Namespace Reference

Namespaces

4.28 HutongGames.PlayMaker.Actions Namespace Reference

Classes

- class [Silence](#)
Silence-action for [PlayMaker](#).
- class [Speak](#)
Speak-action for [PlayMaker](#).
- class [SpeakBase](#)
Base for Speak-actions in [PlayMaker](#).
- class [SpeakUI](#)
Speak-action for UI-components in [PlayMaker](#).


Chapter 5

Class Documentation

5.1 Crosstales.RTVoice.Tool.AudioFileGenerator Class Reference

Process files with configured speeches.

Inheritance diagram for Crosstales.RTVoice.Tool.AudioFileGenerator:



Public Member Functions

- void **OnEnable** ()
- void **OnDisable** ()
- void **OnValidate** ()
- void **Generate** ()
Generate the audio files from the text files.
- IEnumerator **generate** ()

Public Attributes

- TextAsset[] **TextFiles**
Text files to generate.
- bool **FileInsideAssets** = true
Are the specified file paths inside the Assets-folder (current project)? If this option is enabled, it prefixes the path with 'Application.dataPath' (default: true).

5.1.1 Detailed Description

Process files with configured speeches.

5.1.2 Member Function Documentation

5.1.2.1 void Crosstales.RTVoice.Tool.AudioFileGenerator.Generate ()

Generate the audio files from the text files.

5.1.3 Member Data Documentation

5.1.3.1 bool Crosstales.RTVoice.Tool.AudioFileGenerator.FileInsideAssets = true

Are the specified file paths inside the Assets-folder (current project)? If this option is enabled, it prefixes the path with 'Application.dataPath' (default: true).

5.1.3.2 TextAsset [] Crosstales.RTVoice.Tool.AudioFileGenerator.TextFiles

Text files to generate.


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/RTVoice/↔ Scripts/Tool/AudioFileGenerator.cs

5.2 Crosstales.RTVoice.EditorExtension.AudioFileGeneratorEditor Class Reference

Custom editor for the 'SpeechText'-class.

Inheritance diagram for Crosstales.RTVoice.EditorExtension.AudioFileGeneratorEditor:



Public Member Functions

- void **OnEnable** ()
- override void **OnInspectorGUI** ()

5.2.1 Detailed Description

Custom editor for the 'SpeechText'-class.


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/RTVoice/↔ Editor/Extension/AudioFileGeneratorEditor.cs

5.3 Crosstales.UI.Util.AudioFilterController Class Reference

Controller for audio filters.

Inheritance diagram for Crosstales.UI.Util.AudioFilterController:



Public Member Functions

- void **Start** ()
- void **Update** ()
- void **FindAllAudioFilters** ()
- void **ResetAudioFilters** ()
- void **ReverbFilterDropdownChanged** (System.Int32 index)
- void **ChorusFilterEnabled** (bool enabled)
- void **EchoFilterEnabled** (bool enabled)
- void **DistortionFilterEnabled** (bool enabled)
- void **DistortionFilterChanged** (float value)
- void **LowPassFilterEnabled** (bool enabled)
- void **LowPassFilterChanged** (float value)
- void **HighPassFilterEnabled** (bool enabled)
- void **HighPassFilterChanged** (float value)

Public Attributes

- bool **FindAllAudioFiltersOnStart** = true
Searches for all audio filters in the whole scene (default: true).
- AudioReverbFilter[] **ReverbFilters**
- AudioChorusFilter[] **ChorusFilters**
- AudioEchoFilter[] **EchoFilters**
- AudioDistortionFilter[] **DistortionFilters**
- AudioLowPassFilter[] **LowPassFilters**
- AudioHighPassFilter[] **HighPassFilters**
- bool **ResetAudioFiltersOnStart** = true
- bool **ChorusFilter** = false
- bool **EchoFilter** = false
- bool **DistortionFilter** = false
- float **DistortionFilterValue** = 0.5f
- bool **LowpassFilter** = false
- float **LowpassFilterValue** = 5000f
- bool **HighpassFilter** = false
- float **HighpassFilterValue** = 5000f
- Dropdown **ReverbFilterDropdown**
- Text **DistortionText**
- Text **LowpassText**
- Text **HighpassText**

5.3.1 Detailed Description

Controller for audio filters.

5.3.2 Member Data Documentation

5.3.2.1 `bool Crosstales.UI.Util.AudioFilterController.FindAllAudioFiltersOnStart = true`

Searches for all audio filters in the whole scene (default: true).


The documentation for this class was generated from the following file:

- `D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/Common/UI/Scripts/Util/AudioFilterController.cs`

5.4 Crosstales.UI.Util.AudioSourceController Class Reference

Controller for AudioSources.

Inheritance diagram for `Crosstales.UI.Util.AudioSourceController`:



Public Member Functions

- `void Update ()`
- `void FindAllAudioSources ()`
- `void ResetAudioFilters ()`
- `void MuteEnabled (bool enabled)`
- `void LoopEnabled (bool enabled)`
- `void VolumeChanged (float value)`
- `void PitchChanged (float value)`
- `void StereoPanChanged (float value)`

Public Attributes

- bool **FindAllAudioSourcesOnStart** = true
Searches for all AudioSource in the whole scene (default: true).
- AudioSource[] **AudioSources**
Active controlled AudioSources.
- bool **ResetAudioSourcesOnStart** = true
Resets all active AudioSources (default: true).
- bool **Mute** = false
Mute on/off (default: false).
- bool **Loop** = false
Loop on/off (default: false).
- float **Volume** = 1f
Volume of the audio (default: 1)
- float **Pitch** = 1f
Pitch of the audio (default: 1).
- float **StereoPan** = 0f
Stereo pan of the audio (default: 0).
- Text **VolumeText**
- Text **PitchText**
- Text **StereoPanText**

5.4.1 Detailed Description

Controller for AudioSources.

5.4.2 Member Data Documentation

5.4.2.1 AudioSource [] Crosstales.UI.Util.AudioSourceController.AudioSources

Active controlled AudioSources.

5.4.2.2 bool Crosstales.UI.Util.AudioSourceController.FindAllAudioSourcesOnStart = true

Searches for all AudioSource in the whole scene (default: true).

5.4.2.3 bool Crosstales.UI.Util.AudioSourceController.Loop = false

Loop on/off (default: false).

5.4.2.4 bool Crosstales.UI.Util.AudioSourceController.Mute = false

Mute on/off (default: false).

5.4.2.5 float Crosstales.UI.Util.AudioSourceController.Pitch = 1f

Pitch of the audio (default: 1).

5.4.2.6 bool Crosstales.UI.Util.AudioSourceController.ResetAudioSourcesOnStart = true

Resets all active AudioSources (default: true).

5.4.2.7 float Crosstales.UI.Util.AudioSourceController.StereoPan = 0f

Stereo pan of the audio (default: 0).

5.4.2.8 float Crosstales.UI.Util.AudioSourceController.Volume = 1f

Volume of the audio (default: 1)

The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/Common/↔ UI/Scripts/Util/AudioSourceController.cs

5.5 Crosstales.RTVoice.EditorTask.AutoInitalize Class Reference

Automatically adds the neccessary RTVoice-prefabs to the current scene.

5.5.1 Detailed Description

Automatically adds the neccessary RTVoice-prefabs to the current scene.


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/RTVoice/↔ Editor/Task/AutoInitalize.cs

5.6 Crosstales.Common.EditorTask.BaseCompileDefines Class Reference

Base for adding the given define symbols to PlayerSettings define symbols.

Inheritance diagram for Crosstales.Common.EditorTask.BaseCompileDefines:



Static Protected Member Functions

- static void **setCompileDefines** (string[] symbols)

5.6.1 Detailed Description

Base for adding the given define symbols to PlayerSettings define symbols.


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/Common/↔ Editor/Task/BaseCompileDefines.cs

5.7 Crosstales.Common.Util.BaseConstants Class Reference

Base for collected constants of very general utility for the asset.

Inheritance diagram for Crosstales.Common.Util.BaseConstants:



Public Attributes

- const string **ASSET_AUTHOR** = "crosstales LLC"
Author of the asset.
- const string **ASSET_AUTHOR_URL** = "https://www.crosstales.com"
URL of the asset author.
- const string **ASSET_CT_URL** = "https://www.assetstore.unity3d.com/#!/list/42213-crosstales?aid=1011IN↔ GT"
URL of the crosstales assets in UAS.
- const string **ASSET_SOCIAL_FACEBOOK** = "https://www.facebook.com/crosstales/"
URL of the crosstales Facebook-profile.
- const string **ASSET_SOCIAL_TWITTER** = "https://twitter.com/crosstales"
URL of the crosstales Twitter-profile.
- const string **ASSET_SOCIAL_YOUTUBE** = "https://www.youtube.com/c/Crosstales"
URL of the crosstales Youtube-profile.
- const string **ASSET_SOCIAL_LINKEDIN** = "https://www.linkedin.com/company/crosstales"
URL of the crosstales LinkedIn-profile.
- const string **ASSET_SOCIAL_XING** = "https://www.xing.com/companies/crosstales"
URL of the crosstales XING-profile.
- const string **ASSET_3P_PLAYMAKER** = "https://www.assetstore.unity3d.com/#!/content/368?aid=1011IN↔ GT"
URL of the 3rd party asset "PlayMaker".
- const int **FACTOR_KB** = 1024

- Factor for kilo bytes.*
 • const int **FACTOR_MB** = **FACTOR_KB** * 1024
- Factor for mega bytes.*
 • const int **FACTOR_GB** = **FACTOR_MB** * 1024
- Factor for giga bytes.*
 • const float **FLOAT_32768** = 32768f
- Float value of 32768.*
 • const string **FORMAT_TWO_DECIMAL_PLACES** = "0.00"
- ToString for two decimal places.*
 • const string **FORMAT_NO_DECIMAL_PLACES** = "0"
- ToString for no decimal places.*
 • const string **FORMAT_PERCENT** = "0%"
- ToString for percent.*
 • const bool **DEFAULT_DEBUG** = false
- const string **PATH_DELIMITER_WINDOWS** = @"\"
- Path delimiter for Windows.*
 • const string **PATH_DELIMITER_UNIX** = "/"
- Path delimiter for Unix.*

Static Public Attributes

- static bool **DEV_DEBUG** = false
Development debug logging for the asset.
- static string **TEXT_TOSTRING_END** = "}"
- static string **TEXT_TOSTRING_DELIMITER** = ", "
- static string **TEXT_TOSTRING_DELIMITER_END** = ""
- static string **TEXT_TOSTRING_START** = "{"
- static string **PREFIX_HTTP** = "http://"
- static string **PREFIX_HTTPS** = "https://"

Properties

- static string **PREFIX_FILE** [get]

5.7.1 Detailed Description

Base for collected constants of very general utility for the asset.

5.7.2 Member Data Documentation

- 5.7.2.1 const string Crosstales.Common.Util.BaseConstants.ASSET_3P_PLAYMAKER = "https://www.assetstore.unity3d.com/#!/content/368?aid=1011INGT"↔

URL of the 3rd party asset "PlayMaker".

5.7.2.2 `const string Crosstales.Common.Util.BaseConstants.ASSET_AUTHOR = "crosstales LLC"`

Author of the asset.

5.7.2.3 `const string Crosstales.Common.Util.BaseConstants.ASSET_AUTHOR_URL = "https://www.crosstales.com"`

URL of the asset author.

5.7.2.4 `const string Crosstales.Common.Util.BaseConstants.ASSET_CT_URL = "https://www.assetstore.unity3d.com/#!/list/42213-crosstales?aid=1011INGT"`

URL of the crosstales assets in UAS.

5.7.2.5 `const string Crosstales.Common.Util.BaseConstants.ASSET_SOCIAL_FACEBOOK = "https://www.facebook.com/crosstales/"`

URL of the crosstales Facebook-profile.

5.7.2.6 `const string Crosstales.Common.Util.BaseConstants.ASSET_SOCIAL_LINKEDIN = "https://www.linkedin.com/company/crosstales"`

URL of the crosstales LinkedIn-profile.

5.7.2.7 `const string Crosstales.Common.Util.BaseConstants.ASSET_SOCIAL_TWITTER = "https://twitter.com/crosstales"`

URL of the crosstales Twitter-profile.

5.7.2.8 `const string Crosstales.Common.Util.BaseConstants.ASSET_SOCIAL_XING = "https://www.xing.com/companies/crosstales"`

URL of the crosstales XING-profile.

5.7.2.9 `const string Crosstales.Common.Util.BaseConstants.ASSET_SOCIAL_YOUTUBE = "https://www.youtube.com/c/Crosstales"`

URL of the crosstales Youtube-profile.

5.7.2.10 `bool Crosstales.Common.Util.BaseConstants.DEV_DEBUG = false` `[static]`

Development debug logging for the asset.

5.7.2.11 `const int Crosstales.Common.Util.BaseConstants.FACTOR_GB = FACTOR_MB * 1024`

Factor for giga bytes.

5.7.2.12 `const int Crosstales.Common.Util.BaseConstants.FACTOR_KB = 1024`

Factor for kilo bytes.

5.7.2.13 `const int Crosstales.Common.Util.BaseConstants.FACTOR_MB = FACTOR_KB * 1024`

Factor for mega bytes.

5.7.2.14 `const float Crosstales.Common.Util.BaseConstants.FLOAT_32768 = 32768f`

Float value of 32768.

5.7.2.15 `const string Crosstales.Common.Util.BaseConstants.FORMAT_NO_DECIMAL_PLACES = "0"`

ToString for no decimal places.

5.7.2.16 `const string Crosstales.Common.Util.BaseConstants.FORMAT_PERCENT = "0%"`

ToString for percent.

5.7.2.17 `const string Crosstales.Common.Util.BaseConstants.FORMAT_TWO_DECIMAL_PLACES = "0.00"`

ToString for two decimal places.

5.7.2.18 `const string Crosstales.Common.Util.BaseConstants.PATH_DELIMITER_UNIX = "/"`

Path delimiter for Unix.

5.7.2.19 `const string Crosstales.Common.Util.BaseConstants.PATH_DELIMITER_WINDOWS = @"\"`

Path delimiter for Windows.


The documentation for this class was generated from the following file:

- `D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/Common/Scripts/Util/BaseConstants.cs`

5.8 Crosstales.Common.EditorUtil.BaseGAApi Class Reference

Base GA-wrapper API.

Inheritance diagram for Crosstales.Common.EditorUtil.BaseGAApi:



Static Public Member Functions

- static void [Event](#) (string name, string version, string category, string action, string label="", int value=0)
Tracks an event from the asset.

5.8.1 Detailed Description

Base GA-wrapper API.

5.8.2 Member Function Documentation

5.8.2.1 static void Crosstales.Common.EditorUtil.BaseGAApi.Event (string name, string version, string category, string action, string label = " ", int value = 0) [static]

Tracks an event from the asset.

Parameters

<i>category</i>	Specifies the event category.
<i>action</i>	Specifies the event action.
<i>label</i>	Specifies the event label.
<i>value</i>	Specifies the event value.


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/Common/↔ Editor/Util/BaseGAApi.cs

5.9 Crosstales.Common.Util.BaseHelper Class Reference

Base for various helper functions.

Inheritance diagram for Crosstales.Common.Util.BaseHelper:



Static Public Member Functions

- static bool [RemoteCertificateValidationCallback](#) (System.Object sender, System.Security.Cryptography.X509Certificates.X509Certificate certificate, System.Security.Cryptography.X509Certificates.X509Chain chain, System.Net.Security.SslPolicyErrors sslPolicyErrors)
HTTPS-certification callback.
- static string [ValidatePath](#) (string path, bool addEndDelimiter=true)
Validates a given path and add missing slash.
- static string [ValidateFile](#) (string path)
Validates a given file.
- static string [ValidURLFromFilePath](#) (string path)
Validates a given file.
- static string [CleanUrl](#) (string url, bool removeProtocol=true, bool removeWWW=true, bool removeSlash=true)
Cleans a given URL.

Parameters

url	URL to clean
removeProtocol	Remove the protocol, e.g. http:// (default: true, optional).
removeWWW	Remove www (default: true, optional).
removeSlash	Remove slash at the end (default: true, optional)

Returns

Clean URL

- static string [ClearTags](#) (string text)
Cleans a given text from tags.
- static string [ClearSpaces](#) (string text)
Cleans a given text from multiple spaces.
- static string [ClearLineEndings](#) (string text)
Cleans a given text from line endings.
- static System.Collections.Generic.List< string > [SplitStringToLines](#) (string text, bool ignoreCommented↵ Lines=true, int skipHeaderLines=0, int skipFooterLines=0)
Split the given text to lines and return it as list.
- static string [FormatBytesToHRF](#) (long bytes)
Format byte-value to Human-Readable-Form.
- static string [FormatSecondsToHourMinSec](#) (double seconds)
Format seconds to Human-Readable-Form.
- static Color [HSVToRGB](#) (float h, float s, float v, float a=1f)
Generate nice HSV colors. Based on <https://gist.github.com/rje/6206099>
- static bool [IsValidURL](#) (string url)
Checks if the URL is valid.

Properties

- static bool [IsInternetAvailable](#) [get]

- Checks if an Internet connection is available.*

 - static bool `isWindowsPlatform` [get]

Checks if the current platform is Windows.
- static bool `isMacOSPlatform` [get]

Checks if the current platform is OSX.
- static bool `isLinuxPlatform` [get]

Checks if the current platform is Linux.
- static bool `isStandalonePlatform` [get]

Checks if the current platform is standalone (Windows, macOS or Linux).
- static bool `isAndroidPlatform` [get]

Checks if the current platform is Android.
- static bool `isIOSPlatform` [get]

Checks if the current platform is iOS.
- static bool `isWSAPlatform` [get]

Checks if the current platform is WSA.
- static bool `isWebGLPlatform` [get]

Checks if the current platform is WebGL.
- static bool `isWebPlayerPlatform` [get]

Checks if the current platform is WebPlayer.
- static bool `isWebPlatform` [get]

Checks if the current platform is Web (WebPlayer or WebGL).
- static bool `isWindowsBasedPlatform` [get]

Checks if the current platform is Windows-based (Windows standalone or WSA).
- static bool `isAppleBasedPlatform` [get]

Checks if the current platform is Apple-based (macOS standalone or iOS).
- static bool `isEditor` [get]

Checks if we are inside the Editor.
- static bool `isEditorMode` [get]

Checks if we are in Editor mode.

5.9.1 Detailed Description

Base for various helper functions.

5.9.2 Member Function Documentation

5.9.2.1 static string Crosstales.Common.Util.BaseHelper.ClearLineEndings (string text) [static]

Cleans a given text from line endings.

Parameters

<i>text</i>	Text to clean.
-------------	----------------

Returns

Clean text without line endings.

5.9.2.2 static string Crosstales.Common.Util.BaseHelper.ClearSpaces (string *text*) [static]

Cleans a given text from multiple spaces.

Parameters

<i>text</i>	Text to clean.
-------------	----------------

Returns

Clean text without multiple spaces.

5.9.2.3 static string Crosstales.Common.Util.BaseHelper.ClearTags (string *text*) [static]

Cleans a given text from tags.

Parameters

<i>text</i>	Text to clean.
-------------	----------------

Returns

Clean text without tags.

5.9.2.4 static string Crosstales.Common.Util.BaseHelper.FormatBytesToHRF (long *bytes*) [static]

Format byte-value to Human-Readable-Form.

Returns

Formatted byte-value in Human-Readable-Form.

5.9.2.5 static string Crosstales.Common.Util.BaseHelper.FormatSecondsToHourMinSec (double *seconds*) [static]

Format seconds to Human-Readable-Form.

Returns

Formatted seconds in Human-Readable-Form.

5.9.2.6 static Color Crosstales.Common.Util.BaseHelper.HSVToRGB (float *h*, float *s*, float *v*, float *a* = 1f) [static]

Generate nice HSV colors. Based on <https://gist.github.com/rje/6206099>

Parameters

<i>h</i>	Hue
<i>s</i>	Saturation
<i>v</i>	Value
<i>a</i>	Alpha (optional)

Returns

True if the current platform is supported.

5.9.2.7 static bool Crosstales.Common.Util.BaseHelper.IsValidURL (string url) [static]

Checks if the URL is valid.

Parameters

<i>url</i>	URL to check
------------	--------------

Returns

True if the URL is valid.

5.9.2.8 static bool Crosstales.Common.Util.BaseHelper.RemoteCertificateValidationCallback (System.Object sender, System.Security.Cryptography.X509Certificates.X509Certificate certificate, System.Security.Cryptology.X509Certificates.X509Chain chain, System.Net.Security.SslPolicyErrors sslPolicyErrors) [static]

HTTPS-certification callback.

5.9.2.9 static System.Collections.Generic.List<string> Crosstales.Common.Util.BaseHelper.SplitStringToLines (string text, bool ignoreCommentedLines = true, int skipHeaderLines = 0, int skipFooterLines = 0) [static]

Split the given text to lines and return it as list.

Parameters

<i>text</i>	Complete text fragment
<i>ignoreCommentedLines</i>	Ignore commente lines (default: true, optional)
<i>skipHeaderLines</i>	Number of skipped header lines (default: 0, optional)
<i>skipFooterLines</i>	Number of skipped footer lines (default: 0, optional)

Returns

Splitted lines as array

5.9.2.10 static string Crosstales.Common.Util.BaseHelper.ValidateFile (string *path*) [static]

Validates a given file.

Parameters

<i>path</i>	File to validate
-------------	------------------

Returns

Valid file path

5.9.2.11 static string Crosstales.Common.Util.BaseHelper.ValidatePath (string *path*, bool *addEndDelimiter* = true) [static]

Validates a given path and add missing slash.

Parameters

<i>path</i>	Path to validate
<i>addEndDelimiter</i>	Add delimiter at the end of the path (optional, default: true)

Returns

Valid path

5.9.2.12 static string Crosstales.Common.Util.BaseHelper.ValidURLFromFilePath (string *path*) [static]

Validates a given file.

Parameters

<i>path</i>	File to validate
-------------	------------------

Returns

Valid file path

5.9.3 Property Documentation**5.9.3.1** bool Crosstales.Common.Util.BaseHelper.isAndroidPlatform [static], [get]

Checks if the current platform is Android.

Returns

True if the current platform is Android.

5.9.3.2 bool Crosstales.Common.Util.BaseHelper.isAppleBasedPlatform [static], [get]

Checks if the current platform is Apple-based (macOS standalone or iOS).

Returns

True if the current platform is Apple-based (macOS standalone or iOS).

5.9.3.3 bool Crosstales.Common.Util.BaseHelper.isEditor [static], [get]

Checks if we are inside the Editor.

Returns

True if we are inside the Editor.

5.9.3.4 bool Crosstales.Common.Util.BaseHelper.isEditorMode [static], [get]

Checks if we are in Editor mode.

Returns

True if in Editor mode.

5.9.3.5 bool Crosstales.Common.Util.BaseHelper.isInternetAvailable [static], [get]

Checks if an Internet connection is available.

Returns

True if an Internet connection is available.

5.9.3.6 bool Crosstales.Common.Util.BaseHelper.isiOSPlatform [static], [get]

Checks if the current platform is iOS.

Returns

True if the current platform is iOS.

5.9.3.7 bool Crosstales.Common.Util.BaseHelper.isLinuxPlatform [static], [get]

Checks if the current platform is Linux.

Returns

True if the current platform is Linux.

5.9.3.8 bool Crosstales.Common.Util.BaseHelper.isMacOSPlatform [static], [get]

Checks if the current platform is OSX.

Returns

True if the current platform is OSX.

5.9.3.9 bool Crosstales.Common.Util.BaseHelper.isStandalonePlatform [static], [get]

Checks if the current platform is standalone (Windows, macOS or Linux).

Returns

True if the current platform is standalone (Windows, macOS or Linux).

5.9.3.10 bool Crosstales.Common.Util.BaseHelper.isWebGLPlatform [static], [get]

Checks if the current platform is WebGL.

Returns

True if the current platform is WebGL.

5.9.3.11 bool Crosstales.Common.Util.BaseHelper.isWebPlatform [static], [get]

Checks if the current platform is Web (WebPlayer or WebGL).

Returns

True if the current platform is Web (WebPlayer or WebGL).

5.9.3.12 bool Crosstales.Common.Util.BaseHelper.isWebPlayerPlatform [static], [get]

Checks if the current platform is WebPlayer.

Returns

True if the current platform is WebPlayer.

5.9.3.13 bool Crosstales.Common.Util.BaseHelper.isWindowsBasedPlatform [static], [get]

Checks if the current platform is Windows-based (Windows standalone or WSA).

Returns

True if the current platform is Windows-based (Windows standalone or WSA).

5.9.3.14 bool Crosstales.Common.Util.BaseHelper.isWindowsPlatform [static], [get]

Checks if the current platform is Windows.

Returns

True if the current platform is Windows.

5.9.3.15 bool Crosstales.Common.Util.BaseHelper.isWSAPlatform [static], [get]

Checks if the current platform is WSA.

Returns

True if the current platform is WSA.


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/Common/↔ Scripts/Util/BaseHelper.cs

5.10 Crosstales.Common.EditorTask.BaseSetupResources Class Reference

Base for copying all resources to 'Editor Default Resources'.

Inheritance diagram for Crosstales.Common.EditorTask.BaseSetupResources:



Static Protected Member Functions

- static void **setupResources** (string source, string sourceFolder, string target, string targetFolder, string metafile)

5.10.1 Detailed Description

Base for copying all resources to 'Editor Default Resources'.


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/Common/↔ Editor/Task/BaseSetupResources.cs

5.11 Crosstales.RTVoice.Provider.BaseVoiceProvider Class Reference

Base class for voice providers.

Inheritance diagram for Crosstales.RTVoice.Provider.BaseVoiceProvider:



Public Member Functions

- **BaseVoiceProvider** (MonoBehaviour obj)
Constructor for a VoiceProvider.
- delegate void **VoicesReady** ()
- delegate void **SpeakStart** (Model.Wrapper wrapper)
- delegate void **SpeakComplete** (Model.Wrapper wrapper)
- delegate void **SpeakCurrentWord** (Model.Wrapper wrapper, string[] speechTextArray, int wordIndex)
- delegate void **SpeakCurrentPhoneme** (Model.Wrapper wrapper, string phoneme)
- delegate void **SpeakCurrentViseme** (Model.Wrapper wrapper, string viseme)
- delegate void **SpeakAudioGenerationStart** (Model.Wrapper wrapper)
- delegate void **SpeakAudioGenerationComplete** (Model.Wrapper wrapper)
- delegate void **ErrorInfo** (Model.Wrapper wrapper, string info)
- virtual void **Silence** ()
Silence all active TTS-providers.
- virtual void **Silence** (string uid)
Silence the current TTS-provider (native mode).
- abstract IEnumerator **SpeakNative** (Model.Wrapper wrapper)
The current provider speaks a text with a given voice (native mode).
- abstract IEnumerator **Speak** (Model.Wrapper wrapper)
The current provider speaks a text with a given voice.
- abstract IEnumerator **Generate** (Model.Wrapper wrapper)
The current provider generates an audio file from a text with a given voice.

Static Protected Member Functions

- static void **fileCopy** (string inputFile, string outputFile, bool move=false)
- static void **onVoicesReady** ()
- static void **onSpeakStart** (Model.Wrapper wrapper)
- static void **onSpeakComplete** (Model.Wrapper wrapper)
- static void **onSpeakCurrentWord** (Model.Wrapper wrapper, string[] speechTextArray, int wordIndex)
- static void **onSpeakCurrentPhoneme** (Model.Wrapper wrapper, string phoneme)
- static void **onSpeakCurrentViseme** (Model.Wrapper wrapper, string viseme)
- static void **onSpeakAudioGenerationStart** (Model.Wrapper wrapper)
- static void **onSpeakAudioGenerationComplete** (Model.Wrapper wrapper)
- static void **onErrorInfo** (Model.Wrapper wrapper, string info)

Protected Attributes

- System.Collections.Generic.Dictionary< string, System.Diagnostics.Process > **processes** = new System.Collections.Generic.Dictionary<string, System.Diagnostics.Process>()
- bool **silence** = false
- MonoBehaviour **speakerObj**

Static Protected Attributes

- static char[] **splitCharWords** = new char[] { ' ' }

Properties

- abstract string [AudioFileExtension](#) [get]
Returns the extension of the generated audio files.
- abstract System.Collections.Generic.List< [Model.Voice](#) > [Voices](#) [get]
Get all available voices from the current TTS-provider and fills it into a given list.
- static VoicesReady [OnVoicesReady](#)
An event triggered whenever the voices of a provider are ready.
- static SpeakStart [OnSpeakStart](#)
An event triggered whenever a speak is started.
- static SpeakComplete [OnSpeakComplete](#)
An event triggered whenever a speak is completed.
- static SpeakCurrentWord [OnSpeakCurrentWord](#)
An event triggered whenever a new word is spoken (native, Windows and iOS only).
- static SpeakCurrentPhoneme [OnSpeakCurrentPhoneme](#)
An event triggered whenever a new phoneme is spoken (native mode, Windows only).
- static SpeakCurrentViseme [OnSpeakCurrentViseme](#)
An event triggered whenever a new viseme is spoken (native mode, Windows only).
- static SpeakAudioGenerationStart [OnSpeakAudioGenerationStart](#)
An event triggered whenever a speak audio generation is started.
- static SpeakAudioGenerationComplete [OnSpeakAudioGenerationComplete](#)
An event triggered whenever a speak audio generation is completed.
- static ErrorInfo [OnErrorInfo](#)
An event triggered whenever an error occurs.

5.11.1 Detailed Description

Base class for voice providers.

5.11.2 Constructor & Destructor Documentation

5.11.2.1 Crosstales.RTVoice.Provider.BaseVoiceProvider.BaseVoiceProvider (MonoBehaviour *obj*)

Constructor for a VoiceProvider.

Parameters

<i>obj</i>	Instance of the speaker
------------	-------------------------

5.11.3 Member Function Documentation

5.11.3.1 **abstract IEnumerator** **Crosstales.RTVoice.Provider.BaseVoiceProvider.Generate** (**Model.Wrapper** *wrapper*)
[pure virtual]

The current provider generates an audio file from a text with a given voice.

Parameters

<i>wrapper</i>	Wrapper containing the data.
----------------	------------------------------

Implemented in [Crosstales.RTVoice.Provider.VoiceProviderWindows](#), [Crosstales.RTVoice.Provider.VoiceProviderMacOS](#), [Crosstales.RTVoice.Provider.VoiceProviderAndroid](#), [Crosstales.RTVoice.Provider.VoiceProviderIOS](#), [Crosstales.RTVoice.Provider.VoiceProviderMary](#), and [Crosstales.RTVoice.Provider.VoiceProviderWSA](#).

5.11.3.2 **virtual void** **Crosstales.RTVoice.Provider.BaseVoiceProvider.Silence** () [virtual]

Silence all active TTS-providers.

Reimplemented in [Crosstales.RTVoice.Provider.VoiceProviderAndroid](#), [Crosstales.RTVoice.Provider.VoiceProviderIOS](#), [Crosstales.RTVoice.Provider.VoiceProviderMary](#), and [Crosstales.RTVoice.Provider.VoiceProviderWSA](#).

5.11.3.3 **virtual void** **Crosstales.RTVoice.Provider.BaseVoiceProvider.Silence** (**string** *uid*) [virtual]

Silence the current TTS-provider (native mode).

Parameters

<i>uid</i>	UID of the speaker
------------	--------------------

5.11.3.4 **abstract IEnumerator** **Crosstales.RTVoice.Provider.BaseVoiceProvider.Speak** (**Model.Wrapper** *wrapper*) [pure virtual]

The current provider speaks a text with a given voice.

Parameters

<i>wrapper</i>	Wrapper containing the data.
----------------	------------------------------

Implemented in [Crosstales.RTVoice.Provider.VoiceProviderIOS](#), [Crosstales.RTVoice.Provider.VoiceProviderWindows](#), [Crosstales.RTVoice.Provider.VoiceProviderMacOS](#), [Crosstales.RTVoice.Provider.VoiceProviderAndroid](#), [Crosstales.RTVoice.Provider.VoiceProviderMary](#), and [Crosstales.RTVoice.Provider.VoiceProviderWSA](#).

5.11.3.5 **abstract IEnumerator** **Crosstales.RTVoice.Provider.BaseVoiceProvider.SpeakNative** (**Model.Wrapper** *wrapper*)
[pure virtual]

The current provider speaks a text with a given voice (native mode).

Parameters

<i>wrapper</i>	Wrapper containing the data.
----------------	------------------------------

Implemented in [Crosstales.RTVoice.Provider.VoiceProviderIOS](#), [Crosstales.RTVoice.Provider.VoiceProvider↳ Mary](#), [Crosstales.RTVoice.Provider.VoiceProviderWindows](#), [Crosstales.RTVoice.Provider.VoiceProviderWSA](#), [Crosstales.RTVoice.Provider.VoiceProviderAndroid](#), and [Crosstales.RTVoice.Provider.VoiceProviderMacOS](#).

5.11.4 Property Documentation

5.11.4.1 abstract string Crosstales.RTVoice.Provider.BaseVoiceProvider.AudioFileExtension [get]

Returns the extension of the generated audio files.

Returns

Extension of the generated audio files.

5.11.4.2 ErrorInfo Crosstales.RTVoice.Provider.BaseVoiceProvider.OnErrorInfo [static], [add], [remove]

An event triggered whenever an error occurs.

5.11.4.3 SpeakAudioGenerationComplete Crosstales.RTVoice.Provider.BaseVoiceProvider.OnSpeakAudioGenerationComplete [static], [add], [remove]

An event triggered whenever a speak audio generation is completed.

5.11.4.4 SpeakAudioGenerationStart Crosstales.RTVoice.Provider.BaseVoiceProvider.OnSpeakAudioGenerationStart [static], [add], [remove]

An event triggered whenever a speak audio generation is started.

5.11.4.5 SpeakComplete Crosstales.RTVoice.Provider.BaseVoiceProvider.OnSpeakComplete [static], [add], [remove]

An event triggered whenever a speak is completed.

5.11.4.6 SpeakCurrentPhoneme Crosstales.RTVoice.Provider.BaseVoiceProvider.OnSpeakCurrentPhoneme [static], [add], [remove]

An event triggered whenever a new phoneme is spoken (native mode, Windows only).

5.11.4.7 SpeakCurrentViseme `Crosstales.RTVoice.Provider.BaseVoiceProvider.OnSpeakCurrentViseme` `[static]`, `[add]`, `[remove]`

An event triggered whenever a new viseme is spoken (native mode, Windows only).

5.11.4.8 SpeakCurrentWord `Crosstales.RTVoice.Provider.BaseVoiceProvider.OnSpeakCurrentWord` `[static]`, `[add]`, `[remove]`

An event triggered whenever a new word is spoken (native, Windows and iOS only).

5.11.4.9 SpeakStart `Crosstales.RTVoice.Provider.BaseVoiceProvider.OnSpeakStart` `[static]`, `[add]`, `[remove]`

An event triggered whenever a speak is started.

5.11.4.10 VoicesReady `Crosstales.RTVoice.Provider.BaseVoiceProvider.OnVoicesReady` `[static]`, `[add]`, `[remove]`

An event triggered whenever the voices of a provider are ready.

5.11.4.11 abstract System.Collections.Generic.List<Model.Voice> `Crosstales.RTVoice.Provider.BaseVoiceProvider.Voices` `[get]`

Get all available voices from the current TTS-provider and fills it into a given list.

Returns

All available voices from the current TTS-provider as list.


The documentation for this class was generated from the following file:

- `D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/RTVoice/Scripts/Provider/BaseVoiceProvider.cs`

5.12 Crosstales.RTVoice.SALSA.Bots Class Reference

This is class for conversations between two SALSA-Bots.

Inheritance diagram for `Crosstales.RTVoice.SALSA.Bots`:



Public Member Functions

- void **OnEnable** ()
- void **OnDestroy** ()
- void **Update** ()

Public Attributes

- AudioSource **SourceA**
- AudioSource **SourceB**
- string[] **ConversationsA**
- string[] **ConversationsB**

5.12.1 Detailed Description

This is class for conversations between two SALSA-Bots.

The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/RTVoice/3rd party/SALSA/Scripts/Bots.cs

5.13 Crosstales.RTVoice.EditorUtil.BuildPostprocessor Class Reference

[BuildPostprocessor](#) for Windows. Adds the TTS-wrapper to the build.

Static Public Member Functions

- static void **OnPostprocessBuild** (BuildTarget target, string pathToBuiltProject)

5.13.1 Detailed Description

[BuildPostprocessor](#) for Windows. Adds the TTS-wrapper to the build.


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/RTVoice/Editor/Util/BuildPostprocessor.cs

5.14 Crosstales.RTVoice.EditorTask.CompileDefines Class Reference

Adds the given define symbols to PlayerSettings define symbols.

Inheritance diagram for Crosstales.RTVoice.EditorTask.CompileDefines:



Additional Inherited Members

5.14.1 Detailed Description

Adds the given define symbols to PlayerSettings define symbols.

The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/RTVoice/↵
Editor/Task/CompileDefines.cs

5.15 Crosstales.RTVoice.Util.Config Class Reference

Configuration for the asset.

Static Public Member Functions

- static void [Reset](#) ()
Resets all changable variables to their default value.
- static void [Load](#) ()
Loads all changable variables.
- static void [Save](#) ()
Saves all changable variables.

Static Public Attributes

- static string [ASSET_PATH](#) = "/crosstales/RTVoice/"
Path to the asset inside the Unity project.
- static bool [DEBUG](#) = Constants.DEFAULT_DEBUG
Enable or disable debug logging for the asset.
- static string [AUDIOFILE_PATH](#) = Constants.DEFAULT_AUDIOFILE_PATH
Don't destroy the objects during scene switches.
- static bool [AUDIOFILE_AUTOMATIC_DELETE](#) = Constants.DEFAULT_AUDIOFILE_AUTOMATIC_DELETE
Automatically delete the generated audio files.
- static bool [ENFORCE_32BIT_WINDOWS](#) = Constants.DEFAULT_ENFORCE_32BIT_WINDOWS
Enforce 32bit versions of voices under Windows.
- static string [TTS_WINDOWS_BUILD](#) = Constants.DEFAULT_TTS_WINDOWS_BUILD
Location of the TTS-wrapper under Windows (stand-alone).
- static string [TTS_MACOS](#) = Constants.DEFAULT_TTS_MACOS
Location of the TTS-system under MacOS.
- static bool [isLoading](#) = false
Is the configuration loaded?

Properties

- static string [TTS_WINDOWS_EDITOR](#) [get]
Location of the TTS-wrapper under Windows (Editor).
- static string [TTS_WINDOWS_EDITOR_x86](#) [get]
Location of the TTS-wrapper (32bit) under Windows (Editor).

5.15.1 Detailed Description

Configuration for the asset.

5.15.2 Member Function Documentation

5.15.2.1 static void Crosstales.RTVoice.Util.Config.Load () [static]

Loads all changable variables.

5.15.2.2 static void Crosstales.RTVoice.Util.Config.Reset () [static]

Resets all changable variables to their default value.

5.15.2.3 static void Crosstales.RTVoice.Util.Config.Save () [static]

Saves all changable variables.

5.15.3 Member Data Documentation

5.15.3.1 string Crosstales.RTVoice.Util.Config.ASSET_PATH = "/crosstales/RTVoice/" [static]

Path to the asset inside the Unity project.

5.15.3.2 bool Crosstales.RTVoice.Util.Config.AUDIOFILE_AUTOMATIC_DELETE = Constants.DEFAULT_AUDIOFILE_AUTOMATIC_DELETE [static]

Automatically delete the generated audio files.

5.15.3.3 string Crosstales.RTVoice.Util.Config.AUDIOFILE_PATH = Constants.DEFAULT_AUDIOFILE_PATH [static]

Don't destroy the objects during scene switches.

Path to the generated audio files.

5.15.3.4 `bool Crosstales.RTVoice.Util.Config.DEBUG = Constants.DEFAULT_DEBUG` `[static]`

Enable or disable debug logging for the asset.

5.15.3.5 `bool Crosstales.RTVoice.Util.Config.ENFORCE_32BIT_WINDOWS = Constants.DEFAULT_ENFORCE_32BIT_WINDOWS`
`[static]`

Enforce 32bit versions of voices under Windows.

5.15.3.6 `bool Crosstales.RTVoice.Util.Config.isLoaded = false` `[static]`

Is the configuration loaded?

5.15.3.7 `string Crosstales.RTVoice.Util.Config.TTS_MACOS = Constants.DEFAULT_TTS_MACOS` `[static]`

Location of the TTS-system under MacOS.

5.15.3.8 `string Crosstales.RTVoice.Util.Config.TTS_WINDOWS_BUILD = Constants.DEFAULT_TTS_WINDOWS_BUILD`
`[static]`

Location of the TTS-wrapper under Windows (stand-alone).

5.15.4 Property Documentation

5.15.4.1 `string Crosstales.RTVoice.Util.Config.TTS_WINDOWS_EDITOR` `[static], [get]`

Location of the TTS-wrapper under Windows (Editor).

5.15.4.2 `string Crosstales.RTVoice.Util.Config.TTS_WINDOWS_EDITOR_x86` `[static], [get]`

Location of the TTS-wrapper (32bit) under Windows (Editor).


The documentation for this class was generated from the following file:

- `D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/RTVoice/Scripts/Util/Config.cs`

5.16 Crosstales.RTVoice.EditorIntegration.ConfigBase Class Reference

Base class for editor windows.

Inheritance diagram for Crosstales.RTVoice.EditorIntegration.ConfigBase:



Protected Member Functions

- void **showConfiguration** ()
- void **showHelp** ()
- void **showAbout** ()

Static Protected Member Functions

- static void **save** ()

5.16.1 Detailed Description

Base class for editor windows.

The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/RTVoice/↔ Editor/Integration/ConfigBase.cs

5.17 Crosstales.RTVoice.EditorTask.ConfigLoader Class Reference

Loads the configuration at startup.

5.17.1 Detailed Description

Loads the configuration at startup.


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/RTVoice/↔ Editor/Task/ConfigLoader.cs

5.18 Crosstales.RTVoice.EditorIntegration.ConfigPreferences Class Reference

Unity "Preferences" extension.

Inheritance diagram for Crosstales.RTVoice.EditorIntegration.ConfigPreferences:



Additional Inherited Members

5.18.1 Detailed Description

Unity "Preferences" extension.


The documentation for this class was generated from the following file:

- `D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/RTVoice/Editor/Integration/ConfigPreferences.cs`

5.19 Crosstales.RTVoice.EditorIntegration.ConfigWindow Class Reference

Editor window extension.

Inheritance diagram for Crosstales.RTVoice.EditorIntegration.ConfigWindow:



Public Member Functions

- delegate void **StopPlayback** ()
- void **OnEnable** ()
- void **OnDisable** ()
- void **OnGUI** ()
- void **OnInspectorUpdate** ()

Static Public Member Functions

- static void **ShowWindow** ()
- static void **ShowWindow** (int tab)

Events

- static StopPlayback **OnStopPlayback**

Additional Inherited Members

5.19.1 Detailed Description

Editor window extension.


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/RTVoice/↵
Editor/Integration/ConfigWindow.cs

5.20 Crosstales.RTVoice.Util.Constants Class Reference

Collected constants of very general utility for the asset.

Inheritance diagram for Crosstales.RTVoice.Util.Constants:



Public Attributes

- const string **ASSET_NAME** = "RTVoice PRO"
Name of the asset.
- const string **ASSET_VERSION** = "2.9.4"
Version of the asset.
- const int **ASSET_BUILD** = 294
Build number of the asset.
- const string **ASSET_PRO_URL** = "https://www.assetstore.unity3d.com/#!/content/41068?aid=10111NG↵
T&pubref=" + ASSET_NAME
URL of the PRO asset in UAS.
- const string **ASSET_3P_URL** = "https://www.assetstore.unity3d.com/#!/list/42209-rt-voice-friends?aid=10111↵
NGT&pubref=" + ASSET_NAME
URL of the 3rd party assets in UAS.

- const string **ASSET_UPDATE_CHECK_URL** = "https://www.crosstales.com/media/assets/rtvoice_versions.txt"
URL for update-checks of the asset
- const string **ASSET_CONTACT** = "rtvoice@crosstales.com"
Contact to the owner of the asset.
- const string **ASSET_MANUAL_URL** = "https://www.crosstales.com/media/data/assets/rtvoice/RTVoice-doc.pdf"
URL of the asset manual.
- const string **ASSET_API_URL** = "http://goo.gl/6w4Fy0"
URL of the asset API.
- const string **ASSET_FORUM_URL** = "http://goo.gl/Z6MZMI"
URL of the asset forum.
- const string **ASSET_WEB_URL** = "https://www.crosstales.com/en/portfolio/rtvoice/"
URL of the asset in crosstales.
- const string **ASSET_VIDEO_PROMO** = "https://youtu.be/iVhTWDLY7g8?list=PLgtonlOr6Tb41XTMeeZ836tjHIKgOO84S"
URL of the promotion video of the asset (Youtube).
- const string **ASSET_VIDEO_TUTORIAL** = "https://youtu.be/OJyVgCmX3wU?list=PLgtonlOr6Tb41XTMeeZ836tjHIKgOO84S"
URL of the tutorial video of the asset (Youtube).
- const string **ASSET_3P_ADVENTURE_CREATOR** = "https://www.assetstore.unity3d.com/#!/content/11896?aid=1011NGT&pubref=" + ASSET_NAME
URL of the 3rd party asset "Adventure Creator".
- const string **ASSET_3P_CINEMA_DIRECTOR** = "https://www.assetstore.unity3d.com/#!/content/19779?aid=1011NGT&pubref=" + ASSET_NAME
URL of the 3rd party asset "Cinema Director".
- const string **ASSET_3P_DIALOG_SYSTEM** = "https://www.assetstore.unity3d.com/#!/content/11672?aid=1011NGT&pubref=" + ASSET_NAME
URL of the 3rd party asset "Dialogue System".
- const string **ASSET_3P_LOCALIZED_DIALOGS** = "https://www.assetstore.unity3d.com/#!/content/5020?aid=1011NGT&pubref=" + ASSET_NAME
URL of the 3rd party asset "Localized Dialogs".
- const string **ASSET_3P_LIPSYNC** = "https://www.assetstore.unity3d.com/#!/content/32117?aid=1011NGT&pubref=" + ASSET_NAME
URL of the 3rd party asset "LipSync Pro".
- const string **ASSET_3P_NPC_CHAT** = "https://www.assetstore.unity3d.com/#!/content/9723?aid=1011NGT&pubref=" + ASSET_NAME
URL of the 3rd party asset "NPC Chat".
- const string **ASSET_3P_QUEST_SYSTEM** = "https://www.assetstore.unity3d.com/#!/content/63460?aid=1011NGT&pubref=" + ASSET_NAME
URL of the 3rd party asset "Quest System Pro".
- const string **ASSET_3P_SALSA** = "https://www.assetstore.unity3d.com/#!/content/16944?aid=1011NGT&pubref=" + ASSET_NAME
URL of the 3rd party asset "SALSA".
- const string **ASSET_3P_SLATE** = "https://www.assetstore.unity3d.com/#!/content/56558?aid=1011NGT&pubref=" + ASSET_NAME
URL of the 3rd party asset "SLATE".
- const string **ASSET_3P_DIALOGUE_ENGINE** = "https://www.assetstore.unity3d.com/#!/content/42467?aid=1011NGT&pubref=" + ASSET_NAME
URL of the 3rd party asset "THE Dialogue Engine".
- const string **ASSET_3P_USEQUENCER** = "https://www.assetstore.unity3d.com/#!/content/3666?aid=1011NGT&pubref=" + ASSET_NAME
URL of the 3rd party asset "uSequencer".

- const string **KEY_PREFIX** = "RTVOICE_CFG_"
- const string **KEY_ASSET_PATH** = KEY_PREFIX + "ASSET_PATH"
- const string **KEY_DEBUG** = KEY_PREFIX + "DEBUG"
- const string **KEY_AUDIOFILE_PATH** = KEY_PREFIX + "AUDIOFILE_PATH"
- const string **KEY_AUDIOFILE_AUTOMATIC_DELETE** = KEY_PREFIX + "AUDIOFILE_AUTOMATIC_DELETE"
- const string **KEY_ENFORCE_32BIT_WINDOWS** = KEY_PREFIX + "ENFORCE_32BIT_WINDOWS"
- const bool **DEFAULT_AUDIOFILE_AUTOMATIC_DELETE** = true
- const bool **DEFAULT_ENFORCE_32BIT_WINDOWS** = false
- const string **DEFAULT_TTS_WINDOWS_BUILD** = @"/RTVoiceTTSWrapper.exe"
- const string **DEFAULT_TTS_MACOS** = "say"
- const int **DEFAULT_TTS_KILL_TIME** = 7000
- const string **RTVOICE_SCENE_OBJECT_NAME** = "RTVoice"

RTVoice prefab scene name.

Static Public Attributes

- static readonly bool **isPro** = true
Is PRO-version?
- static readonly System.DateTime **ASSET_CREATED** = new System.DateTime(2015, 4, 29)
Create date of the asset (YYYY, MM, DD).
- static readonly System.DateTime **ASSET_CHANGED** = new System.DateTime(2017, 1, 8)
Change date of the asset (YYYY, MM, DD).
- static readonly string **DEFAULT_AUDIOFILE_PATH** = Application.temporaryCachePath
- static string **TTS_WINDOWS_SUBPATH** = "Wrapper/Windows/RTVoiceTTSWrapper.exe"
Sub-path to the TTS-wrapper under Windows (Editor).
- static string **TTS_WINDOWS_x86_SUBPATH** = "Wrapper/Windows/RTVoiceTTSWrapper_x86.exe"
Sub-path to the TTS-wrapper (32bit) under Windows (Editor).

Additional Inherited Members

5.20.1 Detailed Description

Collected constants of very general utility for the asset.

5.20.2 Member Data Documentation

5.20.2.1 const string Crosstales.RTVoice.Util.Constants.ASSET_3P_ADVENTURE_CREATOR =
"https://www.assetstore.unity3d.com/#!/content/11896?aid=1011INGT&pubref=" + ASSET_NAME

URL of the 3rd party asset "Adventure Creator".

5.20.2.2 const string Crosstales.RTVoice.Util.Constants.ASSET_3P_CINEMA_DIRECTOR =
"https://www.assetstore.unity3d.com/#!/content/19779?aid=1011INGT&pubref=" + ASSET_NAME

URL of the 3rd party asset "Cinema Director".

5.20.2.3 `const string Crosstales.RTVoice.Util.Constants.ASSET_3P_DIALOG_SYSTEM = "https://www.assetstore.unity3d.com/#!/content/11672?aid=1011INGT&pubref=" + ASSET_NAME`

URL of the 3rd party asset "Dialogue System".

5.20.2.4 `const string Crosstales.RTVoice.Util.Constants.ASSET_3P_DIALOGUE_ENGINE = "https://www.assetstore.unity3d.com/#!/content/42467?aid=1011INGT&pubref=" + ASSET_NAME`

URL of the 3rd party asset "THE Dialogue Engine".

5.20.2.5 `const string Crosstales.RTVoice.Util.Constants.ASSET_3P_LIPSYNC = "https://www.assetstore.unity3d.com/#!/content/32117?aid=1011INGT&pubref=" + ASSET_NAME`

URL of the 3rd party asset "LipSync Pro".

5.20.2.6 `const string Crosstales.RTVoice.Util.Constants.ASSET_3P_LOCALIZED_DIALOGS = "https://www.assetstore.unity3d.com/#!/content/5020?aid=1011INGT&pubref=" + ASSET_NAME`

URL of the 3rd party asset "Localized Dialogs".

5.20.2.7 `const string Crosstales.RTVoice.Util.Constants.ASSET_3P_NPC_CHAT = "https://www.assetstore.unity3d.com/#!/content/9723?aid=1011INGT&pubref=" + ASSET_NAME`

URL of the 3rd party asset "NPC Chat".

5.20.2.8 `const string Crosstales.RTVoice.Util.Constants.ASSET_3P_QUEST_SYSTEM = "https://www.assetstore.unity3d.com/#!/content/63460?aid=1011INGT&pubref=" + ASSET_NAME`

URL of the 3rd party asset "Quest System Pro".

5.20.2.9 `const string Crosstales.RTVoice.Util.Constants.ASSET_3P_SALSA = "https://www.assetstore.unity3d.com/#!/content/16944?aid=1011INGT&pubref=" + ASSET_NAME`

URL of the 3rd party asset "SALSA".

5.20.2.10 `const string Crosstales.RTVoice.Util.Constants.ASSET_3P_SLATE = "https://www.assetstore.unity3d.com/#!/content/56558?aid=1011INGT&pubref=" + ASSET_NAME`

URL of the 3rd party asset "SLATE".

5.20.2.11 `const string Crosstales.RTVoice.Util.Constants.ASSET_3P_URL = "https://www.assetstore.unity3d.com/#!/list/42209-rt-voice-friends?aid=1011INGT&pubref=" + ASSET_NAME`

URL of the 3rd party assets in UAS.

5.20.2.12 `const string Crosstales.RTVoice.Util.Constants.ASSET_3P_USEQUENCER = "https://www.assetstore.unity3d.com/#!/content/3666?aid=1011INGT&pubref=" + ASSET_NAME`

URL of the 3rd party asset "uSequencer".

5.20.2.13 `const string Crosstales.RTVoice.Util.Constants.ASSET_API_URL = "http://goo.gl/6w4Fy0"`

URL of the asset API.

5.20.2.14 `const int Crosstales.RTVoice.Util.Constants.ASSET_BUILD = 294`

Build number of the asset.

5.20.2.15 `readonly System.DateTime Crosstales.RTVoice.Util.Constants.ASSET_CHANGED = new System.DateTime(2017, 1, 8)`
`[static]`

Change date of the asset (YYYY, MM, DD).

5.20.2.16 `const string Crosstales.RTVoice.Util.Constants.ASSET_CONTACT = "rtvoice@crosstales.com"`

Contact to the owner of the asset.

5.20.2.17 `readonly System.DateTime Crosstales.RTVoice.Util.Constants.ASSET_CREATED = new System.DateTime(2015, 4, 29)`
`[static]`

Create date of the asset (YYYY, MM, DD).

5.20.2.18 `const string Crosstales.RTVoice.Util.Constants.ASSET_FORUM_URL = "http://goo.gl/Z6MZMI"`

URL of the asset forum.

5.20.2.19 `const string Crosstales.RTVoice.Util.Constants.ASSET_MANUAL_URL = "https://www.crosstales.com/media/data/assets/rtvoice/RTVoice-doc.pdf"`

URL of the asset manual.

5.20.2.20 `const string Crosstales.RTVoice.Util.Constants.ASSET_NAME = "RTVoice PRO"`

Name of the asset.

5.20.2.21 `const string Crosstales.RTVoice.Util.Constants.ASSET_PRO_URL = "https://www.assetstore.unity3d.com/#!/content/41068?aid=1011INGT&pubref=" + ASSET_NAME`

URL of the PRO asset in UAS.

5.20.2.22 `const string Crosstales.RTVoice.Util.Constants.ASSET_UPDATE_CHECK_URL = "https://www.crosstales.com/media/assets/rtvoice_versions.txt"`

URL for update-checks of the asset

5.20.2.23 `const string Crosstales.RTVoice.Util.Constants.ASSET_VERSION = "2.9.4"`

Version of the asset.

5.20.2.24 `const string Crosstales.RTVoice.Util.Constants.ASSET_VIDEO_PROMO = "https://youtu.be/iVhTWDLY7g8?list=PLgtonlOr6Tb41XTMeeZ836tjHIKgOO84S"`

URL of the promotion video of the asset (Youtube).

5.20.2.25 `const string Crosstales.RTVoice.Util.Constants.ASSET_VIDEO_TUTORIAL = "https://youtu.be/OJyVgCmX3wU?list=PLgtonlOr6Tb41XTMeeZ836tjHIKgOO84S"`

URL of the tutorial video of the asset (Youtube).

5.20.2.26 `const string Crosstales.RTVoice.Util.Constants.ASSET_WEB_URL = "https://www.crosstales.com/en/portfolio/rtvoice/"`

URL of the asset in crosstales.

5.20.2.27 `readonly bool Crosstales.RTVoice.Util.Constants.isPro = true` `[static]`

Is PRO-version?

5.20.2.28 `const string Crosstales.RTVoice.Util.Constants.RTVOICE_SCENE_OBJECT_NAME = "RTVoice"`

[RTVoice](#) prefab scene name.

5.20.2.29 `string Crosstales.RTVoice.Util.Constants.TTS_WINDOWS_SUBPATH = "Wrapper/Windows/RTVoiceTTSWrapper.exe"` `[static]`

Sub-path to the TTS-wrapper under Windows (Editor).

5.20.2.30 `string Crosstales.RTVoice.Util.Constants.TTS_WINDOWS_x86_SUBPATH = "Wrapper/Windows/RTVoiceTTS↔
Wrapper_x86.exe" [static]`

Sub-path to the TTS-wrapper (32bit) under Windows (Editor).

The documentation for this class was generated from the following file:

- `D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/RTVoice/↔
Scripts/Util/Constants.cs`

5.21 Crosstales.Common.Util.CTPlayerPrefs Class Reference

Wrapper for the PlayerPrefs.

Static Public Member Functions

- static bool `HasKey` (string key)
Exists the key?
- static void `DeleteAll` ()
Deletes all keys.
- static void `DeleteKey` (string key)
Delete the key.
- static void `Save` ()
Saves all modifications.
- static string `GetString` (string key)
Allows to get a string from a key.
- static float `GetFloat` (string key)
Allows to get a float from a key.
- static int `GetInt` (string key)
Allows to get an int from a key.
- static bool `GetBool` (string key)
Allows to get a bool from a key.
- static void `SetString` (string key, string value)
Allows to set a string for a key.
- static void `SetFloat` (string key, float value)
Allows to set a float for a key.
- static void `SetInt` (string key, int value)
Allows to set an int for a key.
- static void `SetBool` (string key, bool value)
Allows to set a bool for a key.

5.21.1 Detailed Description

Wrapper for the PlayerPrefs.

5.21.2 Member Function Documentation

5.21.2.1 static void Crosstales.Common.Util.CTPlayerPrefs.DeleteAll () [static]

Deletes all keys.

5.21.2.2 static void Crosstales.Common.Util.CTPlayerPrefs.DeleteKey (string *key*) [static]

Delete the key.

Parameters

<i>key</i>	Key to delete in the PlayerPrefs.
------------	-----------------------------------

5.21.2.3 static bool Crosstales.Common.Util.CTPlayerPrefs.GetBool (string *key*) [static]

Allows to get a bool from a key.

Parameters

<i>key</i>	Key for the PlayerPrefs.
------------	--------------------------

Returns

Value for the key.

5.21.2.4 static float Crosstales.Common.Util.CTPlayerPrefs.GetFloat (string *key*) [static]

Allows to get a float from a key.

Parameters

<i>key</i>	Key for the PlayerPrefs.
------------	--------------------------

Returns

Value for the key.

5.21.2.5 static int Crosstales.Common.Util.CTPlayerPrefs.GetInt (string *key*) [static]

Allows to get an int from a key.

Parameters

<i>key</i>	Key for the PlayerPrefs.
------------	--------------------------

Returns

Value for the key.

5.21.2.6 static string Crosstales.Common.Util.CTPlayerPrefs.GetString (string *key*) [static]

Allows to get a string from a key.

Parameters

<i>key</i>	Key for the PlayerPrefs.
------------	--------------------------

Returns

Value for the key.

5.21.2.7 `static bool Crosstales.Common.Util.CTPlayerPrefs.HasKey (string key) [static]`

Exists the key?

Parameters

<i>key</i>	Key for the PlayerPrefs.
------------	--------------------------

Returns

Value for the key.

5.21.2.8 `static void Crosstales.Common.Util.CTPlayerPrefs.Save () [static]`

Saves all modifications.

5.21.2.9 `static void Crosstales.Common.Util.CTPlayerPrefs.SetBool (string key, bool value) [static]`

Allows to set a bool for a key.

Parameters

<i>key</i>	Key for the PlayerPrefs.
<i>value</i>	Value for the PlayerPrefs.

5.21.2.10 `static void Crosstales.Common.Util.CTPlayerPrefs.SetFloat (string key, float value) [static]`

Allows to set a float for a key.

Parameters

<i>key</i>	Key for the PlayerPrefs.
<i>value</i>	Value for the PlayerPrefs.

5.21.2.11 `static void Crosstales.Common.Util.CTPlayerPrefs.SetInt (string key, int value) [static]`

Allows to set an int for a key.

Parameters

<i>key</i>	Key for the PlayerPrefs.
<i>value</i>	Value for the PlayerPrefs.

5.21.2.12 `static void Crosstales.Common.Util.CTPlayerPrefs.SetString (string key, string value) [static]`

Allows to set a string for a key.

Parameters

<i>key</i>	Key for the PlayerPrefs.
<i>value</i>	Value for the PlayerPrefs.


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/Common/Scripts/Util/CTPlayerPrefs.cs

5.22 Crosstales.Common.Util.CTWebClient Class Reference

Specialized WebClient.

Inheritance diagram for Crosstales.Common.Util.CTWebClient:



Public Member Functions

- **CTWebClient** (int timeout, int connectionLimit=20)
- System.Net.WebRequest **CTGetWebRequest** (string uri)

Protected Member Functions

- override System.Net.WebRequest **GetWebRequest** (System.Uri uri)

Properties

- int [Timeout](#) [get, set]
Timeout in milliseconds
- int [ConnectionLimit](#) [get, set]
Connection limit for all WebClients

5.22.1 Detailed Description

Specialized WebClient.

5.22.2 Property Documentation

5.22.2.1 int Crosstales.Common.Util.CTWebClient.ConnectionLimit [get], [set]

Connection limit for all WebClients

5.22.2.2 int Crosstales.Common.Util.CTWebClient.Timeout [get], [set]

Timeout in milliseconds


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/Common/Scripts/Util/CTWebClient.cs

5.23 Crosstales.RTVoice.Demo.Dialog Class Reference

[Simple](#) dialog system with TTS voices.

Inheritance diagram for Crosstales.RTVoice.Demo.Dialog:



Public Member Functions

- void **Start** ()
- IEnumerator **DialogSequence** ()

Public Attributes

- string **CultureA** = "en"
- string **CultureB** = "en"
- float **RateA** = 1f
- float **RateB** = 1f
- float **PitchA** = 1f
- float **PitchB** = 1f
- float **VolumeA** = 1f
- float **VolumeB** = 1f
- AudioSource **AudioPersonA**
- AudioSource **AudioPersonB**
- string[] **DialogPersonA**
- string[] **DialogPersonB**
- string **CurrentDialogA** = string.Empty
- string **CurrentDialogB** = string.Empty
- bool **Running** = false

5.23.1 Detailed Description

[Simple](#) dialog system with TTS voices.

The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/RTVoice/↵ Demo/Scripts/Dialog.cs

5.24 Crosstales.RTVoice.EditorUtil.EditorConfig Class Reference

Editor configuration for the asset.

Static Public Member Functions

- static void [Reset](#) ()
Resets all changable variables to their default value.
- static void [Load](#) ()
Loads all changable variables.
- static void [Save](#) ()
Saves all changable variables.

Static Public Attributes

- static bool [UPDATE_CHECK](#) = EditorConstants.DEFAULT_UPDATE_CHECK
Enable or disable update-checks for the asset.
- static bool [REMINDER_CHECK](#) = EditorConstants.DEFAULT_REMINDER_CHECK
Enable or disable reminder-checks for the asset.
- static bool [TELEMETRY](#) = EditorConstants.DEFAULT_TELEMETRY
Enable or disable anonymous telemetry data.
- static bool [PREFAB_AUTOLOAD](#) = EditorConstants.DEFAULT_PREFAB_AUTOLOAD
Automatically load and add the prefabs to the scene.
- static bool [HIERARCHY_ICON](#) = EditorConstants.DEFAULT_HIERARCHY_ICON
Enable or disable the icon in the hierarchy.
- static bool [isLoading](#) = false
Is the configuration loaded?

Properties

- static string `ASSET_PATH` [get]
Returns the path to the asset inside the Unity project.
- static string `PREFAB_PATH` [get]
Returns the path of the prefabs.

5.24.1 Detailed Description

Editor configuration for the asset.

5.24.2 Member Function Documentation

5.24.2.1 static void Crosstales.RTVoice.EditorUtil.EditorConfig.Load () [static]

Loads all changable variables.

5.24.2.2 static void Crosstales.RTVoice.EditorUtil.EditorConfig.Reset () [static]

Resets all changable variables to their default value.

5.24.2.3 static void Crosstales.RTVoice.EditorUtil.EditorConfig.Save () [static]

Saves all changable variables.

5.24.3 Member Data Documentation

5.24.3.1 bool Crosstales.RTVoice.EditorUtil.EditorConfig.HIERARCHY_ICON = EditorConstants.DEFAULT_HIERARCHY_ICON [static]

Enable or disable the icon in the hierarchy.

5.24.3.2 bool Crosstales.RTVoice.EditorUtil.EditorConfig.isLoaded = false [static]

Is the configuration loaded?

5.24.3.3 bool Crosstales.RTVoice.EditorUtil.EditorConfig.PREFAB_AUTOLOAD = EditorConstants.DEFAULT_PREFAB_AUTOLOAD [static]

Automatically load and add the prefabs to the scene.

5.24.3.4 **bool** Crosstales.RTVoice.EditorUtil.EditorConfig.REMINDER_CHECK = EditorConstants.DEFAULT_REMINDER_CHECK
[static]

Enable or disable reminder-checks for the asset.

5.24.3.5 **bool** Crosstales.RTVoice.EditorUtil.EditorConfig.TELEMTRY = EditorConstants.DEFAULT_TELEMTRY
[static]

Enable or disable anonymous telemetry data.

5.24.3.6 **bool** Crosstales.RTVoice.EditorUtil.EditorConfig.UPDATE_CHECK = EditorConstants.DEFAULT_UPDATE_CHECK
[static]

Enable or disable update-checks for the asset.

5.24.4 Property Documentation

5.24.4.1 **string** Crosstales.RTVoice.EditorUtil.EditorConfig.ASSET_PATH [static], [get]

Returns the path to the asset inside the Unity project.

Returns

The path to the asset inside the Unity project.

5.24.4.2 **string** Crosstales.RTVoice.EditorUtil.EditorConfig.PREFAB_PATH [static], [get]

Returns the path of the prefabs.

Returns

The path of the prefabs.

The documentation for this class was generated from the following file:

- D:/slauberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/RTVoice/↔
Editor/Util/EditorConfig.cs

5.25 Crosstales.RTVoice.EditorUtil.EditorConstants Class Reference

Collected constants of very general utility for the asset.

Public Attributes

- const string **KEY_UPDATE_CHECK** = Util.Constants.KEY_PREFIX + "UPDATE_CHECK"
- const string **KEY_REMINDER_CHECK** = Util.Constants.KEY_PREFIX + "REMINDER_CHECK"
- const string **KEY_TELEMETRY** = Util.Constants.KEY_PREFIX + "TELEMETRY"
- const string **KEY_PREFAB_AUTOLOAD** = Util.Constants.KEY_PREFIX + "PREFAB_AUTOLOAD"
- const string **KEY_HIERARCHY_ICON** = Util.Constants.KEY_PREFIX + "HIERARCHY_ICON"
- const string **KEY_UPDATE_DATE** = Util.Constants.KEY_PREFIX + "UPDATE_DATE"
- const string **KEY_REMINDER_DATE** = Util.Constants.KEY_PREFIX + "REMINDER_DATE"
- const string **KEY_REMINDER_COUNT** = Util.Constants.KEY_PREFIX + "REMINDER_COUNT"
- const string **KEY_LAUNCH** = Util.Constants.KEY_PREFIX + "LAUNCH"
- const string **KEY_TELEMETRY_DATE** = Util.Constants.KEY_PREFIX + "TELEMETRY_DATE"
- const string **DEFAULT_ASSET_PATH** = "/Plugins/crosstales/RTVoice/"
- const bool **DEFAULT_UPDATE_CHECK** = true
- const bool **DEFAULT_UPDATE_OPEN_UAS** = false
- const bool **DEFAULT_REMINDER_CHECK** = true
- const bool **DEFAULT_TELEMETRY** = true
- const bool **DEFAULT_PREFAB_AUTOLOAD** = false
- const bool **DEFAULT_HIERARCHY_ICON** = true

Static Public Attributes

- static string **PREFAB_SUBPATH** = "Prefabs/"
Sub-path to the prefabs.

Properties

- static string **ASSET_URL** [get]
Returns the URL of the asset in UAS.
- static System.Guid **ASSET_UID** [get]
Returns the UID of the asset.

5.25.1 Detailed Description

Collected constants of very general utility for the asset.

5.25.2 Member Data Documentation

5.25.2.1 string Crosstales.RTVoice.EditorUtil.EditorConstants.PREFAB_SUBPATH = "Prefabs/" [static]

Sub-path to the prefabs.

5.25.3 Property Documentation

5.25.3.1 System.Guid Crosstales.RTVoice.EditorUtil.EditorConstants.ASSET_UID [static], [get]

Returns the UID of the asset.

Returns

The UID of the asset.

5.25.3.2 string Crosstales.RTVoice.EditorUtil.EditorConstants.ASSET_URL [static], [get]

Returns the URL of the asset in UAS.

Returns

The URL of the asset in UAS.

The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/RTVoice/Editor/Util/EditorConstants.cs

5.26 Crosstales.RTVoice.EditorUtil.EditorHelper Class Reference

Editor helper class.

Static Public Member Functions

- static void **NoVoicesUI** ()
Shows the "no voices found"-UI.
- static void **SeparatorUI** (int space=12)
Shows a separator-UI.
- static void **InstantiatePrefab** (string prefabName)
Instantiates a prefab.

Public Attributes

- const int **GO_ID** = 20
Start index inside the "GameObject"-menu.
- const int **MENU_ID** = 11820
Start index inside the "Tools"-menu.

Properties

- static Texture2D **Logo_Asset** [get]
- static Texture2D **Logo_Asset_Small** [get]
- static Texture2D **Logo_CT** [get]
- static Texture2D **Logo_Unity** [get]
- static Texture2D **Icon_Save** [get]
- static Texture2D **Icon_Reset** [get]
- static Texture2D **Icon_Plus** [get]
- static Texture2D **Icon_Minus** [get]
- static Texture2D **Icon_Refresh** [get]
- static Texture2D **Icon_Speak** [get]
- static Texture2D **Icon_Silence** [get]
- static Texture2D **Icon_Manual** [get]
- static Texture2D **Icon_API** [get]

- static Texture2D **Icon_Forum** [get]
- static Texture2D **Icon_Product** [get]
- static Texture2D **Icon_Check** [get]
- static Texture2D **Social_Facebook** [get]
- static Texture2D **Social_Twitter** [get]
- static Texture2D **Social_Youtube** [get]
- static Texture2D **Social_Linkedin** [get]
- static Texture2D **Social_Xing** [get]
- static Texture2D **Video_Promo** [get]
- static Texture2D **Video_Tutorial** [get]
- static Texture2D **Icon_Videos** [get]
- static Texture2D **Store_PlayMaker** [get]
- static Texture2D **Store_AdventureCreator** [get]
- static Texture2D **Store_CinemaDirector** [get]
- static Texture2D **Store_DialogueSystem** [get]
- static Texture2D **Store_LDC** [get]
- static Texture2D **Store_LipSync** [get]
- static Texture2D **Store_NPC_Chat** [get]
- static Texture2D **Store_QuestSystem** [get]
- static Texture2D **Store_SALSA** [get]
- static Texture2D **Store_SLATE** [get]
- static Texture2D **Store_THE_Dialogue_Engine** [get]
- static Texture2D **Store_uSequencer** [get]
- static Texture2D **Icon_3p_Assets** [get]
- static bool **isRTVoiceInScene** [get]

Checks if the 'RTVoice'-prefab is in the scene.

5.26.1 Detailed Description

Editor helper class.

5.26.2 Member Function Documentation

5.26.2.1 static void Crosstales.RTVoice.EditorUtil.EditorHelper.InstantiatePrefab (string *prefabName*) [static]

Instantiates a prefab.

Parameters

<i>prefabName</i>	Name of the prefab.
-------------------	---------------------

5.26.2.2 static void Crosstales.RTVoice.EditorUtil.EditorHelper.NoVoicesUI () [static]

Shows the "no voices found"-UI.

5.26.2.3 static void Crosstales.RTVoice.EditorUtil.EditorHelper.SeparatorUI (int *space* = 12) [static]

Shows a separator-UI.

Parameters

<i>space</i>	Space in pixels between the component and the seperator line (default: 12, optional).
--------------	---

5.26.3 Member Data Documentation

5.26.3.1 `const int Crosstales.RTVoice.EditorUtil.EditorHelper.GO_ID = 20`

Start index inside the "GameObject"-menu.

5.26.3.2 `const int Crosstales.RTVoice.EditorUtil.EditorHelper.MENU_ID = 11820`

Start index inside the "Tools"-menu.

5.26.4 Property Documentation

5.26.4.1 `bool Crosstales.RTVoice.EditorUtil.EditorHelper.isRTVoiceInScene` `[static], [get]`

Checks if the 'RTVoice'-prefab is in the scene.

Returns

True if the 'RTVoice'-prefab is in the scene.

The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/RTVoice/↔ Editor/Util/EditorHelper.cs

5.27 Crosstales.ExtensionMethods Class Reference

Various extension methods.

Static Public Member Functions

- static string [CTToTitleCase](#) (this string str)
Extension method for strings. Converts a string to title case (first letter uppercase).
- static string [CTReplace](#) (this string str, string oldString, string newString, System.StringComparison comp=System.StringComparison.OrdinalIgnoreCase)
Extension method for strings. Case insensitive 'Replace'.
- static bool [CTEquals](#) (this string str, string toCheck, System.StringComparison comp=System.StringComparison.OrdinalIgnoreCase)
Extension method for strings. Case insensitive 'Equals'.
- static bool [CTContains](#) (this string str, string toCheck, System.StringComparison comp=System.StringComparison.OrdinalIgnoreCase)
Extension method for strings. Case insensitive 'Contains'.
- static bool [CTContainsAny](#) (this string str, string searchTerms, char splitChar= ' ')
Extension method for strings. Contains any given string.
- static bool [CTContainsAll](#) (this string str, string searchTerms, char splitChar= ' ')
Extension method for strings. Contains all given strings.
- static void [CTShuffle< T >](#) (this T[] array)
Extension method for Arrays. Shuffles an Array.
- static string [CTDump< T >](#) (this T[] array)
Extension method for Arrays. Dumps an array to a string.
- static string[] [CTToString< T >](#) (this T[] array)
Extension method for Arrays. Generates a string array with all entries (via ToString).
- static void [CTShuffle< T >](#) (this System.Collections.Generic.IList< T > list)
Extension method for Lists. Shuffles a List.
- static string [CTDump< T >](#) (this System.Collections.Generic.List< T > list)
Extension method for Lists. Dumps a list to a string.
- static System.Collections.Generic.List< string > [CTToString< T >](#) (this System.Collections.Generic.List< T > list)
Extension method for Lists. Generates a string list with all entries (via ToString).
- static void [CTAddRange< T, S >](#) (this System.Collections.Generic.Dictionary< T, S > source, System.Collections.Generic.Dictionary< T, S > collection)
Extension method for dictionaries. Adds a dictionary to an existing one.

5.27.1 Detailed Description

Various extension methods.

5.27.2 Member Function Documentation

- 5.27.2.1** static void `Crosstales.ExtensionMethods.CTAddRange< T, S > (this System.Collections.Generic.Dictionary< T, S > source, System.Collections.Generic.Dictionary< T, S > collection)` [static]

Extension method for dictionaries. Adds a dictionary to an existing one.

Parameters

<i>source</i>	Dictionary-instance.
<i>collection</i>	Dictionary to add.

5.27.2.2 `static bool Crosstales.ExtensionMethods.CTContains (this string str, string toCheck, System.StringComparison comp = System.StringComparison.OrdinalIgnoreCase) [static]`

Extension method for strings. Case insensitive 'Contains'.

Parameters

<i>str</i>	String-instance.
<i>toCheck</i>	String to check.
<i>comp</i>	StringComparison-method (default: StringComparison.OrdinalIgnoreCase, optional)

Returns

True if the string contains the given string.

5.27.2.3 `static bool Crosstales.ExtensionMethods.CTContainsAll (this string str, string searchTerms, char splitChar = ' ') [static]`

Extension method for strings. Contains all given strings.

Parameters

<i>str</i>	String-instance.
<i>searchTerms</i>	Search terms separated by the given split-character.
<i>splitChar</i>	Split-character (default: ' ', optional)

Returns

True if the string contains all parts of the given string.

5.27.2.4 `static bool Crosstales.ExtensionMethods.CTContainsAny (this string str, string searchTerms, char splitChar = ' ') [static]`

Extension method for strings. Contains any given string.

Parameters

<i>str</i>	String-instance.
<i>searchTerms</i>	Search terms separated by the given split-character.
<i>splitChar</i>	Split-character (default: ' ', optional)

Returns

True if the string contains any parts of the given string.

5.27.2.5 static string Crosstales.ExtensionMethods.CTDump< T > (this T[] array) [static]

Extension method for Arrays. Dumps an array to a string.

Parameters

<i>array</i>	Array-instance to dump.
--------------	-------------------------

Returns

String with lines for all array entries.

5.27.2.6 static string Crosstales.ExtensionMethods.CTDump< T > (this System.Collections.Generic.List< T > list) [static]

Extension method for Lists. Dumps a list to a string.

Parameters

<i>list</i>	List-instance to dump.
-------------	------------------------

Returns

String with lines for all list entries.

5.27.2.7 static bool Crosstales.ExtensionMethods.CTEquals (this string str, string toCheck, System.StringComparison comp = System.StringComparison.OrdinalIgnoreCase) [static]

Extension method for strings. Case insensitive 'Equals'.

Parameters

<i>str</i>	String-instance.
<i>toCheck</i>	String to check.
<i>comp</i>	StringComparison-method (default: StringComparison.OrdinalIgnoreCase, optional)

Returns

True if the string contains the given string.

5.27.2.8 static string Crosstales.ExtensionMethods.CTReplace (this string str, string oldString, string newString, System.StringComparison comp = System.StringComparison.OrdinalIgnoreCase) [static]

Extension method for strings. Case insensitive 'Replace'.

Parameters

<i>str</i>	String-instance.
<i>oldString</i>	String to replace.
<i>newString</i>	New replacement string.
<i>comp</i>	StringComparison-method (default: StringComparison.OrdinalIgnoreCase, optional)

Returns

Replaced string.

5.27.2.9 `static void Crosstales.ExtensionMethods.CTShuffle< T > (this T[] array) [static]`

Extension method for Arrays. Shuffles an Array.

Parameters

<i>array</i>	Array-instance to shuffle.
--------------	----------------------------

5.27.2.10 `static void Crosstales.ExtensionMethods.CTShuffle< T > (this System.Collections.Generic.IList< T > list) [static]`

Extension method for Lists. Shuffles a List.

Parameters

<i>list</i>	List-instance to shuffle.
-------------	---------------------------

5.27.2.11 `static string [] Crosstales.ExtensionMethods.CTToString< T > (this T[] array) [static]`

Extension method for Arrays. Generates a string array with all entries (via ToString).

Parameters

<i>array</i>	Array-instance to ToString.
--------------	-----------------------------

Returns

String array with all entries (via ToString).

5.27.2.12 `static System.Collections.Generic.List<string> Crosstales.ExtensionMethods.CTToString< T > (this System.Collections.Generic.List< T > list) [static]`

Extension method for Lists. Generates a string list with all entries (via ToString).

Parameters

<i>list</i>	List-instance to ToString.
-------------	----------------------------

Returns

String list with all entries (via ToString).

5.27.2.13 static string Crosstales.ExtensionMethods.CTToTitleCase (this string *str*) [static]

Extension method for strings. Converts a string to title case (first letter uppercase).

Parameters

<i>str</i>	String-instance.
------------	------------------

Returns

Converted string in title case.


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/Common/↵
Scripts/ExtensionMethods.cs

5.28 Crosstales.DJ.Demo.Util.FFTAnalyzer Class Reference

FFT analyzer for an audio channel.

Inheritance diagram for Crosstales.DJ.Demo.Util.FFTAnalyzer:



Public Member Functions

- void **Update** ()

Public Attributes

- float[] **Samples** = new float[256]
- int **Channel** = 0
- FFTWindow **FFTMode** = FFTWindow.BlackmanHarris

5.28.1 Detailed Description

FFT analyzer for an audio channel.


The documentation for this class was generated from the following file:

- [D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstailes/Common/UI/Scripts/Util/FFTAnalyzer.cs](#)

5.29 Crosstailes.UI.Util.FPSDisplay Class Reference

Simple FPS-Counter.

Inheritance diagram for Crosstailes.UI.Util.FPSDisplay:



Public Member Functions

- void **Update** ()

Public Attributes

- Text **FPS**

5.29.1 Detailed Description

Simple FPS-Counter.


The documentation for this class was generated from the following file:

- [D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstailes/Common/UI/Scripts/Util/FPSDisplay.cs](#)

5.30 Crosstailes.RTVoice.EditorUtil.GAApi Class Reference

GA-wrapper API.

Inheritance diagram for Crosstailes.RTVoice.EditorUtil.GAApi:



Static Public Member Functions

- static void [Event](#) (string category, string action, string label="", int value=0)
Tracks an event from the asset.

5.30.1 Detailed Description

GA-wrapper API.

5.30.2 Member Function Documentation

5.30.2.1 static void Crosstales.RTVoice.EditorUtil.GAApi.Event (string *category*, string *action*, string *label* = " ", int *value* = 0) [static]

Tracks an event from the asset.

Parameters

<i>category</i>	Specifies the event category.
<i>action</i>	Specifies the event action.
<i>label</i>	Specifies the event label.
<i>value</i>	Specifies the event value.


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/RTVoice/↔ Editor/Util/GAApi.cs

5.31 Crosstales.RTVoice.Demo.GUIAudioFilter Class Reference

[Simple](#) GUI for audio filters.

Inheritance diagram for Crosstales.RTVoice.Demo.GUIAudioFilter:



Public Member Functions

- void **Start** ()
- void **ResetFilters** ()
- void **ReverbFilterDropdownChanged** (System.Int32 index)
- void **ChorusFilterEnabled** (bool enabled)

- void **EchoFilterEnabled** (bool enabled)
- void **DistortionFilterEnabled** (bool enabled)
- void **DistortionFilterChanged** (float value)
- void **LowPassFilterEnabled** (bool enabled)
- void **LowPassFilterChanged** (float value)
- void **HighPassFilterEnabled** (bool enabled)
- void **HighPassFilterChanged** (float value)
- void **VolumeChanged** (float value)
- void **PitchChanged** (float value)

Public Attributes

- AudioSource **Source**
- AudioReverbFilter **ReverbFilter**
- AudioChorusFilter **ChorusFilter**
- AudioEchoFilter **EchoFilter**
- AudioDistortionFilter **DistortionFilter**
- AudioLowPassFilter **LowPassFilter**
- AudioHighPassFilter **HighPassFilter**
- Text **Distortion**
- Text **Lowpass**
- Text **Highpass**
- Text **Volume**
- Text **Pitch**
- Dropdown **ReverbFilterDropdown**

5.31.1 Detailed Description

[Simple](#) GUI for audio filters.


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/RTVoice/↔ Demo/Scripts/GUIAudioFilter.cs

5.32 Crosstales.RTVoice.Demo.GUIDialog Class Reference

[Simple](#) GUI for runtime dialogs with all available OS voices.

Inheritance diagram for Crosstales.RTVoice.Demo.GUIDialog:



Public Member Functions

- void **Start** ()
- void **Update** ()
- void **StartDialog** ()
- void **Silence** ()
- void **ChangeRateA** (float value)
- void **ChangeRateB** (float value)
- void **ChangePitchA** (float value)
- void **ChangePitchB** (float value)
- void **ChangeVolumeA** (float value)
- void **ChangeVolumeB** (float value)

Public Attributes

- [Dialog](#) **DialogScript**
- Color32 **SpeakerColor** = new Color32(0, 255, 0, 192)
- Image **PanelPersonA**
- Image **PanelPersonB**
- Text **PersonA**
- Text **PersonB**

5.32.1 Detailed Description

[Simple](#) GUI for runtime dialogs with all available OS voices.


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/RTVoice/↔ Demo/Scripts/GUIDialog.cs

5.33 Crosstales.RTVoice.Demo.GUIMain Class Reference

Main GUI component for all demo scenes.

Inheritance diagram for Crosstales.RTVoice.Demo.GUIMain:



Public Member Functions

- void **Start** ()
- void **Update** ()
- void **OnDestroy** ()
- void **OpenAssetURL** ()
- void **OpenCTURL** ()
- void **Silence** ()
- void **Quit** ()

Public Attributes

- Text **Name**
- Text **Version**
- Text **Scene**
- GameObject **NoVoices**
- Text **Errors**

5.33.1 Detailed Description

Main GUI component for all demo scenes.


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/RTVoice/↔ Demo/Scripts/GUIMain.cs

5.34 Crosstales.RTVoice.Demo.GUIMultiAudioFilter Class Reference

[Simple](#) GUI for audio filters on multiple objects.

Inheritance diagram for Crosstales.RTVoice.Demo.GUIMultiAudioFilter:



Public Member Functions

- void **Start** ()
- void **ResetFilters** ()
- void **ClearFilters** ()
- void **ReverbFilterDropdownChanged** (System.Int32 index)
- void **ChorusFilterEnabled** (bool enabled)
- void **EchoFilterEnabled** (bool enabled)
- void **DistortionFilterEnabled** (bool enabled)
- void **DistortionFilterChanged** (float value)
- void **LowPassFilterEnabled** (bool enabled)
- void **LowPassFilterChanged** (float value)
- void **HighPassFilterEnabled** (bool enabled)
- void **HighPassFilterChanged** (float value)
- void **VolumeChanged** (float value)
- void **PitchChanged** (float value)

Public Attributes

- System.Collections.Generic.List< AudioSource > **Sources** = new System.Collections.Generic.List<AudioSource>()
- System.Collections.Generic.List< AudioReverbFilter > **ReverbFilters** = new System.Collections.Generic.List<AudioReverbFilter>()
- System.Collections.Generic.List< AudioChorusFilter > **ChorusFilters** = new System.Collections.Generic.List<AudioChorusFilter>()
- System.Collections.Generic.List< AudioEchoFilter > **EchoFilters** = new System.Collections.Generic.List<AudioEchoFilter>()
- System.Collections.Generic.List< AudioDistortionFilter > **DistortionFilters** = new System.Collections.Generic.List<AudioDistortionFilter>()
- System.Collections.Generic.List< AudioLowPassFilter > **LowPassFilters** = new System.Collections.Generic.List<AudioLowPassFilter>()
- System.Collections.Generic.List< AudioHighPassFilter > **HighPassFilters** = new System.Collections.Generic.List<AudioHighPassFilter>()
- Text **Distortion**
- Text **Lowpass**
- Text **Highpass**
- Text **Volume**
- Text **Pitch**
- Dropdown **ReverbFilterDropdown**

5.34.1 Detailed Description

[Simple](#) GUI for audio filters on multiple objects.


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstailes/RTVoice/Demo/Scripts/GUIMultiAudioFilter.cs

5.35 Crosstailes.RTVoice.Demo.GUIScenes Class Reference

Main GUI scene manager for all demo scenes.

Inheritance diagram for Crosstailes.RTVoice.Demo.GUIScenes:



Public Member Functions

- void **LoadPrevoiusScene** ()
- void **LoadNextScene** ()

Public Attributes

- string **PreviousScene**
- string **NextScene**

5.35.1 Detailed Description

Main GUI scene manager for all demo scenes.


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/RTVoice/↔ Demo/Scripts/GUIScenes.cs

5.36 Crosstales.RTVoice.Demo.GUISpeech Class Reference

[Simple](#) GUI for runtime TTS with all available OS voices.

Inheritance diagram for Crosstales.RTVoice.Demo.GUISpeech:



Public Member Functions

- void **Start** ()
- void **Update** ()
- void **OnDestroy** ()
- void **Silence** ()
- void **ChangeRate** (float rate)
- void **ChangeVolume** (float volume)
- void **ChangePitch** (float pitch)
- void **ChangeNative** (bool native)
- void **ChangeMaryTTS** (bool maryTTS)

Public Attributes

- bool **StartAsNative** = false
- [GUIMultiAudioFilter](#) **AudioFilter**
- GameObject **ItemPrefab**
- GameObject **Target**
- Scrollbar **Scroll**
- int **ColumnCount** = 1
- Vector2 **SpaceWidth** = new Vector2(8, 8)
- Vector2 **SpaceHeight** = new Vector2(8, 8)
- InputField **Input**
- InputField **Culture**
- Text **Cultures**
- Toggle **MaryToogle**
- Text **Voices**

Static Public Attributes

- static float **Rate** = 1f
- static float **Pitch** = 1f
- static float **Volume** = 1f
- static bool **isNative** = false

5.36.1 Detailed Description

[Simple](#) GUI for runtime TTS with all available OS voices.


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/RTVoice/↵ Demo/Scripts/GUISpeech.cs

5.37 Crosstales.RTVoice.Util.Helper Class Reference

Various helper functions.

Inheritance diagram for Crosstales.RTVoice.Util.Helper:



Static Public Member Functions

- static string [CleanText](#) (string text, bool removeTags=true, bool clearSpaces=true, bool clearLine↵ Endings=true)
Cleans a given text to contain only letters or digits.
- static string [MarkSpokenText](#) (string[] speechTextArray, int wordIndex, bool markAllSpokenWords=false, string markPrefix="<color=green>", string markPostfix="</color>")
Marks the current word or all spoken words from a given text array.

Properties

- static bool [hasBuiltInTTS](#) [get]
Checks if the current platform has built-in TTS.
- static [Model.Enum.ProviderType CurrentProviderType](#) [get]
The current provider type.

5.37.1 Detailed Description

Various helper functions.

5.37.2 Member Function Documentation

- 5.37.2.1 static string Crosstales.RTVoice.Util.Helper.CleanText (string text, bool removeTags = true, bool clearSpaces = true, bool clearLineEndings = true) [static]

Cleans a given text to contain only letters or digits.

Parameters

<i>text</i>	Text to clean.
<i>removeTags</i>	Removes tags from text (default: true, optional).
<i>clearSpaces</i>	Clears multiple spaces from text (default: true, optional).
<i>clearLineEndings</i>	Clears line endings from text (default: true, optional).

Returns

Clean text with only letters and digits.

5.37.2.2 `static string Crosstales.RTVoice.Util.Helper.MarkSpokenText (string[] speechTextArray, int wordIndex, bool markAllSpokenWords = false, string markPrefix = "<color=green>", string markPostfix = "</color>") [static]`

Marks the current word or all spoken words from a given text array.

Parameters

<i>speechTextArray</i>	Array with all text fragments
<i>wordIndex</i>	Current word index
<i>markAllSpokenWords</i>	Mark the spoken words (default: false, optional)
<i>markPrefix</i>	Prefix for every marked word (default: green, optional)
<i>markPostfix</i>	Postfix for every marked word (default: green, optional)

Returns

Marked current word or all spoken words.

5.37.3 Property Documentation

5.37.3.1 `Model.Enum.ProviderType Crosstales.RTVoice.Util.Helper.CurrentProviderType [static], [get]`

The current provider type.

Returns

Current provider type.

5.37.3.2 `bool Crosstales.RTVoice.Util.Helper.hasBuiltInTTS [static], [get]`

Checks if the current platform has built-in TTS.

Returns

True if the current platform has built-in TTS.


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/RTVoice/Scripts/Util/Helper.cs

5.38 Crosstales.RTVoice.Demo.Util.iOSController Class Reference

Enables MaryTTS on iOS for specific scenes.

Inheritance diagram for Crosstales.RTVoice.Demo.Util.iOSController:



Public Member Functions

- void **Start** ()
- void **OnDestroy** ()

5.38.1 Detailed Description

Enables MaryTTS on iOS for specific scenes.

The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/RTVoice/↔ Demo/Scripts/Util/iOSController.cs

5.39 Crosstales.RTVoice.EditorTask.Launch Class Reference

Show the configuration window on the first launch.

5.39.1 Detailed Description

Show the configuration window on the first launch.


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/RTVoice/↔ Editor/Task/Launch.cs

5.40 Crosstales.RTVoice.LiveSpeaker Class Reference

Wrapper of the main component from [RTVoice](#) for MonoBehaviour-access (like "SendMessage").

Inheritance diagram for Crosstales.RTVoice.LiveSpeaker:



Public Member Functions

- void [SpeakNative](#) ([Model.Wrapper](#) wrapper)
Speaks a text with a given wrapper -> native mode.
- void [SpeakNative](#) (string args)
Speaks a text with a given array of arguments (native mode).
- void [SpeakNative](#) (string[] args)
Speaks a text with a given array of arguments (native mode).
- void [Speak](#) ([Model.Wrapper](#) wrapper)
Speaks a text with a given wrapper.
- void [Speak](#) (string args)
Speaks a text with a given array of arguments.
- void [Speak](#) (string[] args)
Speaks a text with a given array of arguments.
- void [Silence](#) ()
Silence all active TTS-voices.
- void [SetVoices](#) (string voices)
Sets all voices from iOS.
- void [WordSpoken](#) (string word)
The current spoken word from iOS.
- void [SetState](#) (string state)
Sets the state from iOS.

5.40.1 Detailed Description

Wrapper of the main component from [RTVoice](#) for MonoBehaviour-access (like "SendMessage").

5.40.2 Member Function Documentation

5.40.2.1 void Crosstales.RTVoice.LiveSpeaker.SetState (string state)

Sets the state from iOS.

Parameters

<i>voices</i>	State from iOS.</param
---------------	------------------------

5.40.2.2 void Crosstales.RTVoice.LiveSpeaker.SetVoices (string voices)

Sets all voices from iOS.

Parameters

<i>voices</i>	All voices from iOS.</param
---------------	-----------------------------

5.40.2.3 void Crosstales.RTVoice.LiveSpeaker.Silence ()

Silence all active TTS-voices.

5.40.2.4 void Crosstales.RTVoice.LiveSpeaker.Speak (**Model.Wrapper** *wrapper*)

Speaks a text with a given wrapper.

Parameters

<i>wrapper</i>	Wrapper with the speech details.
----------------	----------------------------------

5.40.2.5 void Crosstales.RTVoice.LiveSpeaker.Speak (string *args*)

Speaks a text with a given array of arguments.

Important: you can't specify the AudioSource with this method!

Parameters

<i>args</i>	Argument string delimited by ';': 0 = text, 1 = culture (optional), 2 = voiceName (optional), 3 = rate (optional), 4 = volume (optional), 5 = pitch (optional).
-------------	---

5.40.2.6 void Crosstales.RTVoice.LiveSpeaker.Speak (string[] *args*)

Speaks a text with a given array of arguments.

Important: you can't specify the AudioSource with this method!

Parameters

<i>args</i>	Argument index: 0 = text, 1 = culture (optional), 2 = voiceName (optional), 3 = rate (optional), 4 = pitch (optional), 5 = volume (optional).
-------------	---

5.40.2.7 void Crosstales.RTVoice.LiveSpeaker.SpeakNative (**Model.Wrapper** *wrapper*)

Speaks a text with a given wrapper -> native mode.

Parameters

<i>wrapper</i>	Wrapper with the speech details.
----------------	----------------------------------

5.40.2.8 void Crosstales.RTVoice.LiveSpeaker.SpeakNative (string *args*)

Speaks a text with a given array of arguments (native mode).

Parameters

<i>args</i>	Argument string delimited by ';': 0 = text, 1 = culture (optional), 2 = voiceName (optional), 3 = rate (optional), 4 = volume (optional), 5 = pitch (optional).
-------------	---

5.40.2.9 void Crosstales.RTVoice.LiveSpeaker.SpeakNative (string[] *args*)

Speaks a text with a given array of arguments (native mode).

Parameters

<i>args</i>	Argument index: 0 = text, 1 = culture (optional), 2 = voiceName (optional), 3 = rate (optional), 4 = pitch (optional), 5 = volume (optional).
-------------	---

5.40.2.10 void Crosstales.RTVoice.LiveSpeaker.WordSpoken (string *word*)

The current spoken word from iOS.

Parameters

<i>voices</i>	Current spoken word from iOS.
---------------	-------------------------------


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/RTVoice/Scripts/LiveSpeaker.cs

5.41 Crosstales.RTVoice.Tool.Loudspeaker Class Reference

[Loudspeaker](#) for an AudioSource.

Inheritance diagram for Crosstales.RTVoice.Tool.Loudspeaker:



Public Member Functions

- void **Awake** ()
- void **Start** ()
- void **Update** ()
- void **FixedUpdate** ()
- void **OnDisable** ()

Public Attributes

- AudioSource [Source](#)
Origin AudioSource.
- bool [Synchronized](#) = false
Synchronize with the origin (default: false).
- bool [SilenceSource](#) = true
Silence the origin (default: true).

Properties

- bool [isSynchronized](#) [get, set]
Synchronize with the origin (main use is for [UI](#)).
- bool [isSilenceSource](#) [get, set]
Silence the origin (main use is for [UI](#)).

5.41.1 Detailed Description

[Loudspeaker](#) for an AudioSource.

5.41.2 Member Data Documentation

5.41.2.1 bool Crosstales.RTVoice.Tool.Loudspeaker.SilenceSource = true

Silence the origin (default: true).

5.41.2.2 AudioSource Crosstales.RTVoice.Tool.Loudspeaker.Source

Origin AudioSource.

5.41.2.3 bool Crosstales.RTVoice.Tool.Loudspeaker.Synchronized = false

Synchronize with the origin (default: false).

5.41.3 Property Documentation

5.41.3.1 `bool Crosstales.RTVoice.Tool.Loudspeaker.isSilenceSource` `[get]`, `[set]`

Silence the origin (main use is for [UI](#)).

5.41.3.2 `bool Crosstales.RTVoice.Tool.Loudspeaker.isSynchronized` `[get]`, `[set]`

Synchronize with the origin (main use is for [UI](#)).


The documentation for this class was generated from the following file:

- `D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/RTVoice/↔ Scripts/Tool/Loudspeaker.cs`

5.42 Crosstales.RTVoice.EditorExtension.LoudspeakerEditor Class Reference

Custom editor for the 'Loudspeaker'-class.

Inheritance diagram for `Crosstales.RTVoice.EditorExtension.LoudspeakerEditor`:



Public Member Functions

- void **OnEnable** ()
- override void **OnInspectorGUI** ()

5.42.1 Detailed Description

Custom editor for the 'Loudspeaker'-class.


The documentation for this class was generated from the following file:

- `D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/RTVoice/↔ Editor/Extension/LoudspeakerEditor.cs`

5.43 Crosstales.RTVoice.Demo.Util.MaterialChanger Class Reference

Changes the material of a renderer while an AudioSource is playing.

Inheritance diagram for Crosstales.RTVoice.Demo.Util.MaterialChanger:



Public Member Functions

- void **Start** ()
- void **Update** ()

Public Attributes

- AudioSource **Source**
- Material **ActiveMaterial**

5.43.1 Detailed Description

Changes the material of a renderer while an AudioSource is playing.


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/RTVoice/↵ Demo/Scripts/Util/MaterialChanger.cs

5.44 Crosstales.RTVoice.Demo.NativeAudio Class Reference

[Simple](#) example with native audio for exact timing.

Inheritance diagram for Crosstales.RTVoice.Demo.NativeAudio:



Public Member Functions

- void **Start** ()
- void **OnDestroy** ()
- void **StartTTS** ()
- void **Silence** ()

Public Attributes

- string **SpeechText** = "This is an example with native audio for exact timing (e.g. animations)."
- bool **PlayOnStart** = false
- float **Delay** = 1f

5.44.1 Detailed Description

[Simple](#) example with native audio for exact timing.


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/RTVoice/↔ Demo/Scripts/NativeAudio.cs

5.45 Crosstales.RTVoice.Demo.Util.NativeController Class Reference

Enables or disable game objects for native mode.

Inheritance diagram for Crosstales.RTVoice.Demo.Util.NativeController:



Public Member Functions

- void **Update** ()

Public Attributes

- bool [Active](#) = true
Enable or disable the 'Objects' for native mode (default: true).
- GameObject[] [Objects](#)
Selected objects for the controller.

5.45.1 Detailed Description

Enables or disable game objects for native mode.

5.45.2 Member Data Documentation

5.45.2.1 bool Crosstales.RTVoice.Demo.Util.NativeController.Active = true

Enable or disable the 'Objects' for native mode (default: true).

5.45.2.2 GameObject [] Crosstales.RTVoice.Demo.Util.NativeController.Objects

Selected objects for the controller.

The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/RTVoice/↔ Demo/Scripts/Util/NativeController.cs

5.46 Crosstales.Common.EditorTask.NYCheck Class Reference

Checks if a 'Happy new year'-message must be displayed.

5.46.1 Detailed Description

Checks if a 'Happy new year'-message must be displayed.

The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/Common/↔ Editor/Task/NYCheck.cs

5.47 Crosstales.Common.EditorTask.OCCheck Class Reference

Checks if 'Online Check' is installed.

5.47.1 Detailed Description

Checks if 'Online Check' is installed.


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/Common/↔ Editor/Task/OCCheck.cs

5.48 Crosstales.Common.Util.PlatformController Class Reference

Enables or disable game objects for a given platform.

Inheritance diagram for Crosstales.Common.Util.PlatformController:



Public Member Functions

- virtual void **Start** ()

Public Attributes

- System.Collections.Generic.List< [Platform](#) > [Platforms](#)
Selected platforms for the controller.
- bool **Active** = true
- GameObject[] [Objects](#)
Selected objects for the controller.

Protected Member Functions

- void **selectPlatform** ()
- void **activateGO** ()

Protected Attributes

- [Platform](#) **currentPlatform**

5.48.1 Detailed Description

Enables or disable game objects for a given platform.

5.48.2 Member Data Documentation

5.48.2.1 [GameObject](#) [] [Crosstales.Common.Util.PlatformController.Objects](#)

Selected objects for the controller.

5.48.2.2 [System.Collections.Generic.List](#)<[Platform](#)> [Crosstales.Common.Util.PlatformController.Platforms](#)

Selected platforms for the controller.

summary>Enable or disable the 'Objects' for the selected 'Platforms' (default: true).


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/Common/↔ Scripts/Util/PlatformController.cs

5.49 Crosstales.RTVoice.Demo.Util.PlatformController Class Reference

Enables or disable game objects for a given platform.

Inheritance diagram for Crosstales.RTVoice.Demo.Util.PlatformController:



Public Member Functions

- override void **Start** ()
- void **OnDestroy** ()

Additional Inherited Members

5.49.1 Detailed Description

Enables or disable game objects for a given platform.


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/RTVoice/↔ Demo/Scripts/Util/PlatformController.cs

5.50 Crosstales.RTVoice.Demo.PreGeneratedAudio Class Reference

[Simple](#) example with pre-generated audio for exact timing.

Inheritance diagram for Crosstales.RTVoice.Demo.PreGeneratedAudio:



Public Member Functions

- void **Start** ()
- void **Update** ()
- void **OnDestroy** ()
- void **Play** ()
- void **Silence** ()
- void **Stop** ()

Public Attributes

- string **SpeechText** = "This is an example with pre-generated audio for exact timing (e.g. animations)."
- bool **PlayOnStart** = false

5.50.1 Detailed Description

[Simple](#) example with pre-generated audio for exact timing.


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/RTVoice/↔ Demo/Scripts/PreGeneratedAudio.cs

5.51 Crosstales.Common.Util.RandomColor Class Reference

Random color changer.

Inheritance diagram for Crosstales.Common.Util.RandomColor:



Public Member Functions

- void **Start** ()
- void **Update** ()

Public Attributes

- Vector2 **ChangeInterval** = new Vector2(5, 15)
- float **Saturation** = 1f
- float **Value** = 1f
- float **Opacity** = 1f
- bool **ChangeMaterial** = false
- Material **Material**
- Vector2 **ColorRange** = new Vector2(0f, 360f)
- bool **GrayScale** = false

5.51.1 Detailed Description

Random color changer.


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/Common/↔ Scripts/Util/RandomColor.cs

5.52 Crosstales.Common.Util.RandomRotator Class Reference

Random rotation changer.

Inheritance diagram for Crosstales.Common.Util.RandomRotator:



Public Member Functions

- void **Start** ()
- void **Update** ()

Public Attributes

- Vector3 **Speed** = new Vector3(15, 15, 15)
- Vector2 **ChangeInterval** = new Vector2(10, 20)

5.52.1 Detailed Description

Random rotation changer.


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/Common/Scripts/Util/RandomRotator.cs

5.53 Crosstales.Common.Util.RandomScaler Class Reference

Random scale changer.

Inheritance diagram for Crosstales.Common.Util.RandomScaler:



Public Member Functions

- void **Start** ()
- void **Update** ()

Public Attributes

- Vector3 **ScaleMin** = new Vector3(0.1f, 0.1f, 0.1f)
- Vector3 **ScaleMax** = new Vector3(3, 3, 3)
- bool **Uniform** = true
- Vector2 **ChangeInterval** = new Vector2(5, 15)

5.53.1 Detailed Description

Random scale changer.

The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/Common/↔ Scripts/Util/RandomScaler.cs

5.54 Crosstales.RTVoice.EditorTask.ReminderCheck Class Reference

Reminds the customer to create an UAS review.

5.54.1 Detailed Description

Reminds the customer to create an UAS review.


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/RTVoice/↔ Editor/Task/ReminderCheck.cs

5.55 Crosstales.RTVoice.EditorIntegration.RTVoiceGameObject Class Reference

Editor component for the "Hierarchy"-menu.

Inheritance diagram for Crosstales.RTVoice.EditorIntegration.RTVoiceGameObject:



5.55.1 Detailed Description


Editor component for the "Hierarchy"-menu.

The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/RTVoice/↔ Editor/Integration/RTVoiceGameObject.cs

5.56 RTVoiceIOSBridge Class Reference

Inheritance diagram for RTVoiceIOSBridge:



Instance Methods

- (void) - [setVoices](#)
- (void) - [speak:text:rate:pitch:volume:](#)
- (void) - [stop](#)

5.56.1 Method Documentation

5.56.1.1 - (void) setVoices

Collects and sends all voices to RTVoice.

5.56.1.2 - (void) speak: (NSString *) name text:(NSString *) text rate:(float) rate pitch:(float) pitch volume:(float) volume

Speaks the string with a given rate, pitch, volume and culture.

Parameters

<i>name</i>	Name of the voice to speak
<i>text</i>	Text to speak
<i>rate</i>	Speech rate of the speaker in percent
<i>pitch</i>	Pitch of the speech in percent
<i>volume</i>	Volume of the speaker in percent

5.56.1.3 - (void) stop


Stops speaking

The documentation for this class was generated from the following files:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/RTVoice/↔ Wrapper/iOS/RTVoiceIOSBridge.h
- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/RTVoice/↔ Wrapper/iOS/RTVoiceIOSBridge.mm

5.57 RTVoiceIOSBridge() Category Reference

Inheritance diagram for RTVoiceIOSBridge():



Properties

- AVSpeechSynthesizer * **synthesizer**

The documentation for this category was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/RTVoice/↔ Wrapper/iOS/RTVoiceIOSBridge.mm

5.58 Crosstales.RTVoice.EditorIntegration.RTVoiceMenu Class Reference

Editor component for the "Tools"-menu.

5.58.1 Detailed Description

Editor component for the "Tools"-menu.


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/RTVoice/↔ Editor/Integration/RTVoiceMenu.cs

5.59 Crosstales.UI.Util.ScrollRectHandler Class Reference

Changes the sensitivity of ScrollRects under various platforms.

Inheritance diagram for Crosstales.UI.Util.ScrollRectHandler:



Public Member Functions

- void **Start** ()

Public Attributes

- ScrollRect **Scroll**

5.59.1 Detailed Description

Changes the sensitivity of ScrollRects under various platforms.


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/Common/UI/Scripts/Util/ScrollRectHandler.cs

5.60 Crosstales.RTVoice.Demo.SendMessage Class Reference

[Simple](#) "SendMessage" example.

Inheritance diagram for Crosstales.RTVoice.Demo.SendMessage:



Public Member Functions

- void **Start** ()
- void **Play** ()
- void **SpeakerA** ()
- IEnumerator **SpeakerB** ()
- void **Silence** ()

Public Attributes

- string **TextA** = "RT-Voice works great with PlayMaker, SALSA, Localized Dialogs/Cutscenes, Dialogue System for Unity and THE Dialogue Engine - that's awesome!"
- string **TextB** = "Absolutely true! RT-Voice is fantastic."
- float **DelayTextB** = 12.2f
- bool **PlayOnStart** = false

5.60.1 Detailed Description

Simple "SendMessage" example.

The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/RTVoice/↔ Demo/Scripts/SendMessage.cs

5.61 Crosstales.RTVoice.Model.Sequence Class Reference

Model for a sequence.

Public Member Functions

- override string **ToString** ()

Public Attributes

- string **Text** = string.Empty
Text to speak.
- string **RTVoiceNameWindows** = string.Empty
Name of the RT-Voice under Windows (optional).
- string **RTVoiceNameMac** = string.Empty
Name of the RT-Voice under macOS (optional).
- string **RTVoiceNameAndroid** = string.Empty
Name of the RT-Voice under Android.
- string **RTVoiceNameIOS** = string.Empty
Name of the RT-Voice under iOS.
- string **RTVoiceNameWSA** = string.Empty
Name of the RT-Voice under WSA.
- Enum.SpeakMode **Mode** = Enum.SpeakMode.Speak
Speak mode (default: 'Speak').
- AudioSource **Source**
AudioSource for the output (optional).
- float **Rate** = 1f
Speech rate of the speaker in percent (1 = 100%, default: 1, optional).
- float **Pitch** = 1f
Speech pitch of the speaker in percent (1 = 100%, default: 1, optional, mobile only).
- float **Volume** = 1f
Volume of the speaker in percent (1 = 100%, default: 1, optional, Windows only).
- bool **initialized** = false

Properties

- string **RTVoiceName** [get]
Returns the name of the RT-Voice for the current platform.

5.61.1 Detailed Description

[Model](#) for a sequence.

5.61.2 Member Data Documentation

5.61.2.1 Enum.SpeakMode Crosstales.RTVoice.Model.Sequence.Mode = Enum.SpeakMode.Speak

Speak mode (default: 'Speak').

5.61.2.2 float Crosstales.RTVoice.Model.Sequence.Pitch = 1f

Speech pitch of the speaker in percent (1 = 100%, default: 1, optional, mobile only).

5.61.2.3 float Crosstales.RTVoice.Model.Sequence.Rate = 1f

Speech rate of the speaker in percent (1 = 100%, default: 1, optional).

5.61.2.4 string Crosstales.RTVoice.Model.Sequence.RTVoiceNameAndroid = string.Empty

Name of the RT-Voice under Android.

5.61.2.5 string Crosstales.RTVoice.Model.Sequence.RTVoiceNameIOS = string.Empty

Name of the RT-Voice under iOS.

5.61.2.6 string Crosstales.RTVoice.Model.Sequence.RTVoiceNameMac = string.Empty

Name of the RT-Voice under macOS (optional).

5.61.2.7 string Crosstales.RTVoice.Model.Sequence.RTVoiceNameWindows = string.Empty

Name of the RT-Voice under Windows (optional).

5.61.2.8 string Crosstales.RTVoice.Model.Sequence.RTVoiceNameWSA = string.Empty

Name of the RT-Voice under WSA.

5.61.2.9 AudioSource Crosstales.RTVoice.Model.Sequence.Source

AudioSource for the output (optional).

5.61.2.10 `string Crosstales.RTVoice.Model.Sequence.Text = string.Empty`

Text to speak.

5.61.2.11 `float Crosstales.RTVoice.Model.Sequence.Volume = 1f`

Volume of the speaker in percent (1 = 100%, default: 1, optional, Windows only).

5.61.3 Property Documentation

5.61.3.1 `string Crosstales.RTVoice.Model.Sequence.RTVoiceName` [get]

Returns the name of the RT-Voice for the current platform.

Returns

The name of the RT-Voice for the current platform.


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/RTVoice/↔ Scripts/Model/Sequence.cs

5.62 Crosstales.RTVoice.Demo.SequenceCaller Class Reference

[Simple](#) Sequence caller example.

Inheritance diagram for Crosstales.RTVoice.Demo.SequenceCaller:



Public Member Functions

- void **Start** ()

Public Attributes

- GameObject **receiver**
- int **NumberOfSequences**
- float **SequenceDelay** = 1f

5.62.1 Detailed Description

[Simple](#) Sequence caller example.


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/RTVoice/↔ Demo/Scripts/SequenceCaller.cs

5.63 Crosstales.RTVoice.Tool.Sequencer Class Reference

Simple sequencer for dialogues.

Inheritance diagram for Crosstales.RTVoice.Tool.Sequencer:



Public Member Functions

- void **Start** ()
- void **OnDestroy** ()
- void **OnValidate** ()
- void [PlaySequence](#) (int index=0)
Plays a Sequence with a given index.
- void [PlayNextSequence](#) ()
Plays the next Sequence in the array.
- void [PlayAllSequences](#) ()
Plays all Sequences.
- void [StopAllSequences](#) ()
Stops and silences all active Sequences.

Public Attributes

- [Model.Sequence](#)[] [Sequences](#)
All available sequences.
- string [Culture](#)
Fallback culture for all sequences (e.g. 'en', optional).
- float [Delay](#) = 0f
Delay in seconds before the [Sequencer](#) starts processing (default: 0).
- bool [PlayOnStart](#) = false
Enable the [Sequencer](#) on start (default: false).

Properties

- string [CurrentCulture](#) [get, set]
Fallback culture for the text (main use is for UI).
- [Model.Sequence](#) [CurrentSequence](#) [get]
Returns the current Sequence.

5.63.1 Detailed Description

Simple sequencer for dialogues.

5.63.2 Member Function Documentation

5.63.2.1 void Crosstales.RTVoice.Tool.Sequencer.PlayAllSequences ()

Plays all Sequences.

5.63.2.2 void Crosstales.RTVoice.Tool.Sequencer.PlayNextSequence ()

Plays the next Sequence in the array.

5.63.2.3 void Crosstales.RTVoice.Tool.Sequencer.PlaySequence (int *index* = 0)

Plays a Sequence with a given index.

Parameters

<i>index</i>	Index of the Sequence (default: 0, optional).
--------------	---

5.63.2.4 void Crosstales.RTVoice.Tool.Sequencer.StopAllSequences ()

Stops and silences all active Sequences.

5.63.3 Member Data Documentation

5.63.3.1 string Crosstales.RTVoice.Tool.Sequencer.Culture

Fallback culture for all sequences (e.g. 'en', optional).

5.63.3.2 float Crosstales.RTVoice.Tool.Sequencer.Delay = 0f

Delay in seconds before the [Sequencer](#) starts processing (default: 0).

5.63.3.3 `bool Crosstales.RTVoice.Tool.Sequencer.PlayOnStart = false`

Enable the [Sequencer](#) on start (default: false).

5.63.3.4 `Model.Sequence [] Crosstales.RTVoice.Tool.Sequencer.Sequences`

All available sequences.

5.63.4 Property Documentation

5.63.4.1 `string Crosstales.RTVoice.Tool.Sequencer.CurrentCulture` `[get]`, `[set]`

Fallback culture for the text (main use is for [UI](#)).

5.63.4.2 `Model.Sequence Crosstales.RTVoice.Tool.Sequencer.CurrentSequence` `[get]`

Returns the current Sequence.

Returns

The current Sequence.


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/RTVoice/↵ Scripts/Tool/Sequencer.cs

5.64 Crosstales.RTVoice.EditorExtension.SequencerEditor Class Reference

Custom editor for the 'Sequencer'-class.

Inheritance diagram for Crosstales.RTVoice.EditorExtension.SequencerEditor:



Public Member Functions

- void **OnEnable** ()
- override void **OnInspectorGUI** ()

5.64.1 Detailed Description

Custom editor for the 'Sequencer'-class.

The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/RTVoice/↔ Editor/Extension/SequencerEditor.cs

5.65 Crosstales.Common.Util.SerializeDeSerialize< T > Class Template Reference

Serialize and deserialize objects to/from binary files.

Public Member Functions

- void **ToFile** (T o, string path)
- MemoryStream **ToMemory** (T o)
- Byte[] **ToByteArray** (T o)
- T **FromFile** (string path)
- T **FromMemory** (Byte[] data)

5.65.1 Detailed Description

Serialize and deserialize objects to/from binary files.

The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/Common/↔ Scripts/Util/SerializeDeSerialize.cs

5.66 Crosstales.RTVoice.EditorTask.SetApiLevel Class Reference

Sets the required API levels.

5.66.1 Detailed Description

Sets the required API levels.


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/RTVoice/↔ Editor/Task/SetApiLevel.cs

5.67 Crosstales.RTVoice.EditorTask.SetupResources Class Reference

Moves all needed resources to 'Editor Default Resources'.

Inheritance diagram for Crosstales.RTVoice.EditorTask.SetupResources:



Additional Inherited Members

5.67.1 Detailed Description

Moves all needed resources to 'Editor Default Resources'.


The documentation for this class was generated from the following file:

- `D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/RTVoice/Editor/Task/SetupResources.cs`

5.68 HutongGames.PlayMaker.Actions.Silence Class Reference

Silence-action for [PlayMaker](#).

Inheritance diagram for HutongGames.PlayMaker.Actions.Silence:



Public Member Functions

- override void **OnEnter** ()

Public Attributes

- FsmEvent **sendEvent**

5.68.1 Detailed Description

Silence-action for [PlayMaker](#).


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/RTVoice/3rd party/PlayMaker/Scripts/Silence.cs

5.69 Crosstales.RTVoice.PlayMaker.SilenceEditor Class Reference

Custom editor for the Silence-action.

Inheritance diagram for Crosstales.RTVoice.PlayMaker.SilenceEditor:



Public Member Functions

- override bool **OnGUI** ()

5.69.1 Detailed Description

Custom editor for the Silence-action.


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/RTVoice/3rd party/PlayMaker/Editor/SilenceEditor.cs

5.70 Crosstales.RTVoice.Demo.Simple Class Reference

[Simple](#) TTS example.

Inheritance diagram for Crosstales.RTVoice.Demo.Simple:



Public Member Functions

- void **Start** ()
- void **OnDestroy** ()
- void **Play** ()
- void **SpeakerA** ()
- void **SpeakerB** ()
- void **Silence** ()

Public Attributes

- AudioSource **SourceA**
- AudioSource **SourceB**
- float **RateSpeakerA** = 1.25f
- float **RateSpeakerB** = 1.75f
- bool **PlayOnStart** = false
- Text **TextSpeakerA**
- Text **TextSpeakerB**
- Text **PhonemeSpeakerA**
- Text **PhonemeSpeakerB**
- Text **VisemeSpeakerA**
- Text **VisemeSpeakerB**

5.70.1 Detailed Description

[Simple](#) TTS example.


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/RTVoice/↔ Demo/Scripts/Simple.cs

5.71 Crosstales.RTVoice.Demo.SimpleNative Class Reference

[Simple](#) native TTS example.

Inheritance diagram for Crosstales.RTVoice.Demo.SimpleNative:



Public Member Functions

- void **Start** ()
- void **OnDestroy** ()
- void **Play** ()
- void **SpeakerA** ()
- void **SpeakerB** ()
- void **SpeakerC** ()
- void **Silence** ()

Public Attributes

- float **RateSpeakerA** = 1.25f
- float **RateSpeakerB** = 1.75f
- float **RateSpeakerC** = 2.5f
- bool **PlayOnStart** = false
- Text **TextSpeakerA**
- Text **TextSpeakerB**
- Text **TextSpeakerC**
- Text **PhonemeSpeakerA**
- Text **PhonemeSpeakerB**
- Text **PhonemeSpeakerC**
- Text **VisemeSpeakerA**
- Text **VisemeSpeakerB**
- Text **VisemeSpeakerC**

5.71.1 Detailed Description

[Simple](#) native TTS example.


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/RTVoice/↔ Demo/Scripts/SimpleNative.cs

5.72 Crosstales.UI.Social Class Reference

[Crosstales](#) social media links.

Inheritance diagram for Crosstales.UI.Social:



Public Member Functions

- void **Facebook** ()
- void **Twitter** ()
- void **LinkedIn** ()
- void **Xing** ()
- void **Youtube** ()

5.72.1 Detailed Description

[Crosstailes](#) social media links.


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstailes/Common/↔ UI/Scripts/Social.cs

5.73 HutongGames.PlayMaker.Actions.Speak Class Reference

Speak-action for [PlayMaker](#).

Inheritance diagram for HutongGames.PlayMaker.Actions.Speak:



Public Member Functions

- override void **OnEnter** ()

Public Attributes

- FsmString **Text** = "Hello world!"
Text to speak.
- FsmString **RTVoiceNameWindows** = "Microsoft David Desktop"
Name of the RT-Voice under Windows.
- FsmString **RTVoiceNameMac** = "Alex"
Name of the RT-Voice under macOS.
- FsmString **RTVoiceNameAndroid** = string.Empty
Name of the RT-Voice under Android.
- FsmString **RTVoiceNameIOS** = "Daniel"
Name of the RT-Voice under iOS.
- FsmString **RTVoiceNameWSA** = "Microsoft David Mobile"
Name of the RT-Voice under WSA.
- FsmString **RTVoiceNameMaryTTS** = "cms-rms-hsmm"
Name of the RT-Voice under MaryTTS.
- FsmString **Culture** = "en"
Fallback culture (e.g. 'en', optional).

Additional Inherited Members

5.73.1 Detailed Description

Speak-action for [PlayMaker](#).

5.73.2 Member Data Documentation

5.73.2.1 FsmString HutongGames.PlayMaker.Actions.Speak.Culture = "en"

Fallback culture (e.g. 'en', optional).

5.73.2.2 FsmString HutongGames.PlayMaker.Actions.Speak.RTVoiceNameAndroid = string.Empty

Name of the RT-Voice under Android.

5.73.2.3 FsmString HutongGames.PlayMaker.Actions.Speak.RTVoiceNameIOS = "Daniel"

Name of the RT-Voice under iOS.

5.73.2.4 FsmString HutongGames.PlayMaker.Actions.Speak.RTVoiceNameMac = "Alex"

Name of the RT-Voice under macOS.

5.73.2.5 FsmString HutongGames.PlayMaker.Actions.Speak.RTVoiceNameMaryTTS = "cms-rms-hsmm"

Name of the RT-Voice under MaryTTS.

5.73.2.6 FsmString HutongGames.PlayMaker.Actions.Speak.RTVoiceNameWindows = "Microsoft David Desktop"

Name of the RT-Voice under Windows.

5.73.2.7 FsmString HutongGames.PlayMaker.Actions.Speak.RTVoiceNameWSA = "Microsoft David Mobile"

Name of the RT-Voice under WSA.

5.73.2.8 FsmString HutongGames.PlayMaker.Actions.Speak.Text = "Hello world!"


Text to speak.

The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstailes/RTVoice/3rd party/PlayMaker/Scripts/Speak.cs ↩

5.74 Crosstales.RTVoice.SALSA.Speak Class Reference

Inheritance diagram for Crosstales.RTVoice.SALSA.Speak:



Public Member Functions

- void **Start** ()
- void **OnDestroy** ()
- void **Talk** ()

Public Attributes


- AudioSource **Source**
- CrazyMinnow.SALSA.Salsa3D **Salsa**
- InputField **EnterText**
- Slider **RateSlider**
- Slider **PitchSlider**

The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/RTVoice/3rd party/SALSA/Scripts/Speak.cs

5.75 Crosstales.RTVoice.SALSA.Speak2D Class Reference

Inheritance diagram for Crosstales.RTVoice.SALSA.Speak2D:



Public Member Functions

- void **Start** ()
- void **OnDestroy** ()
- void **Talk** ()

Public Attributes

- AudioSource **Source**
- CrazyMinnow.SALSA.Salsa2D **Salsa**
- InputField **EnterText**
- Slider **RateSlider**
- Slider **PitchSlider**


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/RTVoice/3rd party/SALSA/Scripts/Speak2D.cs

5.76 HutongGames.PlayMaker.Actions.SpeakBase Class Reference

Base for Speak-actions in [PlayMaker](#).

Inheritance diagram for HutongGames.PlayMaker.Actions.SpeakBase:



Public Member Functions

- override void **OnEnter** ()
- override void **OnExit** ()

Public Attributes

- FsmEvent **sendEvent**
- [Crosstales.RTVoice.Model.Enum.SpeakMode Mode](#)
Speak mode (default: 'Speak').
- FsmGameObject [AudioSource](#)
AudioSource for the output (optional).
- FsmFloat [Rate](#) = 1
Speech rate of the speaker in percent (1 = 100%, default: 1, optional).
- FsmFloat [Pitch](#) = 1f
Speech pitch of the speaker in percent (1 = 100%, default: 1, optional, mobile only).
- FsmFloat [Volume](#) = 1
Volume of the speaker in percent (1 = 100%, default: 1, optional).

Protected Member Functions

- void **subscribeEvents** ()
- void **unsubscribeEvents** ()

Protected Attributes

- string **uid**

5.76.1 Detailed Description

Base for Speak-actions in [PlayMaker](#).

5.76.2 Member Data Documentation

5.76.2.1 FsmGameObject HutongGames.PlayMaker.Actions.SpeakBase.AudioSource

AudioSource for the output (optional).

5.76.2.2 Crosstales.RTVoice.Model.Enum.SpeakMode HutongGames.PlayMaker.Actions.SpeakBase.Mode

[Speak](#) mode (default: '[Speak](#)').

5.76.2.3 FsmFloat HutongGames.PlayMaker.Actions.SpeakBase.Pitch = 1f

Speech pitch of the speaker in percent (1 = 100%, default: 1, optional, mobile only).

5.76.2.4 FsmFloat HutongGames.PlayMaker.Actions.SpeakBase.Rate = 1

Speech rate of the speaker in percent (1 = 100%, default: 1, optional).

5.76.2.5 FsmFloat HutongGames.PlayMaker.Actions.SpeakBase.Volume = 1

Volume of the speaker in percent (1 = 100%, default: 1, optional).


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/RTVoice/3rd party/PlayMaker/Scripts/SpeakBase.cs ↩

5.77 Crosstales.RTVoice.PlayMaker.SpeakEditor Class Reference

Custom editor for the Speak-action.

Inheritance diagram for Crosstales.RTVoice.PlayMaker.SpeakEditor:



Public Member Functions

- override void **OnEnable** ()
- override bool **OnGUI** ()

5.77.1 Detailed Description

Custom editor for the Speak-action.


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/RTVoice/3rd party/PlayMaker/Editor/SpeakEditor.cs

5.78 Crosstales.RTVoice.Speaker Class Reference

Main component of [RTVoice](#).

Inheritance diagram for Crosstales.RTVoice.Speaker:



Public Member Functions

- delegate void **VoicesReady** ()
- delegate void **SpeakStart** ([Model.Wrapper](#) wrapper)
- delegate void **SpeakComplete** ([Model.Wrapper](#) wrapper)
- delegate void **SpeakCurrentWord** ([Model.Wrapper](#) wrapper, string[] speechTextArray, int wordIndex)
- delegate void **SpeakCurrentPhoneme** ([Model.Wrapper](#) wrapper, string phoneme)
- delegate void **SpeakCurrentViseme** ([Model.Wrapper](#) wrapper, string viseme)
- delegate void **SpeakAudioGenerationStart** ([Model.Wrapper](#) wrapper)
- delegate void **SpeakAudioGenerationComplete** ([Model.Wrapper](#) wrapper)
- delegate void **ProviderChange** (string provider)
- delegate void **ErrorInfo** ([Model.Wrapper](#) wrapper, string info)
- void **OnEnable** ()
- void **Update** ()
- void **OnDisable** ()
- void **OnDestroy** ()
- void **OnApplicationQuit** ()
- void **OnApplicationFocus** (bool hasFocus)

Static Public Member Functions

- static float [ApproximateSpeechLength](#) (string text, float rate=1f, float wordsPerMinute=175f, float time↔Factor=0.9f)
Approximates the speech length in seconds of a given text and rate. Note: This is an experimental method and doesn't provide an exact value; +/- 15% is "normal"!
- static bool [isVoiceForCultureAvailable](#) (string culture)
Is a voice available for a given culture from the current TTS-system?
- static System.Collections.Generic.List< [Model.Voice](#) > [VoicesForCulture](#) (string culture)
Get all available voices for a given culture from the current TTS-system.
- static [Model.Voice](#) [VoiceForCulture](#) (string culture, int index=0, string fallbackCulture="")
Get a voice from for a given culture and otional index from the current TTS-system.
- static bool [isVoiceForNameAvailable](#) (string name)
Is a voice available for a given name from the current TTS-system?
- static [Model.Voice](#) [VoiceForName](#) (string name)
Get a voice for a given name from the current TTS-system.
- static string [SpeakNative](#) (string text, [Model.Voice](#) voice=null, float rate=1f, float pitch=1f, float volume=1f)
Speaks a text with a given voice (native mode).
- static void [SpeakNativeWithUID](#) ([Model.Wrapper](#) wrapper)
Speaks a text with a given voice (native mode).
- static string [SpeakNative](#) ([Model.Wrapper](#) wrapper)
Speaks a text with a given wrapper (native mode).
- static string [Speak](#) (string text, AudioSource source=null, [Model.Voice](#) voice=null, bool speak↔Immediately=true, float rate=1f, float pitch=1f, float volume=1f, string outputFile="")
Speaks a text with a given voice.
- static void [SpeakWithUID](#) ([Model.Wrapper](#) wrapper)
Speaks a text with a given voice.
- static string [Speak](#) ([Model.Wrapper](#) wrapper)
Speaks a text with a given wrapper.
- static void [SpeakMarkedWordsWithUID](#) ([Model.Wrapper](#) wrapper)
Speaks and marks a text with a given wrapper.
- static void [SpeakMarkedWordsWithUID](#) (string uid, string text, AudioSource source, [Model.Voice](#) voice=null, float rate=1f, float pitch=1f)
Speaks and marks a text with a given voice and tracks the word position.
- static string [Generate](#) ([Model.Wrapper](#) wrapper)
Generates an audio file from a given wrapper.
- static string [Generate](#) (string text, string outputFile, [Model.Voice](#) voice=null, float rate=1f, float pitch=1f, float volume=1f)
Generates an audio file from a text with a given voice.
- static void [Silence](#) ()
Silence all active TTS-voices.
- static void [Silence](#) (string uid)
Silence an active TTS-voice with a UID.
- static void [ReloadProvider](#) ()

Public Attributes

- bool [MaryTTSMode](#) = false
Enables or disables MaryTTS (default: false).
- string [MaryTTSUrl](#) = "http://mary.dfki.de"
Server URL for MaryTTS.
- int [MaryTTSPort](#) = 59125
Server port for MaryTTS (default: 59125).
- string [MaryTTSUser](#) = string.Empty
User name for MaryTTS (default: empty).
- string [MaryTTSPassword](#) = string.Empty
User password for MaryTTS (default: empty).
- [Model.Enum.MaryTTSType](#) [MaryTTSType](#) = Model.Enum.MaryTTSType.RAWMARYXML
Input type for MaryTTS (default: MaryTTSType.RAWMARYXML).
- bool [AutoClearTags](#) = false
Automatically clear tags from speeches depending on the capabilities of the current TTS-system (default: false).
- bool [SilenceOnDisable](#) = false
Silence any speeches if this component gets disabled (default: false).
- bool [SilenceOnFocusLost](#) = true
Silence any speeches if the application loses the focus (default: true).
- bool [DontDestroy](#) = true
Don't destroy gameobject during scene switches (default: true).

Properties

- static VoicesReady [OnVoicesReady](#)
An event triggered whenever the voices of a provider are ready.
- static SpeakStart [OnSpeakStart](#)
An event triggered whenever a speak is started.
- static SpeakComplete [OnSpeakComplete](#)
An event triggered whenever a speak is completed.
- static SpeakCurrentWord [OnSpeakCurrentWord](#)
An event triggered whenever a new word is spoken (native, Windows and iOS only).
- static SpeakCurrentPhoneme [OnSpeakCurrentPhoneme](#)
An event triggered whenever a new phoneme is spoken (native, Windows only).
- static SpeakCurrentViseme [OnSpeakCurrentViseme](#)
An event triggered whenever a new viseme is spoken (native, Windows only).
- static SpeakAudioGenerationStart [OnSpeakAudioGenerationStart](#)
An event triggered whenever a speak audio generation is started.
- static SpeakAudioGenerationComplete [OnSpeakAudioGenerationComplete](#)
An event triggered whenever a speak audio generation is completed.
- static ProviderChange [OnProviderChange](#)
An event triggered whenever a provider changes (e.g. Windows to MaryTTS).
- static ErrorInfo [OnErrorInfo](#)
An event triggered whenever an error occurs.
- static bool [isMaryMode](#) [get, set]
Enables or disables MaryTTS.
- static string [MaryUrl](#) [get, set]
Server URL for MaryTTS.
- static int [MaryPort](#) [get, set]

- Server port for MaryTTS.*
- static string [MaryUser](#) [get, set]
- User name for MaryTTS.*
- static string [MaryPassword](#) [set]
- Password for MaryTTS.*
- static [Model.Enum.MaryTTSType](#) [MaryType](#) [set]
- > Input type for MaryTTS.*
- static bool [isAutoClearTags](#) [get, set]
- Automatically clear tags from speeches depending on the capabilities of the current TTS-system.*
- static bool [isSilenceOnDisable](#) [get, set]
- Silence any speeches if this component gets disabled.*
- static bool [isSilenceOnFocusLost](#) [get, set]
- Silence any speeches if the application loses the focus.*
- static string [AudioFileExtension](#) [get]
- Returns the extension of the generated audio files.*
- static System.Collections.Generic.List< [Model.Voice](#) > [Voices](#) [get]
- Get all available voices from the current TTS-system.*
- static System.Collections.Generic.List< string > [Cultures](#) [get]
- Get all available cultures from the current TTS-system..*
- static bool [isTTSAvailable](#) [get]
- Checks if TTS is available on this system.*
- static bool [isSpeaking](#) [get]
- Checks if RT-Voice is speaking on this system.*

5.78.1 Detailed Description

Main component of [RTVoice](#).

5.78.2 Member Function Documentation

5.78.2.1 static float [Crosstales.RTVoice.Speaker.ApproximateSpeechLength](#) (string *text*, float *rate* = 1f, float *wordsPerMinute* = 175f, float *timeFactor* = 0.9f) [static]

Approximates the speech length in seconds of a given text and rate. Note: This is an experimental method and doesn't provide an exact value; +/- 15% is "normal"!

Parameters

<i>text</i>	Text for the length approximation.
<i>rate</i>	Speech rate of the speaker in percent for the length approximation (1 = 100%, default: 1, optional).
<i>wordsPerMinute</i>	Words per minute (default: 175, optional).
<i>timeFactor</i>	Time factor for the calculated value (default: 0.9, optional).

Returns

Approximated speech length in seconds of the given text and rate.

5.78.2.2 static string Crosstales.RTVoice.Speaker.Generate (Model.Wrapper wrapper) [static]

Generates an audio file from a given wrapper.

Parameters

<i>wrapper</i>	Speak wrapper.
----------------	----------------

Returns

UID of the generator.

5.78.2.3 static string Crosstales.RTVoice.Speaker.Generate (string text, string outputFile, Model.Voice voice = null, float rate = 1f, float pitch = 1f, float volume = 1f) [static]

Generates an audio file from a text with a given voice.

Parameters

<i>text</i>	Text to generate.
<i>outputFile</i>	Saves the generated audio to an output file (without extension).
<i>voice</i>	Voice to speak (optional).
<i>rate</i>	Speech rate of the speaker in percent (1 = 100%, values: 0-3, default: 1, optional).
<i>pitch</i>	Pitch of the speech in percent (1 = 100%, values: 0-2, default: 1, optional).
<i>volume</i>	Volume of the speaker in percent (1 = 100%, values: 0-1, default: 1, optional).

Returns

UID of the generator.

5.78.2.4 static bool Crosstales.RTVoice.Speaker.isVoiceForCultureAvailable (string culture) [static]

Is a voice available for a given culture from the current TTS-system?

Parameters

<i>culture</i>	Culture of the voice (e.g. "en")
----------------	----------------------------------

Returns

True if a voice is available for a given culture.

5.78.2.5 static bool Crosstales.RTVoice.Speaker.isVoiceForNameAvailable (string name) [static]

Is a voice available for a given name from the current TTS-system?

Parameters

<i>name</i>	Name of the voice (e.g. "Alex")
-------------	---------------------------------

Returns

True if a voice is available for a given culture.

5.78.2.6 `static void Crosstales.RTVoice.Speaker.Silence () [static]`

Silence all active TTS-voices.

5.78.2.7 `static void Crosstales.RTVoice.Speaker.Silence (string uid) [static]`

Silence an active TTS-voice with a UID.

Parameters

<i>uid</i>	UID of the speaker
------------	--------------------

5.78.2.8 `static string Crosstales.RTVoice.Speaker.Speak (string text, AudioSource source = null, Model.Voice voice = null, bool speakImmediately = true, float rate = 1f, float pitch = 1f, float volume = 1f, string outputFile = " ") [static]`

Speaks a text with a given voice.

Parameters

<i>text</i>	Text to speak.
<i>source</i>	AudioSource for the output (optional).
<i>voice</i>	Voice to speak (optional).
<i>speakImmediately</i>	Speak the text immediately (default: true). Only works if 'Source' is not null.
<i>rate</i>	Speech rate of the speaker in percent (1 = 100%, values: 0-3, default: 1, optional).
<i>pitch</i>	Pitch of the speech in percent (1 = 100%, values: 0-2, default: 1, optional).
<i>volume</i>	Volume of the speaker in percent (1 = 100%, values: 0-1, default: 1, optional).
<i>outputFile</i>	Saves the generated audio to an output file (without extension, optional).

Returns

UID of the speaker.

5.78.2.9 `static string Crosstales.RTVoice.Speaker.Speak (Model.Wrapper wrapper) [static]`

Speaks a text with a given wrapper.

Parameters

<i>wrapper</i>	Speak wrapper.
----------------	----------------

Returns

UID of the speaker.

5.78.2.10 `static void Crosstales.RTVoice.Speaker.SpeakMarkedWordsWithUID (Model.Wrapper wrapper)` `[static]`

Speaks and marks a text with a given wrapper.

Parameters

<i>wrapper</i>	Speak wrapper.
----------------	----------------

5.78.2.11 `static void Crosstales.RTVoice.Speaker.SpeakMarkedWordsWithUID (string uid, string text, AudioSource source, Model.Voice voice = null, float rate = 1f, float pitch = 1f)` `[static]`

Speaks and marks a text with a given voice and tracks the word position.

Parameters

<i>uid</i>	UID of the speaker
<i>text</i>	Text to speak.
<i>source</i>	AudioSource for the output.
<i>voice</i>	Voice to speak (optional).
<i>rate</i>	Speech rate of the speaker in percent (1 = 100%, values: 0-3, default: 1, optional).
<i>pitch</i>	Pitch of the speech in percent (1 = 100%, values: 0-2, default: 1, optional).

5.78.2.12 `static string Crosstales.RTVoice.Speaker.SpeakNative (string text, Model.Voice voice = null, float rate = 1f, float pitch = 1f, float volume = 1f)` `[static]`

Speaks a text with a given voice (native mode).

Parameters

<i>text</i>	Text to speak.
<i>voice</i>	Voice to speak (optional).
<i>rate</i>	Speech rate of the speaker in percent (1 = 100%, values: 0-3, default: 1, optional).
<i>pitch</i>	Pitch of the speech in percent (1 = 100%, values: 0-2, default: 1, optional).
<i>volume</i>	Volume of the speaker in percent (1 = 100%, values: 0-1, default: 1, optional).

Returns

UID of the speaker.

5.78.2.13 `static string Crosstales.RTVoice.Speaker.SpeakNative (Model.Wrapper wrapper) [static]`

Speaks a text with a given wrapper (native mode).

Parameters

<i>wrapper</i>	Speak wrapper.
----------------	----------------

Returns

UID of the speaker.

5.78.2.14 `static void Crosstales.RTVoice.Speaker.SpeakNativeWithUID (Model.Wrapper wrapper) [static]`

Speaks a text with a given voice (native mode).

Parameters

<i>wrapper</i>	Speak wrapper.
----------------	----------------

5.78.2.15 `static void Crosstales.RTVoice.Speaker.SpeakWithUID (Model.Wrapper wrapper) [static]`

Speaks a text with a given voice.

Parameters

<i>wrapper</i>	Speak wrapper.
----------------	----------------

5.78.2.16 `static Model.Voice Crosstales.RTVoice.Speaker.VoiceForCulture (string culture, int index = 0, string fallbackCulture = " ") [static]`

Get a voice from for a given culture and otional index from the current TTS-system.

Parameters

<i>culture</i>	Culture of the voice (e.g. "en_US")
<i>index</i>	Index of the voice (default: 0, optional)
<i>index</i>	Fallback culture of the voice (e.g. "en", default "", optional)

Returns

Voice for the given culture and index.

5.78.2.17 static Model.Voice Crosstales.RTVoice.Speaker.VoiceForName (string *name*) [static]

Get a voice for a given name from the current TTS-system.

Parameters

<i>name</i>	Name of the voice (e.g. "Alex")
-------------	---------------------------------

Returns

Voice for the given name or null if not found.

5.78.2.18 static System.Collections.Generic.List<Model.Voice> Crosstales.RTVoice.Speaker.VoicesForCulture (string *culture*) [static]

Get all available voices for a given culture from the current TTS-system.

Parameters

<i>culture</i>	Culture of the voice (e.g. "en")
----------------	----------------------------------

Returns

All available voices (alphabetically ordered by 'Name') for a given culture as a list.

5.78.3 Member Data Documentation**5.78.3.1 bool Crosstales.RTVoice.Speaker.AutoClearTags = false**

Automatically clear tags from speeches depending on the capabilities of the current TTS-system (default: false).

5.78.3.2 bool Crosstales.RTVoice.Speaker.DontDestroy = true

Don't destroy gameobject during scene switches (default: true).

5.78.3.3 bool Crosstales.RTVoice.Speaker.MaryTTSMode = false

Enables or disables MaryTTS (default: false).

5.78.3.4 `string Crosstales.RTVoice.Speaker.MaryTTSPassword = string.Empty`

User password for MaryTTS (default: empty).

5.78.3.5 `int Crosstales.RTVoice.Speaker.MaryTTSPort = 59125`

Server port for MaryTTS (default: 59125).

5.78.3.6 `Model.Enum.MaryTTSType Crosstales.RTVoice.Speaker.MaryTTSType = Model.Enum.MaryTTSType.RAWMARYXML` ↩

Input type for MaryTTS (default: MaryTTSType.RAWMARYXML).

5.78.3.7 `string Crosstales.RTVoice.Speaker.MaryTTSUrl = "http://mary.dfki.de"`

Server URL for MaryTTS.

5.78.3.8 `string Crosstales.RTVoice.Speaker.MaryTTSUser = string.Empty`

User name for MaryTTS (default: empty).

5.78.3.9 `bool Crosstales.RTVoice.Speaker.SilenceOnDisable = false`

Silence any speeches if this component gets disabled (default: false).

5.78.3.10 `bool Crosstales.RTVoice.Speaker.SilenceOnFocustLost = true`

Silence any speeches if the application loses the focus (default: true).

5.78.4 Property Documentation

5.78.4.1 `string Crosstales.RTVoice.Speaker.AudioFileExtension` [static], [get]

Returns the extension of the generated audio files.

Returns

Extension of the generated audio files.

5.78.4.2 `System.Collections.Generic.List<string> Crosstales.RTVoice.Speaker.Cultures` `[static], [get]`

Get all available cultures from the current TTS-system..

Returns

All available cultures (alphabetically ordered by 'Culture') as a list.

5.78.4.3 `bool Crosstales.RTVoice.Speaker.isAutoClearTags` `[static], [get], [set]`

Automatically clear tags from speeches depending on the capabilities of the current TTS-system.

5.78.4.4 `bool Crosstales.RTVoice.Speaker.isMaryMode` `[static], [get], [set]`

Enables or disables MaryTTS.

5.78.4.5 `bool Crosstales.RTVoice.Speaker.isSilenceOnDisable` `[static], [get], [set]`

Silence any speeches if this component gets disabled.

5.78.4.6 `bool Crosstales.RTVoice.Speaker.isSilenceOnFocustLost` `[static], [get], [set]`

Silence any speeches if the application loses the focus.

5.78.4.7 `bool Crosstales.RTVoice.Speaker.isSpeaking` `[static], [get]`

Checks if RT-Voice is speaking on this system.

Returns

True if RT-Voice is speaking on this system.

5.78.4.8 `bool Crosstales.RTVoice.Speaker.isTTSAvailable` `[static], [get]`

Checks if TTS is available on this system.

Returns

True if TTS is available on this system.

5.78.4.9 `string Crosstales.RTVoice.Speaker.MaryPassword` `[static], [set]`

Password for MaryTTS.

5.78.4.10 `int Crosstales.RTVoice.Speaker.MaryPort` `[static], [get], [set]`

Server port for MaryTTS.

5.78.4.11 `Model.Enum.MaryTTSType Crosstales.RTVoice.Speaker.MaryType` `[static], [set]`

>Input type for MaryTTS.

5.78.4.12 `string Crosstales.RTVoice.Speaker.MaryUrl` `[static], [get], [set]`

Server URL for MaryTTS.

5.78.4.13 `string Crosstales.RTVoice.Speaker.MaryUser` `[static], [get], [set]`

User name for MaryTTS.

5.78.4.14 `ErrorInfo Crosstales.RTVoice.Speaker.OnErrorInfo` `[static], [add], [remove]`

An event triggered whenever an error occurs.

5.78.4.15 `ProviderChange Crosstales.RTVoice.Speaker.OnProviderChange` `[static], [add], [remove]`

An event triggered whenever a provider changes (e.g. Windows to MaryTTS).

5.78.4.16 `SpeakAudioGenerationComplete Crosstales.RTVoice.Speaker.OnSpeakAudioGenerationComplete` `[static], [add], [remove]`

An event triggered whenever a speak audio generation is completed.

5.78.4.17 `SpeakAudioGenerationStart Crosstales.RTVoice.Speaker.OnSpeakAudioGenerationStart` `[static], [add], [remove]`

An event triggered whenever a speak audio generation is started.

5.78.4.18 `SpeakComplete Crosstales.RTVoice.Speaker.OnSpeakComplete` `[static], [add], [remove]`

An event triggered whenever a speak is completed.

5.78.4.19 `SpeakCurrentPhoneme Crosstales.RTVoice.Speaker.OnSpeakCurrentPhoneme` `[static], [add], [remove]`

An event triggered whenever a new phoneme is spoken (native, Windows only).

5.78.4.20 SpeakCurrentViseme `Crosstales.RTVoice.Speaker.OnSpeakCurrentViseme` `[static], [add], [remove]`

An event triggered whenever a new viseme is spoken (native, Windows only).

5.78.4.21 SpeakCurrentWord `Crosstales.RTVoice.Speaker.OnSpeakCurrentWord` `[static], [add], [remove]`

An event triggered whenever a new word is spoken (native, Windows and iOS only).

5.78.4.22 SpeakStart `Crosstales.RTVoice.Speaker.OnSpeakStart` `[static], [add], [remove]`

An event triggered whenever a speak is started.

5.78.4.23 VoicesReady `Crosstales.RTVoice.Speaker.OnVoicesReady` `[static], [add], [remove]`

An event triggered whenever the voices of a provider are ready.

5.78.4.24 System.Collections.Generic.List<Model.Voice> `Crosstales.RTVoice.Speaker.Voices` `[static], [get]`

Get all available voices from the current TTS-system.

Returns

All available voices (alphabetically ordered by 'Name') as a list.


The documentation for this class was generated from the following file:

- `D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/RTVoice/Scripts/Speaker.cs`

5.79 Crosstales.RTVoice.EditorExtension.SpeakerEditor Class Reference

Custom editor for the '[Speaker](#)'-class.

Inheritance diagram for `Crosstales.RTVoice.EditorExtension.SpeakerEditor`:



Public Member Functions

- void **OnEnable** ()
- void **OnDisable** ()
- override void **OnInspectorGUI** ()

5.79.1 Detailed Description


Custom editor for the '[Speaker](#)'-class.

The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/RTVoice/Editor/Extension/SpeakerEditor.cs

5.80 Crosstales.RTVoice.SALSA.SpeakSimple Class Reference

Inheritance diagram for Crosstales.RTVoice.SALSA.SpeakSimple:



Public Member Functions

- void **Silence** ()
- void **Talk** ()

Public Attributes

- AudioSource **Source**
- InputField **EnterText**
- Slider **RateSlider**
- Slider **PitchSlider**


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/RTVoice/3rd party/SALSA/Scripts/SpeakSimple.cs

5.81 HutongGames.PlayMaker.Actions.SpeakUI Class Reference

Speak-action for UI-components in [PlayMaker](#).

Inheritance diagram for HutongGames.PlayMaker.Actions.SpeakUI:



Public Member Functions

- override void **OnEnter** ()

Public Attributes

- InputField **Text**
Text to speak.
- InputField **RTVoiceName**
Name of the RT-Voice.
- FsmString **Culture** = "en"
Fallback culture (e.g. 'en', optional).

Additional Inherited Members

5.81.1 Detailed Description

Speak-action for UI-components in [PlayMaker](#).

5.81.2 Member Data Documentation

5.81.2.1 FsmString HutongGames.PlayMaker.Actions.SpeakUI.Culture = "en"

Fallback culture (e.g. 'en', optional).

5.81.2.2 InputField HutongGames.PlayMaker.Actions.SpeakUI.RTVoiceName

Name of the RT-Voice.

5.81.2.3 InputField HutongGames.PlayMaker.Actions.SpeakUI.Text

Text to speak.


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/RTVoice/3rd party/PlayMaker/Scripts/SpeakUI.cs

5.82 Crosstales.RTVoice.PlayMaker.SpeakUIEditor Class Reference

Custom editor for the SpeakUI-action.

Inheritance diagram for Crosstales.RTVoice.PlayMaker.SpeakUIEditor:



Public Member Functions

- override void **OnEnable** ()
- override bool **OnGUI** ()

5.82.1 Detailed Description

Custom editor for the SpeakUI-action.


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/RTVoice/3rd party/PlayMaker/Editor/SpeakUIEditor.cs

5.83 Crosstales.RTVoice.Demo.SpeakWrapper Class Reference

Wrapper for the dynamic speakers.

Inheritance diagram for Crosstales.RTVoice.Demo.SpeakWrapper:



Public Member Functions

- void **Start** ()
- void **Speak** ()

Public Attributes

- **Voice SpeakerVoice**
- InputField **Input**
- Text **Label**
- AudioSource **Audio**

5.83.1 Detailed Description

Wrapper for the dynamic speakers.


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/RTVoice/Demo/Scripts/SpeakWrapper.cs

5.84 Crosstales.DJ.Demo.Util.SpectrumVisualizer Class Reference

Simple spectrum visualizer.

Inheritance diagram for Crosstales.DJ.Demo.Util.SpectrumVisualizer:



Public Member Functions

- void **Start** ()
- void **Update** ()

Public Attributes

- [FFTAnalyzer](#) **Analyzer**
- GameObject **VisualPrefab**
- float **Width** = 0.075f
- float **Gain** = 70f
- bool **LeftToRight** = true
- float **Opacity** = 1f

5.84.1 Detailed Description

Simple spectrum visualizer.


The documentation for this class was generated from the following file:

- `D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/Common/Scripts/Util/SpectrumVisualizer.cs`

5.85 Crosstales.RTVoice.Tool.SpeechText Class Reference

Allows to speak and store generated audio.

Inheritance diagram for Crosstales.RTVoice.Tool.SpeechText:



Public Member Functions

- void **Start** ()
- void **OnDestroy** ()
- void **OnValidate** ()
- void **Speak** ()
Speak the text.
- void **Silence** ()
Silence the speech.

Public Attributes

- string **Text** = string.Empty
Text to speak.
- string **RTVoiceNameWindows** = "Microsoft David Desktop"
Name of the RT-Voice under Windows (optional).
- string **RTVoiceNameMac** = "Alex"
Name of the RT-Voice under macOS (optional).
- string **RTVoiceNameAndroid** = string.Empty
Name of the RT-Voice under Android.
- string **RTVoiceNameIOS** = "Daniel"
Name of the RT-Voice under iOS.
- string **RTVoiceNameWSA** = "Microsoft David Mobile"
Name of the RT-Voice under WSA.
- string **RTVoiceNameMaryTTS** = "cmu-rms-hsmm"
Name of the RT-Voice under MaryTTS.
- **Model.Enum.SpeakMode Mode** = Model.Enum.SpeakMode.Speak
Speak mode (default: 'Speak').
- string **Culture** = "en"
Fallback culture for the text (e.g. 'en', optional).
- AudioSource **Source**
AudioSource for the output (optional).
- float **Rate** = 1f
Speech rate of the speaker in percent (1 = 100%, default: 1, optional).
- float **Pitch** = 1f
Speech pitch of the speaker in percent (1 = 100%, default: 1, optional, mobile only).
- float **Volume** = 1f
Volume of the speaker in percent (1 = 100%, default: 1, optional, Windows only).
- bool **PlayOnStart** = false
Enable speaking of the text on start (default: false).
- float **Delay** = 0f
Delay until the speech for this text starts (default: 0).
- bool **GenerateAudioFile** = false
Generate audio file on/off (default: false).
- string **FilePath** = @"_generatedAudio/"
File path for the generated audio.
- string **FileName** = "Speech01"
File name of the generated audio.
- bool **FileInsideAssets** = true
Is the generated file path inside the Assets-folder (current project)? If this option is enabled, it prefixes the path with 'Application.dataPath'.

Properties

- string `CurrentText` [get, set]
Text to speak (main use is for UI).
- string `CurrentCulture` [get, set]
Fallback culture for the text (main use is for UI).
- float `CurrentRate` [get, set]
Speech rate of the speaker in percent (main use is for UI).
- float `CurrentPitch` [get, set]
Speech pitch of the speaker in percent (main use is for UI).
- float `CurrentVolume` [get, set]
Volume of the speaker in percent (main use is for UI).
- string `RTVoiceName` [get]
Returns the name of the RT-Voice for the current platform.

5.85.1 Detailed Description

Allows to speak and store generated audio.

5.85.2 Member Function Documentation

5.85.2.1 void Crosstales.RTVoice.Tool.SpeechText.Silence ()

Silence the speech.

5.85.2.2 void Crosstales.RTVoice.Tool.SpeechText.Speak ()

Speak the text.

5.85.3 Member Data Documentation

5.85.3.1 string Crosstales.RTVoice.Tool.SpeechText.Culture = "en"

Fallback culture for the text (e.g. 'en', optional).

5.85.3.2 float Crosstales.RTVoice.Tool.SpeechText.Delay = 0f

Delay until the speech for this text starts (default: 0).

5.85.3.3 bool Crosstales.RTVoice.Tool.SpeechText.FileInsideAssets = true

Is the generated file path inside the Assets-folder (current project)? If this option is enabled, it prefixes the path with 'Application.dataPath'.

5.85.3.4 `string Crosstales.RTVoice.Tool.SpeechText.FileName = "Speech01"`

File name of the generated audio.

5.85.3.5 `string Crosstales.RTVoice.Tool.SpeechText.FilePath = @"_generatedAudio/"`

File path for the generated audio.

5.85.3.6 `bool Crosstales.RTVoice.Tool.SpeechText.GenerateAudioFile = false`

Generate audio file on/off (default: false).

5.85.3.7 `Model.Enum.SpeakMode Crosstales.RTVoice.Tool.SpeechText.Mode = Model.Enum.SpeakMode.Speak`

Speak mode (default: 'Speak').

5.85.3.8 `float Crosstales.RTVoice.Tool.SpeechText.Pitch = 1f`

Speech pitch of the speaker in percent (1 = 100%, default: 1, optional, mobile only).

5.85.3.9 `bool Crosstales.RTVoice.Tool.SpeechText.PlayOnStart = false`

Enable speaking of the text on start (default: false).

5.85.3.10 `float Crosstales.RTVoice.Tool.SpeechText.Rate = 1f`

Speech rate of the speaker in percent (1 = 100%, default: 1, optional).

5.85.3.11 `string Crosstales.RTVoice.Tool.SpeechText.RTVoiceNameAndroid = string.Empty`

Name of the RT-Voice under Android.

5.85.3.12 `string Crosstales.RTVoice.Tool.SpeechText.RTVoiceNameIOS = "Daniel"`

Name of the RT-Voice under iOS.

5.85.3.13 `string Crosstales.RTVoice.Tool.SpeechText.RTVoiceNameMac = "Alex"`

Name of the RT-Voice under macOS (optional).

5.85.3.14 `string Crosstales.RTVoice.Tool.SpeechText.RTVoiceNameMaryTTS = "cmu-rms-hsmm"`

Name of the RT-Voice under MaryTTS.

5.85.3.15 `string Crosstales.RTVoice.Tool.SpeechText.RTVoiceNameWindows = "Microsoft David Desktop"`

Name of the RT-Voice under Windows (optional).

5.85.3.16 `string Crosstales.RTVoice.Tool.SpeechText.RTVoiceNameWSA = "Microsoft David Mobile"`

Name of the RT-Voice under WSA.

5.85.3.17 `AudioSource Crosstales.RTVoice.Tool.SpeechText.Source`

AudioSource for the output (optional).

5.85.3.18 `string Crosstales.RTVoice.Tool.SpeechText.Text = string.Empty`

Text to speak.

5.85.3.19 `float Crosstales.RTVoice.Tool.SpeechText.Volume = 1f`

Volume of the speaker in percent (1 = 100%, default: 1, optional, Windows only).

5.85.4 Property Documentation

5.85.4.1 `string Crosstales.RTVoice.Tool.SpeechText.CurrentCulture` `[get]`, `[set]`

Fallback culture for the text (main use is for [UI](#)).

5.85.4.2 `float Crosstales.RTVoice.Tool.SpeechText.CurrentPitch` `[get]`, `[set]`

Speech pitch of the speaker in percent (main use is for [UI](#)).

5.85.4.3 `float Crosstales.RTVoice.Tool.SpeechText.CurrentRate` `[get]`, `[set]`

Speech rate of the speaker in percent (main use is for [UI](#)).

5.85.4.4 `string Crosstales.RTVoice.Tool.SpeechText.CurrentText` `[get]`, `[set]`

Text to speak (main use is for [UI](#)).

5.85.4.5 float `Crosstales.RTVoice.Tool.SpeechText.CurrentVolume` `[get]`, `[set]`

Volume of the speaker in percent (main use is for [UI](#)).

5.85.4.6 string `Crosstales.RTVoice.Tool.SpeechText.RTVoiceName` `[get]`

Returns the name of the RT-Voice for the current platform.

Returns

The name of the RT-Voice for the current platform.


The documentation for this class was generated from the following file:

- `D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/RTVoice/↔ Scripts/Tool/SpeechText.cs`

5.86 Crosstales.RTVoice.EditorExtension.SpeechTextEditor Class Reference

Custom editor for the 'SpeechText'-class.

Inheritance diagram for `Crosstales.RTVoice.EditorExtension.SpeechTextEditor`:



Public Member Functions

- void **OnEnable** ()
- void **OnDisable** ()
- override void **OnInspectorGUI** ()

5.86.1 Detailed Description

Custom editor for the 'SpeechText'-class.


The documentation for this class was generated from the following file:

- `D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/RTVoice/↔ Editor/Extension/SpeechTextEditor.cs`

5.87 Crosstales.UI.StaticManager Class Reference

Static Button Manager.

Inheritance diagram for Crosstales.UI.StaticManager:



Public Member Functions

- void **Quit** ()
- void **OpenCrosstales** ()
- void **OpenAssetstore** ()

Public Attributes

- string **AssetstoreURL** = "https://goo.gl/qwtXyb"

5.87.1 Detailed Description

Static Button Manager.

The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/Common/↔ UI/Scripts/StaticManager.cs

5.88 Crosstales.RTVoice.EditorTask.Telemetry Class Reference

Gather some telemetry data for the asset.

5.88.1 Detailed Description

Gather some telemetry data for the asset.


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/RTVoice/↔ Editor/Task/Telemetry.cs

5.89 Crosstales.RTVoice.Tool.TextFileSpeaker Class Reference

Allows to speak text files.

Inheritance diagram for Crosstales.RTVoice.Tool.TextFileSpeaker:



Public Member Functions

- void **Start** ()
- void **OnDestroy** ()
- void **OnValidate** ()
- void **Speak** ()
Speaks a random text.
- string **SpeakText** (int index=-1)
Speaks a text with an optional index.
- void **Silence** ()
Silence the speech.

Public Attributes

- TextAsset[] **TextFiles**
Text files to speak.
- string **RTVoiceNameWindows** = "Microsoft David Desktop"
Name of the RT-Voice under Windows (optional).
- string **RTVoiceNameMac** = "Alex"
Name of the RT-Voice under macOS (optional).
- string **RTVoiceNameAndroid** = string.Empty
Name of the RT-Voice under Android.
- string **RTVoiceNameIOS** = "Daniel"
Name of the RT-Voice under iOS.
- string **RTVoiceNameWSA** = "Microsoft David Mobile"
Name of the RT-Voice under WSA.
- string **RTVoiceNameMaryTTS** = "cmu-rms-hsmm"
Name of the RT-Voice under MaryTTS.
- **Model.Enum.SpeakMode Mode** = Model.Enum.SpeakMode.Speak
Speak mode (default: 'Speak').
- bool **PlayOnStart** = false
Enable speaking of a random text file on start (default: false).
- float **Delay** = 0f
Delay until the speech for this text starts (default: 0).
- string **Culture** = "en"
Fallback culture for the text (e.g. 'en', optional).
- AudioSource **Source**

- *AudioSource for the output (optional).*
- float **Rate** = 1f
Speech rate of the speaker in percent (1 = 100%, default: 1, optional).
- float **Pitch** = 1f
Speech pitch of the speaker in percent (1 = 100%, default: 1, optional, mobile only).
- float **Volume** = 1f
Volume of the speaker in percent (1 = 100%, default: 1, optional, Windows only).

Properties

- string **CurrentCulture** [get, set]
Fallback culture for the text (main use is for UI).
- float **CurrentRate** [get, set]
Speech rate of the speaker in percent (main use is for UI).
- float **CurrentPitch** [get, set]
Speech pitch of the speaker in percent (main use is for UI).
- float **CurrentVolume** [get, set]
Volume of the speaker in percent (main use is for UI).
- string **RTVoiceName** [get]
Returns the name of the RT-Voice for the current platform.

5.89.1 Detailed Description

Allows to speak text files.

5.89.2 Member Function Documentation

5.89.2.1 void Crosstales.RTVoice.Tool.TextFileSpeaker.Silence ()

Silence the speech.

5.89.2.2 void Crosstales.RTVoice.Tool.TextFileSpeaker.Speak ()

Speaks a random text.

5.89.2.3 string Crosstales.RTVoice.Tool.TextFileSpeaker.SpeakText (int *index* = -1)

Speaks a text with an optional index.

Parameters

<i>index</i>	Index of the text (default: -1 (random), optional).
--------------	---

Returns

UID of the speaker.

5.89.3 Member Data Documentation

5.89.3.1 `string Crosstales.RTVoice.Tool.TextFileSpeaker.Culture = "en"`

Fallback culture for the text (e.g. 'en', optional).

5.89.3.2 `float Crosstales.RTVoice.Tool.TextFileSpeaker.Delay = 0f`

Delay until the speech for this text starts (default: 0).

5.89.3.3 `Model.Enum.SpeakMode Crosstales.RTVoice.Tool.TextFileSpeaker.Mode = Model.Enum.SpeakMode.Speak`

Speak mode (default: 'Speak').

5.89.3.4 `float Crosstales.RTVoice.Tool.TextFileSpeaker.Pitch = 1f`

Speech pitch of the speaker in percent (1 = 100%, default: 1, optional, mobile only).

5.89.3.5 `bool Crosstales.RTVoice.Tool.TextFileSpeaker.PlayOnStart = false`

Enable speaking of a random text file on start (default: false).

5.89.3.6 `float Crosstales.RTVoice.Tool.TextFileSpeaker.Rate = 1f`

Speech rate of the speaker in percent (1 = 100%, default: 1, optional).

5.89.3.7 `string Crosstales.RTVoice.Tool.TextFileSpeaker.RTVoiceNameAndroid = string.Empty`

Name of the RT-Voice under Android.

5.89.3.8 `string Crosstales.RTVoice.Tool.TextFileSpeaker.RTVoiceNameIOS = "Daniel"`

Name of the RT-Voice under iOS.

5.89.3.9 `string Crosstales.RTVoice.Tool.TextFileSpeaker.RTVoiceNameMac = "Alex"`

Name of the RT-Voice under macOS (optional).

5.89.3.10 `string Crosstales.RTVoice.Tool.TextFileSpeaker.RTVoiceNameMaryTTS = "cmu-rms-hsmm"`

Name of the RT-Voice under MaryTTS.

5.89.3.11 `string Crosstales.RTVoice.Tool.TextFileSpeaker.RTVoiceNameWindows = "Microsoft David Desktop"`

Name of the RT-Voice under Windows (optional).

5.89.3.12 `string Crosstales.RTVoice.Tool.TextFileSpeaker.RTVoiceNameWSA = "Microsoft David Mobile"`

Name of the RT-Voice under WSA.

5.89.3.13 `AudioSource Crosstales.RTVoice.Tool.TextFileSpeaker.Source`

AudioSource for the output (optional).

5.89.3.14 `TextAsset [] Crosstales.RTVoice.Tool.TextFileSpeaker.TextFiles`

Text files to speak.

5.89.3.15 `float Crosstales.RTVoice.Tool.TextFileSpeaker.Volume = 1f`

Volume of the speaker in percent (1 = 100%, default: 1, optional, Windows only).

5.89.4 Property Documentation

5.89.4.1 `string Crosstales.RTVoice.Tool.TextFileSpeaker.CurrentCulture` `[get]`, `[set]`

Fallback culture for the text (main use is for [UI](#)).

5.89.4.2 `float Crosstales.RTVoice.Tool.TextFileSpeaker.CurrentPitch` `[get]`, `[set]`

Speech pitch of the speaker in percent (main use is for [UI](#)).

5.89.4.3 `float Crosstales.RTVoice.Tool.TextFileSpeaker.CurrentRate` `[get]`, `[set]`

Speech rate of the speaker in percent (main use is for [UI](#)).

5.89.4.4 `float Crosstales.RTVoice.Tool.TextFileSpeaker.CurrentVolume` `[get]`, `[set]`

Volume of the speaker in percent (main use is for [UI](#)).

5.89.4.5 string Crosstales.RTVoice.Tool.TextFileSpeaker.RTVoiceName [get]

Returns the name of the RT-Voice for the current platform.

Returns

The name of the RT-Voice for the current platform.


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/RTVoice/Scripts/Tool/TextFileSpeaker.cs

5.90 Crosstales.RTVoice.EditorExtension.TextFileSpeakerEditor Class Reference

Custom editor for the 'TextFileSpeaker'-class.

Inheritance diagram for Crosstales.RTVoice.EditorExtension.TextFileSpeakerEditor:



Public Member Functions

- void **OnEnable** ()
- void **OnDisable** ()
- override void **OnInspectorGUI** ()

5.90.1 Detailed Description

Custom editor for the 'TextFileSpeaker'-class.


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/RTVoice/Editor/Extension/TextFileSpeakerEditor.cs

5.91 Crosstales.RTVoice.UDEA2.UDEAConnector Class Reference

Connects UDEA and RT-Voice. Must be placed on a dialogue prefab.

Inheritance diagram for Crosstales.RTVoice.UDEA2.UDEAConnector:



Public Member Functions

- void **Start** ()
- void **OnDestroy** ()
- void **OnValidate** ()
- void **SpeakRT** ()

Public Attributes

- [UDEAVoiceWrapper\[\]](#) [Voices](#)
Voices for the UDEA-characters (optional).
- string [Culture](#)
Fallback culture for all sequences (e.g. 'en', optional).

5.91.1 Detailed Description

Connects UDEA and RT-Voice. Must be placed on a dialogue prefab.

5.91.2 Member Data Documentation

5.91.2.1 string Crosstales.RTVoice.UDEA2.UDEAConnector.Culture

Fallback culture for all sequences (e.g. 'en', optional).

5.91.2.2 UDEAVoiceWrapper [] Crosstales.RTVoice.UDEA2.UDEAConnector.Voices

Voices for the UDEA-characters (optional).


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/RTVoice/3rd party/THE Dialogue Engine/Scripts/UDEAConnector.cs

5.92 Crosstales.RTVoice.UDEA2.UDEAConnectorEditor Class Reference

Custom editor for the '[UDEAConnector](#)'-class.

Inheritance diagram for Crosstales.RTVoice.UDEA2.UDEAConnectorEditor:



Public Member Functions

- override void **OnInspectorGUI** ()

5.92.1 Detailed Description

Custom editor for the 'UDEAConnector'-class.

The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/RTVoice/3rd party/THE Dialogue Engine/Editor/UDEAConnectorEditor.cs

5.93 Crosstales.RTVoice.UDEA2.UDEAVoiceWrapper Class Reference

Wrapper for an UDEA-character to an RT-Voice.

Public Member Functions

- override string **ToString** ()

Public Attributes

- string **UDEAVoiceName** = string.Empty
"Name of the UDEA-character on-screen."
- string **RTVoiceNameWindows** = string.Empty
"Name of the RT-Voice under Windows."
- string **RTVoiceNameMac** = string.Empty
Name of the RT-Voice under macOS.
- string **RTVoiceNameAndroid** = string.Empty
Name of the RT-Voice under Android.
- string **RTVoiceNameIOS** = string.Empty
Name of the RT-Voice under iOS.
- string **RTVoiceNameWSA** = string.Empty
Name of the RT-Voice under WSA.
- string **RTVoiceNameMaryTTS** = string.Empty
Name of the RT-Voice under MaryTTS.
- AudioSource **Source**
Origin AudioSource (optional).
- float **Rate** = 1f
Speech rate of the speaker in percent (1 = 100%, default: 1, optional).
- float **Pitch** = 1f
Speech pitch of the speaker in percent (1 = 100%, default: 1, optional, mobile only).
- float **Volume** = 1f
Volume of the speaker in percent (1 = 100%, default: 1, optional).
- bool **IgnoreCharacter** = false
Ignore this character (default: false).
- bool **initialized** = false

Properties

- string [RTVoiceName](#) [get]
Returns the name of the RT-Voice for the current platform.

5.93.1 Detailed Description

Wrapper for an UDEA-character to an RT-Voice.

5.93.2 Member Data Documentation

5.93.2.1 bool Crosstales.RTVoice.UDEA2.UDEAVoiceWrapper.IgnoreCharacter = false

Ignore this character (default: false).

5.93.2.2 float Crosstales.RTVoice.UDEA2.UDEAVoiceWrapper.Pitch = 1f

Speech pitch of the speaker in percent (1 = 100%, default: 1, optional, mobile only).

5.93.2.3 float Crosstales.RTVoice.UDEA2.UDEAVoiceWrapper.Rate = 1f

Speech rate of the speaker in percent (1 = 100%, default: 1, optional).

5.93.2.4 string Crosstales.RTVoice.UDEA2.UDEAVoiceWrapper.RTVoiceNameAndroid = string.Empty

Name of the RT-Voice under Android.

5.93.2.5 string Crosstales.RTVoice.UDEA2.UDEAVoiceWrapper.RTVoiceNameIOS = string.Empty

Name of the RT-Voice under iOS.

5.93.2.6 string Crosstales.RTVoice.UDEA2.UDEAVoiceWrapper.RTVoiceNameMac = string.Empty

Name of the RT-Voice under macOS.

5.93.2.7 string Crosstales.RTVoice.UDEA2.UDEAVoiceWrapper.RTVoiceNameMaryTTS = string.Empty

Name of the RT-Voice under MaryTTS.

5.93.2.8 string Crosstales.RTVoice.UDEA2.UDEAVoiceWrapper.RTVoiceNameWindows = string.Empty

"Name of the RT-Voice under Windows.

5.93.2.9 `string Crosstales.RTVoice.UDEA2.UDEAVoiceWrapper.RTVoiceNameWSA = string.Empty`

Name of the RT-Voice under WSA.

5.93.2.10 `AudioSource Crosstales.RTVoice.UDEA2.UDEAVoiceWrapper.Source`

Origin AudioSource (optional).

5.93.2.11 `string Crosstales.RTVoice.UDEA2.UDEAVoiceWrapper.UDEAVoiceName = string.Empty`

"Name of the UDEA-character on-screen.

5.93.2.12 `float Crosstales.RTVoice.UDEA2.UDEAVoiceWrapper.Volume = 1f`

Volume of the speaker in percent (1 = 100%, default: 1, optional).

5.93.3 Property Documentation

5.93.3.1 `string Crosstales.RTVoice.UDEA2.UDEAVoiceWrapper.RTVoiceName` [get]

Returns the name of the RT-Voice for the current platform.

Returns

The name of the RT-Voice for the current platform.


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/RTVoice/3rd party/THE Dialogue Engine/Scripts/UDEAVoiceWrapper.cs

5.94 Crosstales.UI.UIDrag Class Reference

Allow to Drag the Windows around.

Inheritance diagram for Crosstales.UI.UIDrag:



Public Member Functions

- void **BeginDrag** ()
- void **OnDrag** ()

5.94.1 Detailed Description

Allow to Drag the Windows arround.


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/Common/↔ UI/Scripts/UIDrag.cs

5.95 Crosstales.UI.UIFocus Class Reference

Change the Focus on from a Window.

Inheritance diagram for Crosstales.UI.UIFocus:



Public Member Functions

- void **Start** ()
- void **onPanelEnter** ()

Public Attributes

- string **CanvasName** = "Canvas"

5.95.1 Detailed Description

Change the Focus on from a Window.


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/Common/↔ UI/Scripts/UIFocus.cs

5.96 Crosstales.UI.UIWindowManager Class Reference

Change the state of all Window panels.

Inheritance diagram for Crosstales.UI.UIWindowManager:



Public Member Functions

- void **Start** ()
- void **ChangeState** (GameObject x)

Public Attributes

- GameObject[] [Windows](#)
All Windows of the scene.

5.96.1 Detailed Description

Change the state of all Window panels.

5.96.2 Member Data Documentation

5.96.2.1 GameObject [] Crosstales.UI.UIWindowManager.Windows

All Windows of the scene.

The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/Common/↔ UI/Scripts/UIWindowManager.cs

5.97 Crosstales.RTVoice.EditorTask.UpdateCheck Class Reference

Checks for updates of the asset.

Static Public Member Functions

- static void **UpdateCheckForEditor** (out string result, out [UpdateStatus](#) st)

Public Attributes

- const string **TEXT_NOT_CHECKED** = "Not checked."
- const string **TEXT_NO_UPDATE** = "No update available - you are using the latest version."

5.97.1 Detailed Description

Checks for updates of the asset.

The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/RTVoice/↵ Editor/Task/UpdateCheck.cs

5.98 Crosstales.RTVoice.Model.Voice Class Reference

[Model](#) for a voice.

Public Member Functions

- [Voice](#) (string name, string description, string gender, string age, string culture)
Instantiate the class.
- [Voice](#) (string name, string description, string culture)
Instantiate the class.
- override string **ToString** ()

Public Attributes

- string [Name](#)
Name of the RT-Voice.
- string [Description](#) = string.Empty
Description of the RT-Voice.
- string [Gender](#) = string.Empty
Gender of the RT-Voice (Windows only).
- string [Age](#) = string.Empty
Age of the RT-Voice (Windows only).
- string [Culture](#) = string.Empty
Culture of the RT-Voice.

5.98.1 Detailed Description

[Model](#) for a voice.

5.98.2 Constructor & Destructor Documentation

5.98.2.1 Crosstales.RTVoice.Model.Voice.Voice (string name, string description, string gender, string age, string culture)

Instantiate the class.

Parameters

<i>name</i>	Name of the RT-Voice.
<i>description</i>	Description of the RT-Voice.
<i>gender</i>	Gender of the RT-Voice (Windows only).
<i>age</i>	Age of the RT-Voice (Windows only).
<i>culture</i>	Culture of the RT-Voice.

5.98.2.2 Crosstales.RTVoice.Model.Voice.Voice (string *name*, string *description*, string *culture*)

Instantiate the class.

Parameters

<i>name</i>	Name of the RT-Voice.
<i>description</i>	Description of the RT-Voice.
<i>culture</i>	Culture of the RT-Voice.

5.98.3 Member Data Documentation

5.98.3.1 string Crosstales.RTVoice.Model.Voice.Age = string.Empty

Age of the RT-Voice (Windows only).

5.98.3.2 string Crosstales.RTVoice.Model.Voice.Culture = string.Empty

Culture of the RT-Voice.

5.98.3.3 string Crosstales.RTVoice.Model.Voice.Description = string.Empty

Description of the RT-Voice.

5.98.3.4 string Crosstales.RTVoice.Model.Voice.Gender = string.Empty

Gender of the RT-Voice (Windows only).

5.98.3.5 string Crosstales.RTVoice.Model.Voice.Name

Name of the RT-Voice.


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/RTVoice/↵ Scripts/Model/Voice.cs

5.99 Crosstales.RTVoice.Tool.VoiceInitializer Class Reference

Allows to initialize voices (useful on Android).

Inheritance diagram for Crosstales.RTVoice.Tool.VoiceInitializer:



Public Member Functions

- void **Start** ()
- void **OnEnable** ()
- void **OnDisable** ()

Public Attributes

- [Model.Enum.ProviderType Provider](#) = Model.Enum.ProviderType.Android
Selected provider to initialize the voices (default: Android).
- [string\[\] VoiceNames](#)
Initialize voices by name.
- [bool AllVoices](#) = false
Initialize all voices (default: false).
- [bool DestroyWhenFinished](#) = true
Destroy the gameobject after initialize (default: true).

5.99.1 Detailed Description

Allows to initialize voices (useful on Android).

5.99.2 Member Data Documentation

5.99.2.1 bool Crosstales.RTVoice.Tool.VoiceInitializer.AllVoices = false

Initialize all voices (default: false).

5.99.2.2 bool Crosstales.RTVoice.Tool.VoiceInitializer.DestroyWhenFinished = true

Destroy the gameobject after initialize (default: true).

5.99.2.3 Model.Enum.ProviderType Crosstales.RTVoice.Tool.VoiceInitializer.Provider = Model.Enum.ProviderType.Android

Selected provider to initialize the voices (default: Android).

5.99.2.4 string [] Crosstales.RTVoice.Tool.VoiceInitializer.VoiceNames

Initialize voices by name.


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/RTVoice/Scripts/Tool/VoiceInitializer.cs

5.100 Crosstales.RTVoice.EditorExtension.VoiceInitializerEditor Class Reference

Custom editor for the 'VoiceInitializer'-class.

Inheritance diagram for Crosstales.RTVoice.EditorExtension.VoiceInitializerEditor:



Public Member Functions

- void **OnEnable** ()
- override void **OnInspectorGUI** ()

5.100.1 Detailed Description

Custom editor for the 'VoiceInitializer'-class.


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/RTVoice/Editor/Extension/VoiceInitializerEditor.cs

5.101 Crosstales.RTVoice.Provider.VoiceProviderAndroid Class Reference

Android voice provider.

Inheritance diagram for Crosstales.RTVoice.Provider.VoiceProviderAndroid:



Public Member Functions

- [VoiceProviderAndroid](#) (MonoBehaviour obj)
Constructor for [VoiceProviderAndroid](#).
- override IEnumerator [SpeakNative](#) ([Model.Wrapper](#) wrapper)
The current provider speaks a text with a given voice (native mode).
- override IEnumerator [Speak](#) ([Model.Wrapper](#) wrapper)
The current provider speaks a text with a given voice.
- override IEnumerator [Generate](#) ([Model.Wrapper](#) wrapper)
The current provider generates an audio file from a text with a given voice.
- override void [Silence](#) ()
Silence all active TTS-providers.
- void **ShutdownTTS** ()

Properties

- override string **AudioFileExtension** [get]
- override System.Collections.Generic.List< [Model.Voice](#) > **Voices** [get]

Additional Inherited Members

5.101.1 Detailed Description

Android voice provider.

5.101.2 Constructor & Destructor Documentation

5.101.2.1 Crosstales.RTVoice.Provider.VoiceProviderAndroid.VoiceProviderAndroid (MonoBehaviour obj)

Constructor for [VoiceProviderAndroid](#).

Parameters

<i>obj</i>	Instance of the speaker
------------	-------------------------

5.101.3 Member Function Documentation

5.101.3.1 override IEnumerator Crosstales.RTVoice.Provider.VoiceProviderAndroid.Generate (Model.Wrapper wrapper) [virtual]

The current provider generates an audio file from a text with a given voice.

Parameters

<i>wrapper</i>	Wrapper containing the data.
----------------	------------------------------

Implements [Crosstales.RTVoice.Provider.BaseVoiceProvider](#).

5.101.3.2 `override void Crosstales.RTVoice.Provider.VoiceProviderAndroid.Silence () [virtual]`

Silence all active TTS-providers.

Reimplemented from [Crosstales.RTVoice.Provider.BaseVoiceProvider](#).

5.101.3.3 `override IEnumerator Crosstales.RTVoice.Provider.VoiceProviderAndroid.Speak (Model.Wrapper wrapper) [virtual]`

The current provider speaks a text with a given voice.

Parameters

<i>wrapper</i>	Wrapper containing the data.
----------------	------------------------------

Implements [Crosstales.RTVoice.Provider.BaseVoiceProvider](#).

5.101.3.4 `override IEnumerator Crosstales.RTVoice.Provider.VoiceProviderAndroid.SpeakNative (Model.Wrapper wrapper) [virtual]`

The current provider speaks a text with a given voice (native mode).

Parameters

<i>wrapper</i>	Wrapper containing the data.
----------------	------------------------------

Implements [Crosstales.RTVoice.Provider.BaseVoiceProvider](#).


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/RTVoice/↔ Scripts/Provider/VoiceProviderAndroid.cs

5.102 Crosstales.RTVoice.Provider.VoiceProviderIOS Class Reference

iOS voice provider.

Inheritance diagram for Crosstales.RTVoice.Provider.VoiceProviderIOS:



Public Member Functions

- [VoiceProviderIOS](#) (MonoBehaviour obj)
Constructor for [VoiceProviderIOS](#).
- override IEnumerator [SpeakNative](#) ([Model.Wrapper](#) wrapper)
The current provider speaks a text with a given voice (native mode).
- override IEnumerator [Speak](#) ([Model.Wrapper](#) wrapper)
The current provider speaks a text with a given voice.
- override IEnumerator [Generate](#) ([Model.Wrapper](#) wrapper)
The current provider generates an audio file from a text with a given voice.
- override void [Silence](#) ()
Silence all active TTS-providers.

Static Public Member Functions

- static void [SetVoices](#) (string voicesText)
Receives all voices
- static void [SetState](#) (string state)
Receives the state of the speaker.
- static void [WordSpoken](#) ()
Called everytime a new word is spoken.

Properties

- override string **AudioFileExtension** [get]
- override System.Collections.Generic.List< [Model.Voice](#) > **Voices** [get]

Additional Inherited Members

5.102.1 Detailed Description

iOS voice provider.

5.102.2 Constructor & Destructor Documentation

5.102.2.1 Crosstales.RTVoice.Provider.VoiceProviderIOS.VoiceProviderIOS (MonoBehaviour obj)

Constructor for [VoiceProviderIOS](#).

Parameters

<i>obj</i>	Instance of the speaker
------------	-------------------------

5.102.3 Member Function Documentation

5.102.3.1 **override IEnumerator** **Crosstales.RTVoice.Provider.VoiceProviderIOS.Generate** (**Model.Wrapper** *wrapper*)
[virtual]

The current provider generates an audio file from a text with a given voice.

Parameters

<i>wrapper</i>	Wrapper containing the data.
----------------	------------------------------

Implements [Crosstales.RTVoice.Provider.BaseVoiceProvider](#).

5.102.3.2 **static void** **Crosstales.RTVoice.Provider.VoiceProviderIOS.SetState** (**string** *state*) [static]

Receives the state of the speaker.

Parameters

<i>state</i>	The state of the speaker.
--------------	---------------------------

5.102.3.3 **static void** **Crosstales.RTVoice.Provider.VoiceProviderIOS.SetVoices** (**string** *voicesText*) [static]

Receives all voices

Parameters

<i>voicesText</i>	All voices as text string.
-------------------	----------------------------

5.102.3.4 **override void** **Crosstales.RTVoice.Provider.VoiceProviderIOS.Silence** () [virtual]

Silence all active TTS-providers.

Reimplemented from [Crosstales.RTVoice.Provider.BaseVoiceProvider](#).

5.102.3.5 **override IEnumerator** **Crosstales.RTVoice.Provider.VoiceProviderIOS.Speak** (**Model.Wrapper** *wrapper*)
[virtual]

The current provider speaks a text with a given voice.

Parameters

<i>wrapper</i>	Wrapper containing the data.
----------------	------------------------------

Implements [Crosstales.RTVoice.Provider.BaseVoiceProvider](#).

5.102.3.6 `override IEnumerator Crosstales.RTVoice.Provider.VoiceProviderIOS.SpeakNative (Model.Wrapper wrapper)`
`[virtual]`

The current provider speaks a text with a given voice (native mode).

Parameters

<i>wrapper</i>	Wrapper containing the data.
----------------	------------------------------

Implements [Crosstales.RTVoice.Provider.BaseVoiceProvider](#).

5.102.3.7 `static void Crosstales.RTVoice.Provider.VoiceProviderIOS.WordSpoken ()` `[static]`

Called everytime a new word is spoken.


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/RTVoice/Scripts/Provider/VoiceProviderIOS.cs

5.103 Crosstales.RTVoice.Provider.VoiceProviderMacOS Class Reference

MacOS voice provider.

Inheritance diagram for Crosstales.RTVoice.Provider.VoiceProviderMacOS:



Public Member Functions

- [VoiceProviderMacOS](#) (MonoBehaviour obj)
Constructor for [VoiceProviderMacOS](#).
- override IEnumerator [SpeakNative](#) ([Model.Wrapper](#) wrapper)
The current provider speaks a text with a given voice (native mode).
- override IEnumerator [Speak](#) ([Model.Wrapper](#) wrapper)
The current provider speaks a text with a given voice.
- override IEnumerator [Generate](#) ([Model.Wrapper](#) wrapper)
The current provider generates an audio file from a text with a given voice.

Properties

- override string **AudioFileExtension** `[get]`
- override System.Collections.Generic.List< [Model.Voice](#) > **Voices** `[get]`

Additional Inherited Members

5.103.1 Detailed Description

MacOS voice provider.

5.103.2 Constructor & Destructor Documentation

5.103.2.1 Crosstales.RTVoice.Provider.VoiceProviderMacOS.VoiceProviderMacOS (MonoBehaviour *obj*)

Constructor for [VoiceProviderMacOS](#).

Parameters

<i>obj</i>	Instance of the speaker
------------	-------------------------

5.103.3 Member Function Documentation

5.103.3.1 override IEnumerator Crosstales.RTVoice.Provider.VoiceProviderMacOS.Generate (Model.Wrapper *wrapper*) [virtual]

The current provider generates an audio file from a text with a given voice.

Parameters

<i>wrapper</i>	Wrapper containing the data.
----------------	------------------------------

Implements [Crosstales.RTVoice.Provider.BaseVoiceProvider](#).

5.103.3.2 override IEnumerator Crosstales.RTVoice.Provider.VoiceProviderMacOS.Speak (Model.Wrapper *wrapper*) [virtual]

The current provider speaks a text with a given voice.

Parameters

<i>wrapper</i>	Wrapper containing the data.
----------------	------------------------------

Implements [Crosstales.RTVoice.Provider.BaseVoiceProvider](#).

5.103.3.3 override IEnumerator Crosstales.RTVoice.Provider.VoiceProviderMacOS.SpeakNative (Model.Wrapper *wrapper*) [virtual]

The current provider speaks a text with a given voice (native mode).

Parameters

<i>wrapper</i>	Wrapper containing the data.
----------------	------------------------------

Implements [Crosstales.RTVoice.Provider.BaseVoiceProvider](#).


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/RTVoice/Scripts/Provider/VoiceProviderMacOS.cs

5.104 Crosstales.RTVoice.Provider.VoiceProviderMary Class Reference

MaryTTS voice provider.

Inheritance diagram for Crosstales.RTVoice.Provider.VoiceProviderMary:



Public Member Functions

- [VoiceProviderMary](#) (MonoBehaviour obj, string url, int port, string user, string password, [Model.Enum.MaryTTSType](#) type)
Constructor for [VoiceProviderMary](#). Needed to pass IP and Port of the MaryTTS server to the [Provider](#).
- override IEnumerator [SpeakNative](#) ([Model.Wrapper](#) wrapper)
The current provider speaks a text with a given voice (native mode).
- override IEnumerator [Speak](#) ([Model.Wrapper](#) wrapper)
The current provider speaks a text with a given voice.
- override IEnumerator [Generate](#) ([Model.Wrapper](#) wrapper)
The current provider generates an audio file from a text with a given voice.
- override void [Silence](#) ()
Silence all active TTS-providers.

Properties

- override string **AudioFileExtension** [get]
- override System.Collections.Generic.List< [Model.Voice](#) > **Voices** [get]

Additional Inherited Members

5.104.1 Detailed Description

MaryTTS voice provider.

5.104.2 Constructor & Destructor Documentation

- 5.104.2.1 [Crosstales.RTVoice.Provider.VoiceProviderMary.VoiceProviderMary](#) (MonoBehaviour obj, string url, int port, string user, string password, [Model.Enum.MaryTTSType](#) type)

Constructor for [VoiceProviderMary](#). Needed to pass IP and Port of the MaryTTS server to the [Provider](#).

Parameters

<i>obj</i>	Instance of the speaker
<i>url</i>	IP-Address of the MaryTTS-server
<i>port</i>	Port to connect to on the MaryTTS-server

5.104.3 Member Function Documentation

5.104.3.1 override IEnumerator Crosstales.RTVoice.Provider.VoiceProviderMary.Generate (**Model.Wrapper wrapper**) [virtual]

The current provider generates an audio file from a text with a given voice.

Parameters

<i>wrapper</i>	Wrapper containing the data.
----------------	------------------------------

Implements [Crosstales.RTVoice.Provider.BaseVoiceProvider](#).

5.104.3.2 override void Crosstales.RTVoice.Provider.VoiceProviderMary.Silence () [virtual]

Silence all active TTS-providers.

Reimplemented from [Crosstales.RTVoice.Provider.BaseVoiceProvider](#).

5.104.3.3 override IEnumerator Crosstales.RTVoice.Provider.VoiceProviderMary.Speak (**Model.Wrapper wrapper**) [virtual]

The current provider speaks a text with a given voice.

Parameters

<i>wrapper</i>	Wrapper containing the data.
----------------	------------------------------

Implements [Crosstales.RTVoice.Provider.BaseVoiceProvider](#).

5.104.3.4 override IEnumerator Crosstales.RTVoice.Provider.VoiceProviderMary.SpeakNative (**Model.Wrapper wrapper**) [virtual]

The current provider speaks a text with a given voice (native mode).

Parameters

<i>wrapper</i>	Wrapper containing the data.
----------------	------------------------------

Implements [Crosstales.RTVoice.Provider.BaseVoiceProvider](#).


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/RTVoice/↔ Scripts/Provider/VoiceProviderMary.cs

5.105 Crosstales.RTVoice.Provider.VoiceProviderWindows Class Reference

Windows voice provider.

Inheritance diagram for Crosstales.RTVoice.Provider.VoiceProviderWindows:



Public Member Functions

- [VoiceProviderWindows](#) (MonoBehaviour obj)
Constructor for [VoiceProviderWindows](#).
- override IEnumerator [SpeakNative](#) ([Model.Wrapper](#) wrapper)
The current provider speaks a text with a given voice (native mode).
- override IEnumerator [Speak](#) ([Model.Wrapper](#) wrapper)
The current provider speaks a text with a given voice.
- override IEnumerator [Generate](#) ([Model.Wrapper](#) wrapper)
The current provider generates an audio file from a text with a given voice.

Properties

- override string **AudioFileExtension** [get]
- override System.Collections.Generic.List< [Model.Voice](#) > **Voices** [get]

Additional Inherited Members

5.105.1 Detailed Description

Windows voice provider.

5.105.2 Constructor & Destructor Documentation

5.105.2.1 Crosstales.RTVoice.Provider.VoiceProviderWindows.VoiceProviderWindows (MonoBehaviour obj)

Constructor for [VoiceProviderWindows](#).

Parameters

<i>obj</i>	Instance of the speaker
------------	-------------------------

5.105.3 Member Function Documentation

5.105.3.1 `override IEnumerator Crosstales.RTVoice.Provider.VoiceProviderWindows.Generate (Model.Wrapper wrapper)`
[virtual]

The current provider generates an audio file from a text with a given voice.

Parameters

<i>wrapper</i>	Wrapper containing the data.
----------------	------------------------------

Implements [Crosstales.RTVoice.Provider.BaseVoiceProvider](#).

5.105.3.2 `override IEnumerator Crosstales.RTVoice.Provider.VoiceProviderWindows.Speak (Model.Wrapper wrapper)`
[virtual]

The current provider speaks a text with a given voice.

Parameters

<i>wrapper</i>	Wrapper containing the data.
----------------	------------------------------

Implements [Crosstales.RTVoice.Provider.BaseVoiceProvider](#).

5.105.3.3 `override IEnumerator Crosstales.RTVoice.Provider.VoiceProviderWindows.SpeakNative (Model.Wrapper wrapper)`
[virtual]

The current provider speaks a text with a given voice (native mode).

Parameters

<i>wrapper</i>	Wrapper containing the data.
----------------	------------------------------


Implements [Crosstales.RTVoice.Provider.BaseVoiceProvider](#).

The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/RTVoice/↔ Scripts/Provider/VoiceProviderWindows.cs

5.106 Crosstales.RTVoice.Provider.VoiceProviderWSA Class Reference

Inheritance diagram for Crosstales.RTVoice.Provider.VoiceProviderWSA:



Public Member Functions

- [VoiceProviderWSA](#) (MonoBehaviour obj)
Constructor for [VoiceProviderWSA](#).
- override IEnumerator [SpeakNative](#) ([Model.Wrapper](#) wrapper)
The current provider speaks a text with a given voice (native mode).
- override IEnumerator [Speak](#) ([Model.Wrapper](#) wrapper)
The current provider speaks a text with a given voice.
- override IEnumerator [Generate](#) ([Model.Wrapper](#) wrapper)
The current provider generates an audio file from a text with a given voice.
- override void [Silence](#) ()
Silence all active TTS-providers.

Properties

- override string **AudioFileExtension** [get]
- override System.Collections.Generic.List< [Model.Voice](#) > **Voices** [get]

Additional Inherited Members

5.106.1 Constructor & Destructor Documentation

5.106.1.1 Crosstales.RTVoice.Provider.VoiceProviderWSA.VoiceProviderWSA (MonoBehaviour obj)

Constructor for [VoiceProviderWSA](#).

Parameters

<i>obj</i>	Instance of the speaker
------------	-------------------------

5.106.2 Member Function Documentation

5.106.2.1 override IEnumerator Crosstales.RTVoice.Provider.VoiceProviderWSA.Generate (Model.Wrapper wrapper) [virtual]

The current provider generates an audio file from a text with a given voice.

Parameters

<i>wrapper</i>	Wrapper containing the data.
----------------	------------------------------

Implements [Crosstales.RTVoice.Provider.BaseVoiceProvider](#).

5.106.2.2 **override void Crosstales.RTVoice.Provider.VoiceProviderWSA.Silence ()** [virtual]

Silence all active TTS-providers.

Reimplemented from [Crosstales.RTVoice.Provider.BaseVoiceProvider](#).

5.106.2.3 **override IEnumerator Crosstales.RTVoice.Provider.VoiceProviderWSA.Speak (Model.Wrapper wrapper)**
[virtual]

The current provider speaks a text with a given voice.

Parameters

<i>wrapper</i>	Wrapper containing the data.
----------------	------------------------------

Implements [Crosstales.RTVoice.Provider.BaseVoiceProvider](#).

5.106.2.4 **override IEnumerator Crosstales.RTVoice.Provider.VoiceProviderWSA.SpeakNative (Model.Wrapper wrapper)**
[virtual]

The current provider speaks a text with a given voice (native mode).

Parameters

<i>wrapper</i>	Wrapper containing the data.
----------------	------------------------------

Implements [Crosstales.RTVoice.Provider.BaseVoiceProvider](#).


The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/RTVoice/↵
Scripts/Provider/VoiceProviderWSA.cs

5.107 Crosstales.UI.WindowManager Class Reference

Manager for a Window.

Inheritance diagram for Crosstales.UI.WindowManager:



Public Member Functions

- void **Start** ()
- void **Update** ()
- void **SwitchPanel** ()
- void **OpenPanel** ()
- void **ClosePanel** ()

Public Attributes

- float **Speed** = 3f
Window movement speed (default: 3).
- GameObject[] **Dependencies**
Dependent GameObjects (active == open).

5.107.1 Detailed Description

Manager for a Window.

5.107.2 Member Data Documentation

5.107.2.1 GameObject [] Crosstales.UI.WindowManager.Dependencies

Dependent GameObjects (active == open).

5.107.2.2 float Crosstales.UI.WindowManager.Speed = 3f

Window movement speed (default: 3).

The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/Common/↔ UI/Scripts/WindowManager.cs

5.108 Crosstales.RTVoice.Model.Wrapper Class Reference

[Wrapper](#) for "Speak"-function calls.

Public Member Functions

- [Wrapper](#) ()
Default.
- [Wrapper](#) (string text, [Voice](#) voice=null, float rate=1f, float pitch=1f, float volume=1f, AudioSource source=null, bool speakImmediately=true, string outputFile="")
Instantiate the class.
- [Wrapper](#) (string uid, string text, [Voice](#) voice=null, float rate=1f, float pitch=1f, float volume=1f, AudioSource source=null, bool speakImmediately=true, string outputFile="")
Instantiate the class.
- override string **Tostring** ()

Public Attributes

- string [Uid](#)
UID of the speech.
- AudioSource [Source](#)
AudioSource for the speech.
- [Voice](#) [Voice](#)
Voice for the speech.
- bool [SpeakImmediately](#) = true
Speak immediately after the audio generation. Only works if 'Source' is not null.
- string [OutputFile](#)
Output file (without extension) for the generated audio.

Properties

- string [Text](#) [get, set]
Text for the speech.
- float [Rate](#) [get, set]
Rate of the speech (values: 0-3).
- float [Pitch](#) [get, set]
Pitch of the speech (values: 0-2).
- float [Volume](#) [get, set]
Volume of the speech (values: 0-1).
- System.DateTime [Created](#) [get]
Returns the creation time of the RecordInfo.

5.108.1 Detailed Description

[Wrapper](#) for "Speak"-function calls.

5.108.2 Constructor & Destructor Documentation

5.108.2.1 Crosstales.RTVoice.Model.Wrapper.Wrapper ()

Default.

5.108.2.2 Crosstales.RTVoice.Model.Wrapper.Wrapper (string text, Voice voice = null, float rate = 1f, float pitch = 1f, float volume = 1f, AudioSource source = null, bool speakImmediately = true, string outputFile = " ")

Instantiate the class.

Parameters

<i>text</i>	Text for the speech.
<i>voice</i>	Voice for the speech (default: null, optional).
<i>rate</i>	Rate of the speech (values: 0-3, default: 1, optional).
<i>pitch</i>	Pitch of the speech (values: 0-2, default: 1, optional).
<i>volume</i>	Volume of the speech (values: 0-1, default: 1, optional).
<i>source</i>	AudioSource for the speech (default: null, optional).
<i>speakImmediately</i>	Speak immediately after the audio generation. Only works if 'Source' is not null (default: true, optional).
<i>outputFile</i>	Output file (without extension) for the generated audio (default: empty, optional).

5.108.2.3 `Crosstales.RTVoice.Model.Wrapper.Wrapper (string uid, string text, Voice voice = null, float rate = 1f, float pitch = 1f, float volume = 1f, AudioSource source = null, bool speakImmediately = true, string outputFile = "")`

Instantiate the class.

Parameters

<i>uid</i>	UID of the speech.
<i>voice</i>	Voice for the speech (default: null, optional).
<i>rate</i>	Rate of the speech (values: 0-3, default: 1, optional).
<i>pitch</i>	Pitch of the speech (values: 0-2, default: 1, optional).
<i>volume</i>	Volume of the speech (values: 0-1, default: 1, optional).
<i>source</i>	AudioSource for the speech (default: null, optional).
<i>speakImmediately</i>	Speak immediately after the audio generation. Only works if 'Source' is not null (default: true, optional).
<i>outputFile</i>	Output file (without extension) for the generated audio (default: empty, optional).

5.108.3 Member Data Documentation**5.108.3.1** `string Crosstales.RTVoice.Model.Wrapper.OutputFile`

Output file (without extension) for the generated audio.

5.108.3.2 `AudioSource Crosstales.RTVoice.Model.Wrapper.Source`

AudioSource for the speech.

5.108.3.3 `bool Crosstales.RTVoice.Model.Wrapper.SpeakImmediately = true`

Speak immediately after the audio generation. Only works if 'Source' is not null.

5.108.3.4 string Crosstales.RTVoice.Model.Wrapper.Uid

UID of the speech.

5.108.3.5 Voice Crosstales.RTVoice.Model.Wrapper.Voice

Voice for the speech.

5.108.4 Property Documentation

5.108.4.1 System.DateTime Crosstales.RTVoice.Model.Wrapper.Created [get]

Returns the creation time of the RecordInfo.

Returns

Creation time of the RecordInfo.

5.108.4.2 float Crosstales.RTVoice.Model.Wrapper.Pitch [get], [set]

Pitch of the speech (values: 0-2).

5.108.4.3 float Crosstales.RTVoice.Model.Wrapper.Rate [get], [set]

Rate of the speech (values: 0-3).

5.108.4.4 string Crosstales.RTVoice.Model.Wrapper.Text [get], [set]

Text for the speech.

5.108.4.5 float Crosstales.RTVoice.Model.Wrapper.Volume [get], [set]

Volume of the speech (values: 0-1).

The documentation for this class was generated from the following file:

- D:/slaubenberger/git/assets/RTVoicePro/3rd party/RTVoice_3rd_party/Assets/Plugins/crosstales/RTVoice/Scripts/Model/Wrapper.cs

Chapter 6

More information

6.1 Homepage

<https://www.crosstales.com/en/portfolio/rtvoice/>

6.2 AssetStore

<https://goo.gl/qwtXyb>

6.3 Forum

<http://goo.gl/Z6MZM1>

6.4 Documentation

<https://www.crosstales.com/media/data/assets/rtvoice/RTVoice-doc.pdf>

6.5 Demos

6.5.1 WebGL

<https://www.crosstales.com/media/data/assets/rtvoice/webgl/>

6.5.2 Windows

https://www.crosstales.com/media/data/assets/rtvoice/downloads/RTVoice_demo_win.zip

6.5.3 macOS

https://www.crosstales.com/media/data/assets/rtvoice/downloads/RTVoice_demo_mac.zip

6.5.4 Android

<https://www.crosstales.com/media/rtvoice/RTVoice.apk>

6.6 Videos

<https://www.youtube.com/c/Crosstales>

6.6.1 Promotion

<https://youtu.be/iVhTWDLY7g8?list=PLgtonIO6Tb41XTMeeZ836tjHlKg0084S>

6.6.2 Tutorial

<https://youtu.be/OJyVgCmX3wU?list=PLgtonIO6Tb41XTMeeZ836tjHlKg0084S>

Index

- ASSET_3P_ADVENTURE_CREATOR
 - Crosstales::RTVoice::Util::Constants, [53](#)
- ASSET_3P_CINEMA_DIRECTOR
 - Crosstales::RTVoice::Util::Constants, [53](#)
- ASSET_3P_DIALOG_SYSTEM
 - Crosstales::RTVoice::Util::Constants, [53](#)
- ASSET_3P_DIALOGUE_ENGINE
 - Crosstales::RTVoice::Util::Constants, [54](#)
- ASSET_3P_LIPSYNC
 - Crosstales::RTVoice::Util::Constants, [54](#)
- ASSET_3P_LOCALIZED_DIALOGS
 - Crosstales::RTVoice::Util::Constants, [54](#)
- ASSET_3P_NPC_CHAT
 - Crosstales::RTVoice::Util::Constants, [54](#)
- ASSET_3P_PLAYMAKER
 - Crosstales::Common::Util::BaseConstants, [28](#)
- ASSET_3P_QUEST_SYSTEM
 - Crosstales::RTVoice::Util::Constants, [54](#)
- ASSET_3P_SALSA
 - Crosstales::RTVoice::Util::Constants, [54](#)
- ASSET_3P_SLATE
 - Crosstales::RTVoice::Util::Constants, [54](#)
- ASSET_3P_URL
 - Crosstales::RTVoice::Util::Constants, [54](#)
- ASSET_3P_USEQUENCER
 - Crosstales::RTVoice::Util::Constants, [54](#)
- ASSET_API_URL
 - Crosstales::RTVoice::Util::Constants, [55](#)
- ASSET_AUTHOR_URL
 - Crosstales::Common::Util::BaseConstants, [29](#)
- ASSET_AUTHOR
 - Crosstales::Common::Util::BaseConstants, [28](#)
- ASSET_BUILD
 - Crosstales::RTVoice::Util::Constants, [55](#)
- ASSET_CHANGED
 - Crosstales::RTVoice::Util::Constants, [55](#)
- ASSET_CONTACT
 - Crosstales::RTVoice::Util::Constants, [55](#)
- ASSET_CREATED
 - Crosstales::RTVoice::Util::Constants, [55](#)
- ASSET_CT_URL
 - Crosstales::Common::Util::BaseConstants, [29](#)
- ASSET_FORUM_URL
 - Crosstales::RTVoice::Util::Constants, [55](#)
- ASSET_MANUAL_URL
 - Crosstales::RTVoice::Util::Constants, [55](#)
- ASSET_NAME
 - Crosstales::RTVoice::Util::Constants, [55](#)
- ASSET_PATH
 - Crosstales::RTVoice::EditorUtil::EditorConfig, [65](#)
 - Crosstales::RTVoice::Util::Config, [47](#)
- ASSET_PRO_URL
 - Crosstales::RTVoice::Util::Constants, [55](#)
- ASSET_SOCIAL_FACEBOOK
 - Crosstales::Common::Util::BaseConstants, [29](#)
- ASSET_SOCIAL_LINKEDIN
 - Crosstales::Common::Util::BaseConstants, [29](#)
- ASSET_SOCIAL_TWITTER
 - Crosstales::Common::Util::BaseConstants, [29](#)
- ASSET_SOCIAL_XING
 - Crosstales::Common::Util::BaseConstants, [29](#)
- ASSET_SOCIAL_YOUTUBE
 - Crosstales::Common::Util::BaseConstants, [29](#)
- ASSET_UID
 - Crosstales::RTVoice::EditorUtil::EditorConstants, [66](#)
- ASSET_UPDATE_CHECK_URL
 - Crosstales::RTVoice::Util::Constants, [56](#)
- ASSET_URL
 - Crosstales::RTVoice::EditorUtil::EditorConstants, [66](#)
- ASSET_VERSION
 - Crosstales::RTVoice::Util::Constants, [56](#)
- ASSET_VIDEO_PROMO
 - Crosstales::RTVoice::Util::Constants, [56](#)
- ASSET_VIDEO_TUTORIAL
 - Crosstales::RTVoice::Util::Constants, [56](#)
- ASSET_WEB_URL
 - Crosstales::RTVoice::Util::Constants, [56](#)
- AUDIOFILE_AUTOMATIC_DELETE
 - Crosstales::RTVoice::Util::Config, [47](#)
- AUDIOFILE_PATH
 - Crosstales::RTVoice::Util::Config, [47](#)
- Active
 - Crosstales::RTVoice::Demo::Util::NativeController, [91](#)
- Age
 - Crosstales::RTVoice::Model::Voice, [152](#)
- AllVoices
 - Crosstales::RTVoice::Tool::VoiceInitializer, [153](#)
- ApproximateSpeechLength
 - Crosstales::RTVoice::Speaker, [120](#)
- AudioFileExtension
 - Crosstales::RTVoice::Provider::BaseVoice↔
Provider, [43](#)
 - Crosstales::RTVoice::Speaker, [126](#)
- AudioSource
 - HutongGames::PlayMaker::Actions::SpeakBase,

- 116
- AudioSources
 - Crosstales::Util::AudioSourceController, 25
- AutoClearTags
 - Crosstales::RTVoice::Speaker, 125
- BaseVoiceProvider
 - Crosstales::RTVoice::Provider::BaseVoice↔Provider, 41
- CTAddRange< T, S >
 - Crosstales::ExtensionMethods, 70
- CTContains
 - Crosstales::ExtensionMethods, 71
- CTContainsAll
 - Crosstales::ExtensionMethods, 71
- CTContainsAny
 - Crosstales::ExtensionMethods, 71
- CTDump< T >
 - Crosstales::ExtensionMethods, 71, 72
- CTEquals
 - Crosstales::ExtensionMethods, 72
- CTReplace
 - Crosstales::ExtensionMethods, 72
- CTShuffle< T >
 - Crosstales::ExtensionMethods, 73
- CTToString< T >
 - Crosstales::ExtensionMethods, 73
- CTToTitleCase
 - Crosstales::ExtensionMethods, 74
- CleanText
 - Crosstales::RTVoice::Util::Helper, 82
- ClearLineEndings
 - Crosstales::Common::Util::BaseHelper, 33
- ClearSpaces
 - Crosstales::Common::Util::BaseHelper, 33
- ClearTags
 - Crosstales::Common::Util::BaseHelper, 34
- ConnectionLimit
 - Crosstales::Common::Util::CTWebClient, 62
- Created
 - Crosstales::RTVoice::Model::Wrapper, 170
- Crosstales, 11
- Crosstales.Common, 11
- Crosstales.Common.EditorTask, 11
- Crosstales.Common.EditorTask.BaseCompileDefines, 26
- Crosstales.Common.EditorTask.BaseSetupResources, 39
- Crosstales.Common.EditorTask.NYCheck, 92
- Crosstales.Common.EditorTask.OCCheck, 92
- Crosstales.Common.EditorUtil, 11
- Crosstales.Common.EditorUtil.BaseGAApi, 31
- Crosstales.Common.Util, 12
- Crosstales.Common.Util.BaseConstants, 27
- Crosstales.Common.Util.BaseHelper, 31
- Crosstales.Common.Util.CTPlayerPrefs, 57
- Crosstales.Common.Util.CTWebClient, 61
- Crosstales.Common.Util.PlatformController, 92
- Crosstales.Common.Util.RandomColor, 95
- Crosstales.Common.Util.RandomRotator, 96
- Crosstales.Common.Util.RandomScaler, 96
- Crosstales.Common.Util.SerializeDeSerialize< T >, 107
- Crosstales.DJ.Demo, 12
- Crosstales.DJ.Demo.Util, 12
- Crosstales.DJ.Demo.Util.FFTAnalyzer, 74
- Crosstales.DJ.Demo.Util.SpectrumVisualizer, 133
- Crosstales.DJ, 12
- Crosstales.ExtensionMethods, 69
- Crosstales.RTVoice, 13
- Crosstales.RTVoice.Demo, 13
- Crosstales.RTVoice.Demo.Dialog, 62
- Crosstales.RTVoice.Demo.GUIAudioFilter, 76
- Crosstales.RTVoice.Demo.GUIDialog, 77
- Crosstales.RTVoice.Demo.GUIMain, 78
- Crosstales.RTVoice.Demo.GUIMultiAudioFilter, 79
- Crosstales.RTVoice.Demo.GUIScenes, 80
- Crosstales.RTVoice.Demo.GUISpeech, 81
- Crosstales.RTVoice.Demo.NativeAudio, 90
- Crosstales.RTVoice.Demo.PreGeneratedAudio, 94
- Crosstales.RTVoice.Demo.SendMessage, 100
- Crosstales.RTVoice.Demo.SequenceCaller, 103
- Crosstales.RTVoice.Demo.Simple, 109
- Crosstales.RTVoice.Demo.SimpleNative, 110
- Crosstales.RTVoice.Demo.SpeakWrapper, 132
- Crosstales.RTVoice.Demo.Util, 14
- Crosstales.RTVoice.Demo.Util.iOSController, 84
- Crosstales.RTVoice.Demo.Util.MaterialChanger, 90
- Crosstales.RTVoice.Demo.Util.NativeController, 91
- Crosstales.RTVoice.Demo.Util.PlatformController, 94
- Crosstales.RTVoice.EditorExtension, 14
- Crosstales.RTVoice.EditorExtension.AudioFileGenerator↔Editor, 22
- Crosstales.RTVoice.EditorExtension.Loudspeaker↔Editor, 89
- Crosstales.RTVoice.EditorExtension.SequencerEditor, 106
- Crosstales.RTVoice.EditorExtension.SpeakerEditor, 129
- Crosstales.RTVoice.EditorExtension.SpeechTextEditor, 138
- Crosstales.RTVoice.EditorExtension.TextFileSpeaker↔Editor, 144
- Crosstales.RTVoice.EditorExtension.VoiceInitializer↔Editor, 154
- Crosstales.RTVoice.EditorIntegration, 14
- Crosstales.RTVoice.EditorIntegration.ConfigBase, 49
- Crosstales.RTVoice.EditorIntegration.ConfigPreferences, 50
- Crosstales.RTVoice.EditorIntegration.ConfigWindow, 50
- Crosstales.RTVoice.EditorIntegration.RTVoiceGame↔Object, 97
- Crosstales.RTVoice.EditorIntegration.RTVoiceMenu, 99
- Crosstales.RTVoice.EditorTask, 15
- Crosstales.RTVoice.EditorTask.AutoInitialize, 26
- Crosstales.RTVoice.EditorTask.CompileDefines, 45

- Crosstales.RTVoice.EditorTask.ConfigLoader, [49](#)
- Crosstales.RTVoice.EditorTask.Launch, [84](#)
- Crosstales.RTVoice.EditorTask.ReminderCheck, [97](#)
- Crosstales.RTVoice.EditorTask.SetApiLevel, [107](#)
- Crosstales.RTVoice.EditorTask.SetupResources, [108](#)
- Crosstales.RTVoice.EditorTask.Telemetry, [139](#)
- Crosstales.RTVoice.EditorTask.UpdateCheck, [150](#)
- Crosstales.RTVoice.EditorUtil, [15](#)
- Crosstales.RTVoice.EditorUtil.BuildPostprocessor, [45](#)
- Crosstales.RTVoice.EditorUtil.EditorConfig, [63](#)
- Crosstales.RTVoice.EditorUtil.EditorConstants, [65](#)
- Crosstales.RTVoice.EditorUtil.EditorHelper, [67](#)
- Crosstales.RTVoice.EditorUtil.GAApi, [75](#)
- Crosstales.RTVoice.LiveSpeaker, [84](#)
- Crosstales.RTVoice.Model, [16](#)
- Crosstales.RTVoice.Model.Enum, [16](#)
- Crosstales.RTVoice.Model.Sequence, [101](#)
- Crosstales.RTVoice.Model.Voice, [151](#)
- Crosstales.RTVoice.Model.Wrapper, [167](#)
- Crosstales.RTVoice.PlayMaker, [17](#)
- Crosstales.RTVoice.PlayMaker.SilenceEditor, [109](#)
- Crosstales.RTVoice.PlayMaker.SpeakEditor, [117](#)
- Crosstales.RTVoice.PlayMaker.SpeakUIEditor, [131](#)
- Crosstales.RTVoice.Provider, [17](#)
- Crosstales.RTVoice.Provider.BaseVoiceProvider, [40](#)
- Crosstales.RTVoice.Provider.VoiceProviderAndroid, [154](#)
- Crosstales.RTVoice.Provider.VoiceProviderIOS, [156](#)
- Crosstales.RTVoice.Provider.VoiceProviderMacOS, [159](#)
- Crosstales.RTVoice.Provider.VoiceProviderMary, [161](#)
- Crosstales.RTVoice.Provider.VoiceProviderWSA, [165](#)
- Crosstales.RTVoice.Provider.VoiceProviderWindows, [163](#)
- Crosstales.RTVoice.SALSA.Bots, [44](#)
- Crosstales.RTVoice.SALSA.Speak, [114](#)
- Crosstales.RTVoice.SALSA.Speak2D, [114](#)
- Crosstales.RTVoice.SALSA.SpeakSimple, [130](#)
- Crosstales.RTVoice.SALSA, [17](#)
- Crosstales.RTVoice.Speaker, [117](#)
- Crosstales.RTVoice.Tool, [18](#)
- Crosstales.RTVoice.Tool.AudioFileGenerator, [21](#)
- Crosstales.RTVoice.Tool.Loudspeaker, [87](#)
- Crosstales.RTVoice.Tool.Sequencer, [104](#)
- Crosstales.RTVoice.Tool.SpeechText, [133](#)
- Crosstales.RTVoice.Tool.TextFileSpeaker, [140](#)
- Crosstales.RTVoice.Tool.VoiceInitializer, [153](#)
- Crosstales.RTVoice.UDEA2, [18](#)
- Crosstales.RTVoice.UDEA2.UDEAConnector, [144](#)
- Crosstales.RTVoice.UDEA2.UDEAConnectorEditor, [145](#)
- Crosstales.RTVoice.UDEA2.UDEAVoiceWrapper, [146](#)
- Crosstales.RTVoice.Util, [18](#)
- Crosstales.RTVoice.Util.Config, [46](#)
- Crosstales.RTVoice.Util.Constants, [51](#)
- Crosstales.RTVoice.Util.Helper, [82](#)
- Crosstales.UI.Social, [111](#)
- Crosstales.UI.StaticManager, [139](#)
- Crosstales.UI.UIDrag, [148](#)
- Crosstales.UI.UIFocus, [149](#)
- Crosstales.UI.UIWindowManager, [150](#)
- Crosstales.UI.Util, [19](#)
- Crosstales.UI.Util.AudioFilterController, [23](#)
- Crosstales.UI.Util.AudioSourceController, [24](#)
- Crosstales.UI.Util.FPSDisplay, [75](#)
- Crosstales.UI.Util.ScrollRectHandler, [99](#)
- Crosstales.UI.WindowManager, [166](#)
- Crosstales.UI, [19](#)
- Crosstales::Common::EditorUtil::BaseGAApiEvent, [31](#)
- Crosstales::Common::UtilPlatform, [12](#)
- Crosstales::Common::Util::BaseConstants
 - ASSET_3P_PLAYMAKER, [28](#)
 - ASSET_AUTHOR_URL, [29](#)
 - ASSET_AUTHOR, [28](#)
 - ASSET_CT_URL, [29](#)
 - ASSET_SOCIAL_FACEBOOK, [29](#)
 - ASSET_SOCIAL_LINKEDIN, [29](#)
 - ASSET_SOCIAL_TWITTER, [29](#)
 - ASSET_SOCIAL_XING, [29](#)
 - ASSET_SOCIAL_YOUTUBE, [29](#)
 - DEV_DEBUG, [29](#)
 - FACTOR_GB, [29](#)
 - FACTOR_KB, [30](#)
 - FACTOR_MB, [30](#)
 - FLOAT_32768, [30](#)
 - FORMAT_NO_DECIMAL_PLACES, [30](#)
 - FORMAT_PERCENT, [30](#)
 - FORMAT_TWO_DECIMAL_PLACES, [30](#)
 - PATH_DELIMITER_UNIX, [30](#)
 - PATH_DELIMITER_WINDOWS, [30](#)
- Crosstales::Common::Util::BaseHelper
 - ClearLineEndings, [33](#)
 - ClearSpaces, [33](#)
 - ClearTags, [34](#)
 - FormatBytesToHRF, [34](#)
 - FormatSecondsToHourMinSec, [34](#)
 - HSVToRGB, [34](#)
 - isAndroidPlatform, [36](#)
 - isAppleBasedPlatform, [36](#)
 - isEditor, [37](#)
 - isEditorMode, [37](#)
 - isIOSPlatform, [37](#)
 - isInternetAvailable, [37](#)
 - isLinuxPlatform, [37](#)
 - isMacOSPlatform, [37](#)
 - isStandalonePlatform, [38](#)
 - isValidURL, [35](#)
 - isWSAPlatform, [39](#)
 - isWebGLPlatform, [38](#)
 - isWebPlatform, [38](#)
 - isWebPlayerPlatform, [38](#)
 - isWindowsBasedPlatform, [38](#)
 - isWindowsPlatform, [38](#)
 - RemoteCertificateValidationCallback, [35](#)
 - SplitStringToLines, [35](#)
 - ValidURLFromFilePath, [36](#)

- ValidateFile, [35](#)
- ValidatePath, [36](#)
- Crosstales::Common::Util::CTPlayerPrefs
 - DeleteAll, [58](#)
 - DeleteKey, [58](#)
 - GetBool, [59](#)
 - GetFloat, [59](#)
 - GetInt, [59](#)
 - GetString, [59](#)
 - HasKey, [60](#)
 - Save, [60](#)
 - SetBool, [60](#)
 - SetFloat, [60](#)
 - SetInt, [60](#)
 - SetString, [61](#)
- Crosstales::Common::Util::CTWebClient
 - ConnectionLimit, [62](#)
 - Timeout, [62](#)
- Crosstales::Common::Util::PlatformController
 - Objects, [93](#)
 - Platforms, [93](#)
- Crosstales::ExtensionMethods
 - CTAddRange< T, S >, [70](#)
 - CTContains, [71](#)
 - CTContainsAll, [71](#)
 - CTContainsAny, [71](#)
 - CTDump< T >, [71](#), [72](#)
 - CTEquals, [72](#)
 - CTReplace, [72](#)
 - CTShuffle< T >, [73](#)
 - CTToString< T >, [73](#)
 - CTToTitleCase, [74](#)
- Crosstales::RTVoice::Demo::Util::NativeController
 - Active, [91](#)
 - Objects, [91](#)
- Crosstales::RTVoice::EditorTask
 - UpdateStatus, [15](#)
- Crosstales::RTVoice::EditorUtil::EditorConfig
 - ASSET_PATH, [65](#)
 - HIERARCHY_ICON, [64](#)
 - isLoading, [64](#)
 - Load, [64](#)
 - PREFAB_AUTOLOAD, [64](#)
 - PREFAB_PATH, [65](#)
 - REMINDER_CHECK, [64](#)
 - Reset, [64](#)
 - Save, [64](#)
 - TELEMETRY, [65](#)
 - UPDATE_CHECK, [65](#)
- Crosstales::RTVoice::EditorUtil::EditorConstants
 - ASSET_UID, [66](#)
 - ASSET_URL, [66](#)
 - PREFAB_SUBPATH, [66](#)
- Crosstales::RTVoice::EditorUtil::EditorHelper
 - GO_ID, [69](#)
 - InstantiatePrefab, [68](#)
 - isRTVoiceInScene, [69](#)
 - MENU_ID, [69](#)
 - NoVoicesUI, [68](#)
 - SeparatorUI, [68](#)
- Crosstales::RTVoice::EditorUtil::GAApi
 - Event, [76](#)
- Crosstales::RTVoice::LiveSpeaker
 - SetState, [85](#)
 - SetVoices, [85](#)
 - Silence, [85](#)
 - Speak, [86](#)
 - SpeakNative, [86](#), [87](#)
 - WordSpoken, [87](#)
- Crosstales::RTVoice::Model::Enum
 - MaryTTSType, [16](#)
 - ProviderType, [16](#)
 - SpeakMode, [16](#)
- Crosstales::RTVoice::Model::Sequence
 - Mode, [102](#)
 - Pitch, [102](#)
 - RTVoiceName, [103](#)
 - RTVoiceNameAndroid, [102](#)
 - RTVoiceNameIOS, [102](#)
 - RTVoiceNameMac, [102](#)
 - RTVoiceNameWSA, [102](#)
 - RTVoiceNameWindows, [102](#)
 - Rate, [102](#)
 - Source, [102](#)
 - Text, [102](#)
 - Volume, [103](#)
- Crosstales::RTVoice::Model::Voice
 - Age, [152](#)
 - Culture, [152](#)
 - Description, [152](#)
 - Gender, [152](#)
 - Name, [152](#)
 - Voice, [151](#), [152](#)
- Crosstales::RTVoice::Model::Wrapper
 - Created, [170](#)
 - OutputFile, [169](#)
 - Pitch, [170](#)
 - Rate, [170](#)
 - Source, [169](#)
 - SpeakImmediately, [169](#)
 - Text, [170](#)
 - Uid, [169](#)
 - Voice, [170](#)
 - Volume, [170](#)
 - Wrapper, [168](#), [169](#)
- Crosstales::RTVoice::Provider::BaseVoiceProvider
 - AudioFileExtension, [43](#)
 - BaseVoiceProvider, [41](#)
 - Generate, [41](#)
 - OnErrorInfo, [43](#)
 - OnSpeakAudioGenerationComplete, [43](#)
 - OnSpeakAudioGenerationStart, [43](#)
 - OnSpeakComplete, [43](#)
 - OnSpeakCurrentPhoneme, [43](#)
 - OnSpeakCurrentViseme, [43](#)
 - OnSpeakCurrentWord, [44](#)

- OnSpeakStart, [44](#)
- OnVoicesReady, [44](#)
- Silence, [42](#)
- Speak, [42](#)
- SpeakNative, [42](#)
- Voices, [44](#)
- Crosstales::RTVoice::Provider::VoiceProviderAndroid
 - Generate, [155](#)
 - Silence, [156](#)
 - Speak, [156](#)
 - SpeakNative, [156](#)
 - VoiceProviderAndroid, [155](#)
- Crosstales::RTVoice::Provider::VoiceProviderIOS
 - Generate, [157](#)
 - SetState, [158](#)
 - SetVoices, [158](#)
 - Silence, [158](#)
 - Speak, [158](#)
 - SpeakNative, [158](#)
 - VoiceProviderIOS, [157](#)
 - WordSpoken, [159](#)
- Crosstales::RTVoice::Provider::VoiceProviderMacOS
 - Generate, [160](#)
 - Speak, [160](#)
 - SpeakNative, [160](#)
 - VoiceProviderMacOS, [160](#)
- Crosstales::RTVoice::Provider::VoiceProviderMary
 - Generate, [162](#)
 - Silence, [162](#)
 - Speak, [162](#)
 - SpeakNative, [162](#)
 - VoiceProviderMary, [161](#)
- Crosstales::RTVoice::Provider::VoiceProviderWSA
 - Generate, [165](#)
 - Silence, [166](#)
 - Speak, [166](#)
 - SpeakNative, [166](#)
 - VoiceProviderWSA, [165](#)
- Crosstales::RTVoice::Provider::VoiceProviderWindows
 - Generate, [164](#)
 - Speak, [164](#)
 - SpeakNative, [164](#)
 - VoiceProviderWindows, [163](#)
- Crosstales::RTVoice::Speaker
 - ApproximateSpeechLength, [120](#)
 - AudioFileExtension, [126](#)
 - AutoClearTags, [125](#)
 - Cultures, [126](#)
 - DontDestroy, [125](#)
 - Generate, [120](#), [121](#)
 - isAutoClearTags, [127](#)
 - isMaryMode, [127](#)
 - isSilenceOnDisable, [127](#)
 - isSilenceOnFocusLost, [127](#)
 - isSpeaking, [127](#)
 - isTTSAvailable, [127](#)
 - isVoiceForCultureAvailable, [121](#)
 - isVoiceForNameAvailable, [121](#)
 - MaryPassword, [127](#)
 - MaryPort, [127](#)
 - MaryTTSMODE, [125](#)
 - MaryTTSPassword, [125](#)
 - MaryTTSPort, [126](#)
 - MaryTSType, [126](#)
 - MaryTTSUrl, [126](#)
 - MaryTTSUser, [126](#)
 - MaryType, [128](#)
 - MaryUrl, [128](#)
 - MaryUser, [128](#)
 - OnErrorInfo, [128](#)
 - OnProviderChange, [128](#)
 - OnSpeakAudioGenerationComplete, [128](#)
 - OnSpeakAudioGenerationStart, [128](#)
 - OnSpeakComplete, [128](#)
 - OnSpeakCurrentPhoneme, [128](#)
 - OnSpeakCurrentViseme, [128](#)
 - OnSpeakCurrentWord, [129](#)
 - OnSpeakStart, [129](#)
 - OnVoicesReady, [129](#)
 - Silence, [122](#)
 - SilenceOnDisable, [126](#)
 - SilenceOnFocusLost, [126](#)
 - Speak, [122](#)
 - SpeakMarkedWordsWithUID, [123](#)
 - SpeakNative, [123](#), [124](#)
 - SpeakNativeWithUID, [124](#)
 - SpeakWithUID, [124](#)
 - VoiceForCulture, [124](#)
 - VoiceForName, [125](#)
 - Voices, [129](#)
 - VoicesForCulture, [125](#)
- Crosstales::RTVoice::Tool::AudioFileGenerator
 - FileInsideAssets, [22](#)
 - Generate, [22](#)
 - TextFiles, [22](#)
- Crosstales::RTVoice::Tool::Loudspeaker
 - isSilenceSource, [89](#)
 - isSynchronized, [89](#)
 - SilenceSource, [88](#)
 - Source, [88](#)
 - Synchronized, [88](#)
- Crosstales::RTVoice::Tool::Sequencer
 - Culture, [105](#)
 - CurrentCulture, [106](#)
 - CurrentSequence, [106](#)
 - Delay, [105](#)
 - PlayAllSequences, [105](#)
 - PlayNextSequence, [105](#)
 - PlayOnStart, [105](#)
 - PlaySequence, [105](#)
 - Sequences, [106](#)
 - StopAllSequences, [105](#)
- Crosstales::RTVoice::Tool::SpeechText
 - Culture, [135](#)
 - CurrentCulture, [137](#)
 - CurrentPitch, [137](#)

- CurrentRate, [137](#)
- CurrentText, [137](#)
- CurrentVolume, [137](#)
- Delay, [135](#)
- FileInsideAssets, [135](#)
- FileName, [135](#)
- FilePath, [136](#)
- GenerateAudioFile, [136](#)
- Mode, [136](#)
- Pitch, [136](#)
- PlayOnStart, [136](#)
- RTVoiceName, [138](#)
- RTVoiceNameAndroid, [136](#)
- RTVoiceNameIOS, [136](#)
- RTVoiceNameMac, [136](#)
- RTVoiceNameMaryTTS, [136](#)
- RTVoiceNameWSA, [137](#)
- RTVoiceNameWindows, [137](#)
- Rate, [136](#)
- Silence, [135](#)
- Source, [137](#)
- Speak, [135](#)
- Text, [137](#)
- Volume, [137](#)
- Crosstales::RTVoice::Tool::TextFileSpeaker
 - Culture, [142](#)
 - CurrentCulture, [143](#)
 - CurrentPitch, [143](#)
 - CurrentRate, [143](#)
 - CurrentVolume, [143](#)
 - Delay, [142](#)
 - Mode, [142](#)
 - Pitch, [142](#)
 - PlayOnStart, [142](#)
 - RTVoiceName, [143](#)
 - RTVoiceNameAndroid, [142](#)
 - RTVoiceNameIOS, [142](#)
 - RTVoiceNameMac, [142](#)
 - RTVoiceNameMaryTTS, [142](#)
 - RTVoiceNameWSA, [143](#)
 - RTVoiceNameWindows, [143](#)
 - Rate, [142](#)
 - Silence, [141](#)
 - Source, [143](#)
 - Speak, [141](#)
 - SpeakText, [141](#)
 - TextFiles, [143](#)
 - Volume, [143](#)
- Crosstales::RTVoice::Tool::VoiceInitializer
 - AllVoices, [153](#)
 - DestroyWhenFinished, [153](#)
 - Provider, [153](#)
 - VoiceNames, [153](#)
- Crosstales::RTVoice::UDEA2::UDEAConnector
 - Culture, [145](#)
 - Voices, [145](#)
- Crosstales::RTVoice::UDEA2::UDEAVoiceWrapper
 - IgnoreCharacter, [147](#)
- Pitch, [147](#)
- RTVoiceName, [148](#)
- RTVoiceNameAndroid, [147](#)
- RTVoiceNameIOS, [147](#)
- RTVoiceNameMac, [147](#)
- RTVoiceNameMaryTTS, [147](#)
- RTVoiceNameWSA, [147](#)
- RTVoiceNameWindows, [147](#)
- Rate, [147](#)
- Source, [148](#)
- UDEAVoiceName, [148](#)
- Volume, [148](#)
- Crosstales::RTVoice::Util::Config
 - ASSET_PATH, [47](#)
 - AUDIOFILE_AUTOMATIC_DELETE, [47](#)
 - AUDIOFILE_PATH, [47](#)
 - DEBUG, [47](#)
 - ENFORCE_32BIT_WINDOWS, [48](#)
 - isLoaded, [48](#)
 - Load, [47](#)
 - Reset, [47](#)
 - Save, [47](#)
 - TTS_MACOS, [48](#)
 - TTS_WINDOWS_BUILD, [48](#)
 - TTS_WINDOWS_EDITOR_x86, [48](#)
 - TTS_WINDOWS_EDITOR, [48](#)
- Crosstales::RTVoice::Util::Constants
 - ASSET_3P_ADVENTURE_CREATOR, [53](#)
 - ASSET_3P_CINEMA_DIRECTOR, [53](#)
 - ASSET_3P_DIALOG_SYSTEM, [53](#)
 - ASSET_3P_DIALOGUE_ENGINE, [54](#)
 - ASSET_3P_LIPSYNC, [54](#)
 - ASSET_3P_LOCALIZED_DIALOGS, [54](#)
 - ASSET_3P_NPC_CHAT, [54](#)
 - ASSET_3P_QUEST_SYSTEM, [54](#)
 - ASSET_3P_SALSA, [54](#)
 - ASSET_3P_SLATE, [54](#)
 - ASSET_3P_URL, [54](#)
 - ASSET_3P_USEQUENCER, [54](#)
 - ASSET_API_URL, [55](#)
 - ASSET_BUILD, [55](#)
 - ASSET_CHANGED, [55](#)
 - ASSET_CONTACT, [55](#)
 - ASSET_CREATED, [55](#)
 - ASSET_FORUM_URL, [55](#)
 - ASSET_MANUAL_URL, [55](#)
 - ASSET_NAME, [55](#)
 - ASSET_PRO_URL, [55](#)
 - ASSET_UPDATE_CHECK_URL, [56](#)
 - ASSET_VERSION, [56](#)
 - ASSET_VIDEO_PROMO, [56](#)
 - ASSET_VIDEO_TUTORIAL, [56](#)
 - ASSET_WEB_URL, [56](#)
 - isPro, [56](#)
 - RTVOICE_SCENE_OBJECT_NAME, [56](#)
 - TTS_WINDOWS_SUBPATH, [56](#)
 - TTS_WINDOWS_x86_SUBPATH, [56](#)
- Crosstales::RTVoice::Util::Helper

- CleanText, [82](#)
- CurrentProviderType, [83](#)
- hasBuiltInTTS, [83](#)
- MarkSpokenText, [83](#)
- Crosstales::UI::UIWindowManager
 - Windows, [150](#)
- Crosstales::UI::Util::AudioFilterController
 - FindAllAudioFiltersOnStart, [24](#)
- Crosstales::UI::Util::AudioSourceController
 - AudioSources, [25](#)
 - FindAllAudioSourcesOnStart, [25](#)
 - Loop, [25](#)
 - Mute, [25](#)
 - Pitch, [25](#)
 - ResetAudioSourcesOnStart, [26](#)
 - StereoPan, [26](#)
 - Volume, [26](#)
- Crosstales::UI::WindowManager
 - Dependencies, [167](#)
 - Speed, [167](#)
- Culture
 - Crosstales::RTVoice::Model::Voice, [152](#)
 - Crosstales::RTVoice::Tool::Sequencer, [105](#)
 - Crosstales::RTVoice::Tool::SpeechText, [135](#)
 - Crosstales::RTVoice::Tool::TextFileSpeaker, [142](#)
 - Crosstales::RTVoice::UDEA2::UDEAConnector, [145](#)
 - HutongGames::PlayMaker::Actions::Speak, [113](#)
 - HutongGames::PlayMaker::Actions::SpeakUI, [131](#)
- Cultures
 - Crosstales::RTVoice::Speaker, [126](#)
- CurrentCulture
 - Crosstales::RTVoice::Tool::Sequencer, [106](#)
 - Crosstales::RTVoice::Tool::SpeechText, [137](#)
 - Crosstales::RTVoice::Tool::TextFileSpeaker, [143](#)
- CurrentPitch
 - Crosstales::RTVoice::Tool::SpeechText, [137](#)
 - Crosstales::RTVoice::Tool::TextFileSpeaker, [143](#)
- CurrentProviderType
 - Crosstales::RTVoice::Util::Helper, [83](#)
- CurrentRate
 - Crosstales::RTVoice::Tool::SpeechText, [137](#)
 - Crosstales::RTVoice::Tool::TextFileSpeaker, [143](#)
- CurrentSequence
 - Crosstales::RTVoice::Tool::Sequencer, [106](#)
- CurrentText
 - Crosstales::RTVoice::Tool::SpeechText, [137](#)
- CurrentVolume
 - Crosstales::RTVoice::Tool::SpeechText, [137](#)
 - Crosstales::RTVoice::Tool::TextFileSpeaker, [143](#)
- DEBUG
 - Crosstales::RTVoice::Util::Config, [47](#)
- DEV_DEBUG
 - Crosstales::Common::Util::BaseConstants, [29](#)
- Delay
 - Crosstales::RTVoice::Tool::Sequencer, [105](#)
 - Crosstales::RTVoice::Tool::SpeechText, [135](#)
 - Crosstales::RTVoice::Tool::TextFileSpeaker, [142](#)
- DeleteAll
 - Crosstales::Common::Util::CTPlayerPrefs, [58](#)
- DeleteKey
 - Crosstales::Common::Util::CTPlayerPrefs, [58](#)
- Dependencies
 - Crosstales::UI::WindowManager, [167](#)
- Description
 - Crosstales::RTVoice::Model::Voice, [152](#)
- DestroyWhenFinished
 - Crosstales::RTVoice::Tool::VoiceInitializer, [153](#)
- DontDestroy
 - Crosstales::RTVoice::Speaker, [125](#)
- ENFORCE_32BIT_WINDOWS
 - Crosstales::RTVoice::Util::Config, [48](#)
- Event
 - Crosstales::Common::EditorUtil::BaseGAApi, [31](#)
 - Crosstales::RTVoice::EditorUtil::GAApi, [76](#)
- FACTOR_GB
 - Crosstales::Common::Util::BaseConstants, [29](#)
- FACTOR_KB
 - Crosstales::Common::Util::BaseConstants, [30](#)
- FACTOR_MB
 - Crosstales::Common::Util::BaseConstants, [30](#)
- FLOAT_32768
 - Crosstales::Common::Util::BaseConstants, [30](#)
- FORMAT_NO_DECIMAL_PLACES
 - Crosstales::Common::Util::BaseConstants, [30](#)
- FORMAT_PERCENT
 - Crosstales::Common::Util::BaseConstants, [30](#)
- FORMAT_TWO_DECIMAL_PLACES
 - Crosstales::Common::Util::BaseConstants, [30](#)
- FileInsideAssets
 - Crosstales::RTVoice::Tool::AudioFileGenerator, [22](#)
 - Crosstales::RTVoice::Tool::SpeechText, [135](#)
- FileName
 - Crosstales::RTVoice::Tool::SpeechText, [135](#)
- FilePath
 - Crosstales::RTVoice::Tool::SpeechText, [136](#)
- FindAllAudioFiltersOnStart
 - Crosstales::UI::Util::AudioFilterController, [24](#)
- FindAllAudioSourcesOnStart
 - Crosstales::UI::Util::AudioSourceController, [25](#)
- FormatBytesToHRF
 - Crosstales::Common::Util::BaseHelper, [34](#)
- FormatSecondsToHourMinSec
 - Crosstales::Common::Util::BaseHelper, [34](#)
- GO_ID
 - Crosstales::RTVoice::EditorUtil::EditorHelper, [69](#)
- Gender
 - Crosstales::RTVoice::Model::Voice, [152](#)
- Generate
 - Crosstales::RTVoice::Provider::BaseVoice↔
Provider, [41](#)
 - Crosstales::RTVoice::Provider::VoiceProvider↔
Android, [155](#)

- Crosstales::RTVoice::Provider::VoiceProviderIOS, 157
- Crosstales::RTVoice::Provider::VoiceProvider↔ MacOS, 160
- Crosstales::RTVoice::Provider::VoiceProviderMary, 162
- Crosstales::RTVoice::Provider::VoiceProviderW↔ SA, 165
- Crosstales::RTVoice::Provider::VoiceProvider↔ Windows, 164
- Crosstales::RTVoice::Speaker, 120, 121
- Crosstales::RTVoice::Tool::AudioFileGenerator, 22
- GenerateAudioFile
 - Crosstales::RTVoice::Tool::SpeechText, 136
- GetBool
 - Crosstales::Common::Util::CTPlayerPrefs, 59
- GetFloat
 - Crosstales::Common::Util::CTPlayerPrefs, 59
- GetInt
 - Crosstales::Common::Util::CTPlayerPrefs, 59
- GetString
 - Crosstales::Common::Util::CTPlayerPrefs, 59
- HIERARCHY_ICON
 - Crosstales::RTVoice::EditorUtil::EditorConfig, 64
- HSVToRGB
 - Crosstales::Common::Util::BaseHelper, 34
- hasBuiltInTTS
 - Crosstales::RTVoice::Util::Helper, 83
- HasKey
 - Crosstales::Common::Util::CTPlayerPrefs, 60
- HutongGames, 19
- HutongGames.PlayMaker, 19
- HutongGames.PlayMaker.Actions, 19
- HutongGames.PlayMaker.Actions.Silence, 108
- HutongGames.PlayMaker.Actions.Speak, 112
- HutongGames.PlayMaker.Actions.SpeakBase, 115
- HutongGames.PlayMaker.Actions.SpeakUI, 130
- HutongGames::PlayMaker::Actions::Speak
 - Culture, 113
 - RTVoiceNameAndroid, 113
 - RTVoiceNameIOS, 113
 - RTVoiceNameMac, 113
 - RTVoiceNameMaryTTS, 113
 - RTVoiceNameWSA, 113
 - RTVoiceNameWindows, 113
 - Text, 113
- HutongGames::PlayMaker::Actions::SpeakBase
 - AudioSource, 116
 - Mode, 116
 - Pitch, 116
 - Rate, 116
 - Volume, 116
- HutongGames::PlayMaker::Actions::SpeakUI
 - Culture, 131
 - RTVoiceName, 131
 - Text, 131
- IgnoreCharacter
- Crosstales::RTVoice::UDEA2::UDEAVoice↔ Wrapper, 147
- InstantiatePrefab
 - Crosstales::RTVoice::EditorUtil::EditorHelper, 68
- isAndroidPlatform
 - Crosstales::Common::Util::BaseHelper, 36
- isAppleBasedPlatform
 - Crosstales::Common::Util::BaseHelper, 36
- isAutoClearTags
 - Crosstales::RTVoice::Speaker, 127
- isEditor
 - Crosstales::Common::Util::BaseHelper, 37
- isEditorMode
 - Crosstales::Common::Util::BaseHelper, 37
- isIOSPlatform
 - Crosstales::Common::Util::BaseHelper, 37
- isInternetAvailable
 - Crosstales::Common::Util::BaseHelper, 37
- isLinuxPlatform
 - Crosstales::Common::Util::BaseHelper, 37
- isLoading
 - Crosstales::RTVoice::EditorUtil::EditorConfig, 64
 - Crosstales::RTVoice::Util::Config, 48
- isMacOSPlatform
 - Crosstales::Common::Util::BaseHelper, 37
- isMaryMode
 - Crosstales::RTVoice::Speaker, 127
- isPro
 - Crosstales::RTVoice::Util::Constants, 56
- isRTVoiceInScene
 - Crosstales::RTVoice::EditorUtil::EditorHelper, 69
- isSilenceOnDisable
 - Crosstales::RTVoice::Speaker, 127
- isSilenceOnFocustLost
 - Crosstales::RTVoice::Speaker, 127
- isSilenceSource
 - Crosstales::RTVoice::Tool::Loudspeaker, 89
- isSpeaking
 - Crosstales::RTVoice::Speaker, 127
- isStandalonePlatform
 - Crosstales::Common::Util::BaseHelper, 38
- isSynchronized
 - Crosstales::RTVoice::Tool::Loudspeaker, 89
- isTTSAvailable
 - Crosstales::RTVoice::Speaker, 127
- isValidURL
 - Crosstales::Common::Util::BaseHelper, 35
- isVoiceForCultureAvailable
 - Crosstales::RTVoice::Speaker, 121
- isVoiceForNameAvailable
 - Crosstales::RTVoice::Speaker, 121
- isWSAPlatform
 - Crosstales::Common::Util::BaseHelper, 39
- isWebGLPlatform
 - Crosstales::Common::Util::BaseHelper, 38
- isWebPlatform
 - Crosstales::Common::Util::BaseHelper, 38
- isWebPlayerPlatform

- Crosstales::Common::Util::BaseHelper, 38
- isWindowsBasedPlatform
 - Crosstales::Common::Util::BaseHelper, 38
- isWindowsPlatform
 - Crosstales::Common::Util::BaseHelper, 38
- Load
 - Crosstales::RTVoice::EditorUtil::EditorConfig, 64
 - Crosstales::RTVoice::Util::Config, 47
- Loop
 - Crosstales::UI::Util::AudioSourceController, 25
- MENU_ID
 - Crosstales::RTVoice::EditorUtil::EditorHelper, 69
- MarkSpokenText
 - Crosstales::RTVoice::Util::Helper, 83
- MaryPassword
 - Crosstales::RTVoice::Speaker, 127
- MaryPort
 - Crosstales::RTVoice::Speaker, 127
- MaryTTSMODE
 - Crosstales::RTVoice::Speaker, 125
- MaryTTSPassword
 - Crosstales::RTVoice::Speaker, 125
- MaryTTSPort
 - Crosstales::RTVoice::Speaker, 126
- MaryTTSType
 - Crosstales::RTVoice::Model::Enum, 16
 - Crosstales::RTVoice::Speaker, 126
- MaryTTSUrl
 - Crosstales::RTVoice::Speaker, 126
- MaryTTSUser
 - Crosstales::RTVoice::Speaker, 126
- MaryType
 - Crosstales::RTVoice::Speaker, 128
- MaryUrl
 - Crosstales::RTVoice::Speaker, 128
- MaryUser
 - Crosstales::RTVoice::Speaker, 128
- Mode
 - Crosstales::RTVoice::Model::Sequence, 102
 - Crosstales::RTVoice::Tool::SpeechText, 136
 - Crosstales::RTVoice::Tool::TextFileSpeaker, 142
 - HutongGames::PlayMaker::Actions::SpeakBase, 116
- Mute
 - Crosstales::UI::Util::AudioSourceController, 25
- Name
 - Crosstales::RTVoice::Model::Voice, 152
- NoVoicesUI
 - Crosstales::RTVoice::EditorUtil::EditorHelper, 68
- Objects
 - Crosstales::Common::Util::PlatformController, 93
 - Crosstales::RTVoice::Demo::Util::NativeController, 91
- OnErrorInfo
 - Crosstales::RTVoice::Provider::BaseVoice↔ Provider, 43
 - Crosstales::RTVoice::Speaker, 128
- OnProviderChange
 - Crosstales::RTVoice::Speaker, 128
- OnSpeakAudioGenerationComplete
 - Crosstales::RTVoice::Provider::BaseVoice↔ Provider, 43
 - Crosstales::RTVoice::Speaker, 128
- OnSpeakAudioGenerationStart
 - Crosstales::RTVoice::Provider::BaseVoice↔ Provider, 43
 - Crosstales::RTVoice::Speaker, 128
- OnSpeakComplete
 - Crosstales::RTVoice::Provider::BaseVoice↔ Provider, 43
 - Crosstales::RTVoice::Speaker, 128
- OnSpeakCurrentPhoneme
 - Crosstales::RTVoice::Provider::BaseVoice↔ Provider, 43
 - Crosstales::RTVoice::Speaker, 128
- OnSpeakCurrentViseme
 - Crosstales::RTVoice::Provider::BaseVoice↔ Provider, 43
 - Crosstales::RTVoice::Speaker, 128
- OnSpeakCurrentWord
 - Crosstales::RTVoice::Provider::BaseVoice↔ Provider, 44
 - Crosstales::RTVoice::Speaker, 129
- OnSpeakStart
 - Crosstales::RTVoice::Provider::BaseVoice↔ Provider, 44
 - Crosstales::RTVoice::Speaker, 129
- OnVoicesReady
 - Crosstales::RTVoice::Provider::BaseVoice↔ Provider, 44
 - Crosstales::RTVoice::Speaker, 129
- OutputFile
 - Crosstales::RTVoice::Model::Wrapper, 169
- PATH_DELIMITER_UNIX
 - Crosstales::Common::Util::BaseConstants, 30
- PATH_DELIMITER_WINDOWS
 - Crosstales::Common::Util::BaseConstants, 30
- PREFAB_AUTOLOAD
 - Crosstales::RTVoice::EditorUtil::EditorConfig, 64
- PREFAB_PATH
 - Crosstales::RTVoice::EditorUtil::EditorConfig, 65
- PREFAB_SUBPATH
 - Crosstales::RTVoice::EditorUtil::EditorConstants, 66
- Pitch
 - Crosstales::RTVoice::Model::Sequence, 102
 - Crosstales::RTVoice::Model::Wrapper, 170
 - Crosstales::RTVoice::Tool::SpeechText, 136
 - Crosstales::RTVoice::Tool::TextFileSpeaker, 142
 - Crosstales::RTVoice::UDEA2::UDEAVoice↔ Wrapper, 147
 - Crosstales::UI::Util::AudioSourceController, 25

- HutongGames::PlayMaker::Actions::SpeakBase, 116
- Platform
 - Crosstales::Common::Util, 12
- Platforms
 - Crosstales::Common::Util::PlatformController, 93
- PlayAllSequences
 - Crosstales::RTVoice::Tool::Sequencer, 105
- PlayNextSequence
 - Crosstales::RTVoice::Tool::Sequencer, 105
- PlayOnStart
 - Crosstales::RTVoice::Tool::Sequencer, 105
 - Crosstales::RTVoice::Tool::SpeechText, 136
 - Crosstales::RTVoice::Tool::TextFileSpeaker, 142
- PlaySequence
 - Crosstales::RTVoice::Tool::Sequencer, 105
- Provider
 - Crosstales::RTVoice::Tool::VoiceInitializer, 153
- ProviderType
 - Crosstales::RTVoice::Model::Enum, 16
- REMINDER_CHECK
 - Crosstales::RTVoice::EditorUtil::EditorConfig, 64
- RTVOICE_SCENE_OBJECT_NAME
 - Crosstales::RTVoice::Util::Constants, 56
- RTVoiceIOSBridge, 98
 - setVoices, 98
 - speak:text:rate:pitch:volume:, 98
 - stop, 98
- RTVoiceIOSBridge(), 99
- RTVoiceName
 - Crosstales::RTVoice::Model::Sequence, 103
 - Crosstales::RTVoice::Tool::SpeechText, 138
 - Crosstales::RTVoice::Tool::TextFileSpeaker, 143
 - Crosstales::RTVoice::UDEA2::UDEAVoice↔
 - Wrapper, 148
 - HutongGames::PlayMaker::Actions::SpeakUI, 131
- RTVoiceNameAndroid
 - Crosstales::RTVoice::Model::Sequence, 102
 - Crosstales::RTVoice::Tool::SpeechText, 136
 - Crosstales::RTVoice::Tool::TextFileSpeaker, 142
 - Crosstales::RTVoice::UDEA2::UDEAVoice↔
 - Wrapper, 147
 - HutongGames::PlayMaker::Actions::Speak, 113
- RTVoiceNameIOS
 - Crosstales::RTVoice::Model::Sequence, 102
 - Crosstales::RTVoice::Tool::SpeechText, 136
 - Crosstales::RTVoice::Tool::TextFileSpeaker, 142
 - Crosstales::RTVoice::UDEA2::UDEAVoice↔
 - Wrapper, 147
 - HutongGames::PlayMaker::Actions::Speak, 113
- RTVoiceNameMac
 - Crosstales::RTVoice::Model::Sequence, 102
 - Crosstales::RTVoice::Tool::SpeechText, 136
 - Crosstales::RTVoice::Tool::TextFileSpeaker, 142
 - Crosstales::RTVoice::UDEA2::UDEAVoice↔
 - Wrapper, 147
 - HutongGames::PlayMaker::Actions::Speak, 113
- RTVoiceNameMaryTTS
 - Crosstales::RTVoice::Tool::SpeechText, 136
 - Crosstales::RTVoice::Tool::TextFileSpeaker, 142
 - Crosstales::RTVoice::UDEA2::UDEAVoice↔
 - Wrapper, 147
 - HutongGames::PlayMaker::Actions::Speak, 113
- RTVoiceNameWSA
 - Crosstales::RTVoice::Model::Sequence, 102
 - Crosstales::RTVoice::Tool::SpeechText, 137
 - Crosstales::RTVoice::Tool::TextFileSpeaker, 143
 - Crosstales::RTVoice::UDEA2::UDEAVoice↔
 - Wrapper, 147
 - HutongGames::PlayMaker::Actions::Speak, 113
- RTVoiceNameWindows
 - Crosstales::RTVoice::Model::Sequence, 102
 - Crosstales::RTVoice::Tool::SpeechText, 137
 - Crosstales::RTVoice::Tool::TextFileSpeaker, 143
 - Crosstales::RTVoice::UDEA2::UDEAVoice↔
 - Wrapper, 147
 - HutongGames::PlayMaker::Actions::Speak, 113
- Rate
 - Crosstales::RTVoice::Model::Sequence, 102
 - Crosstales::RTVoice::Model::Wrapper, 170
 - Crosstales::RTVoice::Tool::SpeechText, 136
 - Crosstales::RTVoice::Tool::TextFileSpeaker, 142
 - Crosstales::RTVoice::UDEA2::UDEAVoice↔
 - Wrapper, 147
 - HutongGames::PlayMaker::Actions::SpeakBase, 116
- RemoteCertificateValidationCallback
 - Crosstales::Common::Util::BaseHelper, 35
- Reset
 - Crosstales::RTVoice::EditorUtil::EditorConfig, 64
 - Crosstales::RTVoice::Util::Config, 47
- ResetAudioSourcesOnStart
 - Crosstales::UI::Util::AudioSourceController, 26
- Save
 - Crosstales::Common::Util::CTPlayerPrefs, 60
 - Crosstales::RTVoice::EditorUtil::EditorConfig, 64
 - Crosstales::RTVoice::Util::Config, 47
- SeparatorUI
 - Crosstales::RTVoice::EditorUtil::EditorHelper, 68
- Sequences
 - Crosstales::RTVoice::Tool::Sequencer, 106
- SetBool
 - Crosstales::Common::Util::CTPlayerPrefs, 60
- SetFloat
 - Crosstales::Common::Util::CTPlayerPrefs, 60
- SetInt
 - Crosstales::Common::Util::CTPlayerPrefs, 60
- SetState
 - Crosstales::RTVoice::LiveSpeaker, 85
 - Crosstales::RTVoice::Provider::VoiceProviderIOS, 158
- SetString
 - Crosstales::Common::Util::CTPlayerPrefs, 61
- SetVoices
 - Crosstales::RTVoice::LiveSpeaker, 85

- Crosstales::RTVoice::Provider::VoiceProviderIOS, 158
- setVoices
 - RTVoiceIOSBridge, 98
- Silence
 - Crosstales::RTVoice::LiveSpeaker, 85
 - Crosstales::RTVoice::Provider::BaseVoice↔ Provider, 42
 - Crosstales::RTVoice::Provider::VoiceProvider↔ Android, 156
 - Crosstales::RTVoice::Provider::VoiceProviderIOS, 158
 - Crosstales::RTVoice::Provider::VoiceProviderMary, 162
 - Crosstales::RTVoice::Provider::VoiceProviderW↔ SA, 166
 - Crosstales::RTVoice::Speaker, 122
 - Crosstales::RTVoice::Tool::SpeechText, 135
 - Crosstales::RTVoice::Tool::TextFileSpeaker, 141
- SilenceOnDisable
 - Crosstales::RTVoice::Speaker, 126
- SilenceOnFocustLost
 - Crosstales::RTVoice::Speaker, 126
- SilenceSource
 - Crosstales::RTVoice::Tool::Loudspeaker, 88
- Source
 - Crosstales::RTVoice::Model::Sequence, 102
 - Crosstales::RTVoice::Model::Wrapper, 169
 - Crosstales::RTVoice::Tool::Loudspeaker, 88
 - Crosstales::RTVoice::Tool::SpeechText, 137
 - Crosstales::RTVoice::Tool::TextFileSpeaker, 143
 - Crosstales::RTVoice::UDEA2::UDEAVoice↔ Wrapper, 148
- Speak
 - Crosstales::RTVoice::LiveSpeaker, 86
 - Crosstales::RTVoice::Provider::BaseVoice↔ Provider, 42
 - Crosstales::RTVoice::Provider::VoiceProvider↔ Android, 156
 - Crosstales::RTVoice::Provider::VoiceProviderIOS, 158
 - Crosstales::RTVoice::Provider::VoiceProvider↔ MacOS, 160
 - Crosstales::RTVoice::Provider::VoiceProviderMary, 162
 - Crosstales::RTVoice::Provider::VoiceProviderW↔ SA, 166
 - Crosstales::RTVoice::Provider::VoiceProvider↔ Windows, 164
 - Crosstales::RTVoice::Speaker, 122
 - Crosstales::RTVoice::Tool::SpeechText, 135
 - Crosstales::RTVoice::Tool::TextFileSpeaker, 141
- speak:text:rate:pitch:volume:
 - RTVoiceIOSBridge, 98
- SpeakImmediately
 - Crosstales::RTVoice::Model::Wrapper, 169
- SpeakMarkedWordsWithUID
 - Crosstales::RTVoice::Speaker, 123
- SpeakMode
 - Crosstales::RTVoice::Model::Enum, 16
- SpeakNative
 - Crosstales::RTVoice::LiveSpeaker, 86, 87
 - Crosstales::RTVoice::Provider::BaseVoice↔ Provider, 42
 - Crosstales::RTVoice::Provider::VoiceProvider↔ Android, 156
 - Crosstales::RTVoice::Provider::VoiceProviderIOS, 158
 - Crosstales::RTVoice::Provider::VoiceProvider↔ MacOS, 160
 - Crosstales::RTVoice::Provider::VoiceProviderMary, 162
 - Crosstales::RTVoice::Provider::VoiceProviderW↔ SA, 166
 - Crosstales::RTVoice::Provider::VoiceProvider↔ Windows, 164
 - Crosstales::RTVoice::Speaker, 123, 124
- SpeakNativeWithUID
 - Crosstales::RTVoice::Speaker, 124
- SpeakText
 - Crosstales::RTVoice::Tool::TextFileSpeaker, 141
- SpeakWithUID
 - Crosstales::RTVoice::Speaker, 124
- Speed
 - Crosstales::UI::WindowManager, 167
- SplitStringToLines
 - Crosstales::Common::Util::BaseHelper, 35
- StereoPan
 - Crosstales::UI::Util::AudioSourceController, 26
- stop
 - RTVoiceIOSBridge, 98
- StopAllSequences
 - Crosstales::RTVoice::Tool::Sequencer, 105
- Synchronized
 - Crosstales::RTVoice::Tool::Loudspeaker, 88
- TELEMETRY
 - Crosstales::RTVoice::EditorUtil::EditorConfig, 65
- TTS_MACOS
 - Crosstales::RTVoice::Util::Config, 48
- TTS_WINDOWS_BUILD
 - Crosstales::RTVoice::Util::Config, 48
- TTS_WINDOWS_EDITOR_x86
 - Crosstales::RTVoice::Util::Config, 48
- TTS_WINDOWS_EDITOR
 - Crosstales::RTVoice::Util::Config, 48
- TTS_WINDOWS_SUBPATH
 - Crosstales::RTVoice::Util::Constants, 56
- TTS_WINDOWS_x86_SUBPATH
 - Crosstales::RTVoice::Util::Constants, 56
- Text
 - Crosstales::RTVoice::Model::Sequence, 102
 - Crosstales::RTVoice::Model::Wrapper, 170
 - Crosstales::RTVoice::Tool::SpeechText, 137
 - HutongGames::PlayMaker::Actions::Speak, 113
 - HutongGames::PlayMaker::Actions::SpeakUI, 131
- TextFiles

- Crosstales::RTVoice::Tool::AudioFileGenerator, [22](#)
- Crosstales::RTVoice::Tool::TextFileSpeaker, [143](#)
- Timeout
 - Crosstales::Common::Util::CTWebClient, [62](#)
- UDEAVoiceName
 - Crosstales::RTVoice::UDEA2::UDEAVoice↔
Wrapper, [148](#)
- UPDATE_CHECK
 - Crosstales::RTVoice::EditorUtil::EditorConfig, [65](#)
- Uid
 - Crosstales::RTVoice::Model::Wrapper, [169](#)
- UpdateStatus
 - Crosstales::RTVoice::EditorTask, [15](#)
- ValidURLFromFilePath
 - Crosstales::Common::Util::BaseHelper, [36](#)
- ValidateFile
 - Crosstales::Common::Util::BaseHelper, [35](#)
- ValidatePath
 - Crosstales::Common::Util::BaseHelper, [36](#)
- Voice
 - Crosstales::RTVoice::Model::Voice, [151](#), [152](#)
 - Crosstales::RTVoice::Model::Wrapper, [170](#)
- VoiceForCulture
 - Crosstales::RTVoice::Speaker, [124](#)
- VoiceForName
 - Crosstales::RTVoice::Speaker, [125](#)
- VoiceNames
 - Crosstales::RTVoice::Tool::VoiceInitalizer, [153](#)
- VoiceProviderAndroid
 - Crosstales::RTVoice::Provider::VoiceProvider↔
Android, [155](#)
- VoiceProviderIOS
 - Crosstales::RTVoice::Provider::VoiceProviderIOS, [157](#)
- VoiceProviderMacOS
 - Crosstales::RTVoice::Provider::VoiceProvider↔
MacOS, [160](#)
- VoiceProviderMary
 - Crosstales::RTVoice::Provider::VoiceProviderMary, [161](#)
- VoiceProviderWSA
 - Crosstales::RTVoice::Provider::VoiceProviderW↔
SA, [165](#)
- VoiceProviderWindows
 - Crosstales::RTVoice::Provider::VoiceProvider↔
Windows, [163](#)
- Voices
 - Crosstales::RTVoice::Provider::BaseVoice↔
Provider, [44](#)
 - Crosstales::RTVoice::Speaker, [129](#)
 - Crosstales::RTVoice::UDEA2::UDEAConnector, [145](#)
- VoicesForCulture
 - Crosstales::RTVoice::Speaker, [125](#)
- Volume
 - Crosstales::RTVoice::Model::Sequence, [103](#)
 - Crosstales::RTVoice::Model::Wrapper, [170](#)
- Crosstales::RTVoice::Tool::SpeechText, [137](#)
- Crosstales::RTVoice::Tool::TextFileSpeaker, [143](#)
- Crosstales::RTVoice::UDEA2::UDEAVoice↔
Wrapper, [148](#)
- Crosstales::UI::Util::AudioSourceController, [26](#)
- HutongGames::PlayMaker::Actions::SpeakBase, [116](#)
- Windows
 - Crosstales::UI::UIWindowManager, [150](#)
- WordSpoken
 - Crosstales::RTVoice::LiveSpeaker, [87](#)
 - Crosstales::RTVoice::Provider::VoiceProviderIOS, [159](#)
- Wrapper
 - Crosstales::RTVoice::Model::Wrapper, [168](#), [169](#)