

Initial Setup

Open the challenge GUI. Open the correct database file if not already selected. Select the appropriate event from the pull down list of events. Initially, there will not be any challenges to select.

From the **Challenge** Menu, select **New Challenge**. You will be asked to select a name and the size of the bracket. This will always be a power of 2 (4, 8, 16, 32). If the number of drivers is not a power of 2, you can select the next largest size for the bracket.

Once the new challenge has been created, go to the challenge menu again and select **Auto Load Current**. This will bring up a dialog letting you select the drivers to add.




Set the number of drivers for the challenge in the top number selection. For most instances, this will be the size of the bracket but it could be a few drivers less in other situations. This setting will verify that you select the correct number of drivers.


Underneath that, select which sets of drivers you are interested in loading, Ladies classes and Open classes (non-ladies classes). You can also select whether to use bonus dialins (everyone users their own dialin) or not (everyone uses their classes leaders dialin * index ratio).

Selecting drivers is done by holding the Ctl key and clicking or dragging across drivers. If you wish to order the list by name or class, click on the column header to do so. Once you have selected enough drivers, click OK. The bracket will be filled with the drivers selected and bracketed based on their net times. You may also drag and drop drivers from the tree on the left of the main window to enter them into a challenge but this is much more cumbersome.

Once, the challenge is ready, it may look something like so:



You will notice that there is a large red label in the top right indicating that the Challenge GUI is not connected to the Timer. When this occurs, the GUI can't set dial in times and the results won't make it back to the GUI. To remedy this, select **Connect** from the **Timer** menu.



The connect dialog will pop up with all of the ProTimer services it can find on the network. There should be only 1. If nothing appears, you must verify that the firewall on either computer isn't interfering. Once selected, click **OK** and a connection will be made and the red label will disappear.

Running a Challenge

To run a challenge, you open up each round as the entrants pull up to the line by clicking the **Open** button for the corresponding round in the challenge tree.


The screenshot shows the ProTimer software window titled "Kit Gauthier VS Karl Coleman". At the top, there are buttons for "Stage" and "Reset Round", and a checkbox for "Swapped Start". Below this, the names and current times of the competitors are displayed: "Kit Gauthier 30.504" and "Karl Coleman 31.445". Each name has "AutoWin" and "Dial" buttons next to it. The main area is divided into four sections for individual runs:

- Left Run:** Indicated by a green box with a green arrow and "Left 1". It contains a table with columns: start, time, cones, gates, status, and diff. The values are: start (00.000), time (0), cones (0), gates (OK), status (), and diff ().
- Right Run:** Indicated by a green box with a green arrow and "Right 1". It contains a table with columns: start, time, cones, gates, status, and diff. The values are: start (00.000), time (0), cones (0), gates (OK), status (), and diff ().
- Right Run:** Indicated by a purple box with a purple arrow and "Right 2". It contains a table with columns: start, time, cones, gates, status, and diff. The values are: start (00.000), time (0), cones (0), gates (OK), status (), and diff ().
- Left Run:** Indicated by a purple box with a purple arrow and "Left 2". It contains a table with columns: start, time, cones, gates, status, and diff. The values are: start (00.000), time (0), cones (0), gates (OK), status (), and diff ().

In this case, it expects Kit to be starting on the left side and Karl to be starting on the right side. If they come up in different lanes, click the **Swap** checkbox and they will be swapped in the window. Before the starter can start the round, you must click **Stage**. This will send the dial in commands to the ProTimer laptop. If the hardware approves, the dialins will appear at the top of the ProTimer window. If not, you can try clicking stage again to resend them.


Once staged, the runs will have colored, labeled and numbers indicators. Green/1 indicates where the next set of run data to be received will be put. Purple/2 indicates the next location after that. Once a run is entered, you will see the green box return to white and the purple box turn to green. If there were cones or a DNF called, the operators must manually enter those by selecting the appropriate value. Not Staged and Red Light errors will automatically be entered once the driver passes through the finish lights. Once a round is over, the winner is automatically moved to the next round along with their dialin. If the driver broke out, their new dialin is calculated and used in the next round.

You can also stage the next set of competitors while the current set is finishing their second runs. There colors will start out as Purple/2 and Red/3 as the next set of runs still belong to the running round.



In special cases, there are some other options you can use:

- The **Dial** button under each driver can be used to override the dialin for the driver in that round. This must be done before clicking stage.
- The **Reset Round** button can be used to remove all run data from the round if something went wrong and it has to be restarted.
- If a driver doesn't show up for the round, clicking **AutoWin** under the driver that did show up will move them to the next round.
- Entering a raw time into one of the run time boxes lets you overwrite the time that came from the hardware or if no time arrived due to a network error.
- Clicking on of the run indicator buttons will bring up a dialog to let you change where the next runs will be placed. Deactivate is the same as assigning the run nothing and progressing as normal. Activate as next target will override current settings and make the selected run the next target.



Understanding the Display

Challenge Tree (Left):

- 31.444 Annie Gill (Open 15)
- 31.151 Kevin Dietz (Open 7)
- 31.445 Karl Coleman (Open 14)
- 31.732 Shane Jensen (Open 6)
- 32.663 Chris Miller (Open 13)
- 31.437 Adam Ruff (Open 6)
- 31.106 Dan Podhola (Open 12)
- 33.694 James Rollo (Open 11)
- 33.339 Michelle Miller (Open 11)
- 33.682 David Cross (Open 11)

Shane Jensen VS Dan Podhola Round Window:

Shane Jensen 31.732 (AutoWin, Dial) | Dan Podhola 31.106 (AutoWin, Dial)

Left Run: start 0.911, time 35.229, cones 0, gates 0, status OK, diff 3.497

Right Run: start 0.750, time 32.324, cones 0, gates 0, status OK, diff 1.218

Annotations: Dan Podhola returns faster by 2.279 (Blue box), Dan Podhola wins by 2.120 (Green box)

Josh McCall VS Brandon Young Round Window:

Josh McCall 33.779 (AutoWin, Dial) | Brandon Young 33.779 (AutoWin, Dial)

Left Run: start 0.877, time 34.456, cones 0, gates 0, status OK, diff 0.677

Right Run: start 0.788, time 36.902, cones 0, gates 0, status OK, diff -0.355

Annotations: Brandon Young returns faster by 1.032 (Blue box), Josh McCall returns faster by 1.975 (Blue box), Josh McCall wins by 0.943 (Green box)

For the announcer, they are most concerned with the active round window. The main window will contain the entire challenge tree but the results appear in each round window. Initially, the only useful data will be the orange box. As the first half of the round ends, the top half of the results become available. After the second round ends, all the results will be available.

- Orange box is the drivers name and dialin
- Red box is the difference from their dialin for the individual run, includes cone penalty
- Blue boxes are the results of one half of a round, value in parenthesis is without cones
- Green box is the final result of the entire round, this field will also indicate a breakout and new dialin