

## MS51 16K Series BSP Guide

Directory Introduction for NuMicro™ 8051 Family

### Directory Information

Please extract the “MS51\_16K\_BSP\_Keil\_C51\_V1.00.zip” file firstly, and confirm the following folder all contain.

This BSP folder contents:

Document\	Driver reference manual and reversion history.
Library\	Device driver header and source files
SampleCode\	Device driver sample code.

*The information described in this document is the exclusive intellectual property of Nuvoton Technology Corporation and shall not be reproduced without permission from Nuvoton.*

*Nuvoton is providing this document only for reference purposes of NuMicro microcontroller based system design.  
Nuvoton assumes no responsibility for errors or omissions.*

*All data and specifications are subject to change without notice.*

For additional information or questions, please contact: Nuvoton Technology Corporation.

[www.nuvoton.com](http://www.nuvoton.com)

## 1 .\Document\

Nuvoton\_MS51\_16K\_BS  
P\_Revision\_History.pdf

This document shows the revision history of MS51 BSP.

## 2 .\Library\

Device\	Compliant device header file
Startup\	A51 startup file and executable file
StdDriver\	All peripheral driver header and source files.

### 3 .\ Device \

<b>Function_Define.h</b>	Special define file include the function peripheral initial setting define.
<b>MS51.h</b>	MS51 header file with keil C51format.
<b>SFR_Macro.h</b>	SFR bit register define with set/clr to make sure can bit to define SFR.

## 4 .\ Startup \

EXE\	hex2bin.exe file included for project call hex to create bin file execute tool.
Keil\	The Keil startup.A51file special for MS51 16K body

## 5 .\SampleCode\

RegBased\	Register base the usage of MS51 series MCU peripheral code.
Template\	A project template for MS51 series MCU

## 6 .\SampleCode\RegBased

<b>ACMP_Bandgap</b>	ADC input pin is bandgap demo.
<b>ACMP_Bandgap_VDD</b>	ADC converts demo code with band-gap value to calculate the VDD value.
<b>ADC_GPIO _Trig</b>	ADC trig start by GPIO demo. External GPIO level change will trig ADC convert start.
<b>ADC_multi_channel</b>	ADC input from ADC_CH4 pin and Bandgap input routine to convert demo.
<b>ADC_PWM_Trig</b>	ADC convert start trig by PWM period demo. Each PWM period over will trig ADC by hardware.
<b>ADC_Simple</b>	ADC convert start by trig SFR bit and convert finish by check flag.
<b>Fsys_ModifyHIRC</b>	Modify internal HIRC value to 16MHz or 24MHz demo. This modify value is from internal defined, after loading, HIRC deviation not over 1%.
<b>Fsys_Select_ECLK</b>	MS51 system clock select from HIRC to External clock demo.
<b>GPIO_ClockOut</b>	MS51 system clock output from GPIO demo. System clock output 100KHz after divider. Since HIRC maybe define to 16MHz or 24MHz, based on HIRC real status to define divider value.
<b>GPIO_InputOutput</b>	MS51 gpio simple toggle out demo. This demo is easy to confirm MS51 normal run status.
<b>GPIO_PowerDown_BODdisable</b>	MS51 power down mode demo. For confirm power down current of each MCU. Call BOD disable function first to confirm down to lowest power consumption.
<b>I2C0_EEPROM</b>	I <sup>2</sup> C setting as master mode to connect W24LC64 EEPROM to write in and read out data demo.
<b>IAP_APROM_program_DataFlash</b>	MS51 Data flash demo code. all APROM memory can be used as Dataflash.
<b>IAP_APROM_program_LD</b>	IAP run in APROM to program LDROM. First need confirm

<b>ROM</b>	the LDROM is enabled.
<b>IAP_Dataflash_EEPROM</b>	Customer use this macro, each time call this subroutine, can use Data flash as EEPROM mode, the process include read old data / erase / modify new code/ write in.
<b>IAP_LD-Program-AP</b>	IAP run in LDROM to program APROM. This function is use in ISP function.
<b>IAP_program_Config</b>	Use code IAP function to modify CONFIG area.
<b>IAP_Read_UCID</b>	Use IAP command to read the UCID of each MS51. Only for customer special order MS51 MCU. One UCID is only for one customer.
<b>IAP_Read_UID</b>	Use IAP command to read the UID of each MS51. Each pieces of MS51 UID is different.
<b>INT0_Ext_Interrupt</b>	External INT0 function demo. The basic 8501 EXT0 function.
<b>INT1_Ext_Interrupt</b>	External INT1 function demo. The basic 8051 EXT1 function.
<b>Pin_Interrupt</b>	One group each GPIO of MS51 use as external interrupt pin. Trig IC wakeup from idle / power down mode.
<b>PWM_DeadTime</b>	PWM output insert with dead time setting demo, include picture to show after insert dead time waveform.
<b>PWM_Interrupt</b>	PWM with interrupt subroutine, after period PWM into interrupt process.
<b>PWM_Simple</b>	PWM simple define output from individual PWM channel.
<b>ROM_Const_One</b>	Combine data table into ROM define special address, picture show the defined item in options. After compiler the output hex or bin file with this table.
<b>ROM_Const_One</b>	Two table file combine special define item in options demo.
<b>Timer0_mode_0_Interrupt</b>	Timer0 mode 0 13-bit timer counter define with interrupt demo. One shot no auto reload function.
<b>Timer0_mode_1_Interrupt</b>	Timer0 mode 1 16-bit timer counter define with interrupt demo. One shot no auto reload function.



<b>Timer0_mode_2_Interrupt</b>	Timer0 mode 2 8-bit auto reload timer counter define with interrupt demo.
<b>Timer01_mode_3_Interrupt</b>	Mode 3 is two separate 8 bit, TR0 and TR1 to control begin the Timer counter.
<b>Timer1_mode_0_Interrupt</b>	Timer1 mode 0 13-bit timer counter define with interrupt demo. One shot no auto reload function.
<b>Timer1_mode_1_Interrupt</b>	Timer1 mode 1 16-bit timer counter define with interrupt demo. One shot no auto reload function.
<b>Timer1_mode_2_Interrupt</b>	Timer1 mode 2 8-bit auto reload timer counter define with interrupt demo.
<b>Timer2_AutoReload_Capture</b>	Timer 2 use as capture initial setting. With 7 channel 3 input capture module setting.
<b>Timer2_AutoReload_Delay</b>	Timer 2 delay counter define with auto reload function.
<b>Timer3</b>	Timer 3 delay counter define with auto reload function. When use timer 3 need confirm this time not used as UART baud rate generator.
<b>UART0</b>	UART0 demo code. Include transmit and receive demo, since default HIRC16MHz not fit for baud rate over 38400, modify HIRC to 24MHz to confirm the baud rate deviation not over 1%.
<b>UART0_Interrupt_RW</b>	UART0 with interrupt, received data from UART0_RXD transmit to UART0_TXD loop.
<b>UART0_printf</b>	Code use “printf” instruction from UART0 setting. Special with “putchar.c” define.
<b>UART1</b>	UART1 demo code Include transmit and receive demo and enable interrupt subroutine. To use UART1 function must remove ICE connect since ICE function will disturb UART1 transmit.
<b>UART0_Interrupt_RW</b>	UART1 with interrupt, received data from UART1_RXD transmit to UART1_TXD loop. To use UART1 function must remove ICE connect since ICE function will disturb UART1 transmit.
<b>UART1_printf</b>	Code use “printf” instruction transmit from UART1 setting. Special with “putchar.c” define. To use UART1 function must

	remove ICE connect since ICE function will disturb UART1 transmit.
<b>WakeupTimer_Interrupt</b>	Wakeup timer over into interrupt to toggle GPIO P1.2 to show result. Based on LIRC clock as source.
<b>Watchdog_Interrupt</b>	Watchdog timer over only jump into interrupt. This auto reload timer counter not with reset and not need special define in CONFIG.
<b>Watchdog_Reset_Disable</b>	After watchdog reset function is enabled, only modify CONFIG to disable it can disable WDT reset function. This demo is use IAP to disable CONFIG WDT function.
<b>Watchdog_Reset_Enable</b>	Watchdog timer over cause reset initial. Include "CONFIG" enable use IAP command and check with POF flag if reset is enabled before, not do IAP again.

## 7 REVISION HISTORY

Date	Revision	Description
2019.1.29	1.00	Initially issued.

### **Important Notice**

**Nuvoton Products are neither intended nor warranted for usage in systems or equipment, any malfunction or failure of which may cause loss of human life, bodily injury or severe property damage. Such applications are deemed, "Insecure Usage".**

**Insecure usage includes, but is not limited to: equipment for surgical implementation, atomic energy control instruments, airplane or spaceship instruments, the control or operation of dynamic, brake or safety systems designed for vehicular use, traffic signal instruments, all types of safety devices, and other applications intended to support or sustain life.**

**All Insecure Usage shall be made at customer's risk, and in the event that third parties lay claims to Nuvoton as a result of customer's Insecure Usage, customer shall indemnify the damages and liabilities thus incurred by Nuvoton.**

---

*Please note that all data and specifications are subject to change without notice.  
All the trademarks of products and companies mentioned in this datasheet belong to their respective owners.*