

LOLLIPOPZ WEBSITE						
VERSION NO:				TESTED BY:ANITA JACOB		
VERIFIED BY:				DATE:30/01/2025		
ENVIRONMENTAL DETAILS: GOOGLE CHROME				MODULE NAME:HOME PAGE		
TEST ID	TEST DESCRIPTION	TEST PROCEDURE	TEST DATA	EXPECTED RESULT	ACTUAL RESULT	STATUS
LW_HP_001	Verify that the home page loads successfully without any errors.	1.Open the website URL in a browser. 2.Check if the home page loads completely.	Lollipopz Boutique	The home page should load successfully, and all elements like header, footer, images, etc. should be displayed correctly.	The home page load successfully, and all elements like header, footer, images, etc. should be displayed correctly.	Pass
LW_HP_002	Verify that all navigation links on the home page are working correctly.	1.Open the home page. 2.Click on each navigation link.		Each navigation link should redirect the user to the correct page.	Each navigation link redirect the user to the correct page.	Pass
LW_HP_003	Verify that the carousel is visible on the homepage.	1.Open the homepage. 2.Scroll to the carousel section. 3.Check if the carousel is displayed.		The carousel should be visible on the homepage.	The carousel is visible on the homepage.	Pass
LW_HP_004	Verify that the carousel automatically slides to the next image after a set interval.	1.Open the homepage. 2.Observe the carousel for a few seconds.		The carousel should automatically slide to the next image after the set interval	The carousel is not automatically slide to the next image after the set interval	Fail
LW_HP_005	Verify that the user can manually navigate through the carousel using the next and previous buttons.	1.Open the homepage. 2.Click on the "Next" button to move to the next slide. 3.Click on the "Previous" button to move to the previous slide.		The carousel should move to the next and previous slides as per the user's clicks.	The carousel move to the next and previous slides as per the user's clicks.	Pass
LW_HP_006	Verify that the carousel is responsive on different devices.	1.Open the homepage on different devices or use browser developer tools to simulate different screen sizes. 2.Scroll to the carousel section. 3.Check if the carousel adjusts correctly for each device.	Mobile Laptop	The carousel should display correctly on all devices without any layout issues.	The carousel display correctly on all devices without any layout issues.	Pass
LW_HP_007	Verify that the carousel loops back to the first image after the last image.	1.Open the homepage. 2.Navigate to the last image in the carousel. 3.Click on the "Next" button.		The carousel should loop back to the first image after the last image.	The carousel shouldn't loop back to the first image after the last image.	Fail
LW_HP_008	Verify that the names of the product categories are displayed correctly.	1.Open the homepage. 2.Scroll to the product categories section. 3.Check the names of each category.	Accessories Kids	The names of the product categories should match the expected names.	The names of the product categories match the expected names.	Pass
LW_HP_009	Verify that each product category has an associated image.	1.Open the homepage. 2.Scroll to the product categories section. 3.Check if each category has an image.		Each product category should have an associated image	Each product category have an associated image	Pass
LW_HP_010	Verify that clicking on a product category redirects to the correct page.	1.Open the homepage. 2.Scroll to the product categories section. 3.Click on each category.	Accessories Kids	Clicking on a category should redirect the user to the correct product listing page for that category.	Clicking on a category redirect the user to the correct product listing page for that category.	Pass

LW_HP_011	Verify that all footer links are working correctly.	1.Open the shop image and click the products. 2.Navigate to the product display page. 3.Click on each link in the footer.		All links should redirect to the correct pages without errors.	All links redirect to the correct pages.	Pass
LW_HP_012	Verify that social media links in the footer are working correctly.	1.Open the shop image and click the products. 2.Navigate to the product display page. 3.Click on each social media icon.		Each social media link should redirect to the correct page without errors.	Each social media link redirects to the correct page.	Pass
LW_HP_013	Verify that the add to cart button is visible and functional.	1.Open the shop image and click the products. 2.Navigate to the product display page. 3.Click the add to cart button.		The product should be added to the cart.	The product is added to the cart successfully.	Pass
LW_HP_014	Verify that the back to top button in the footer works correctly.	1.Open the shop image and click the products. 2.Navigate to the product display page. 3.Click the back to top button in the footer.		The page should scroll back to the top when the button is clicked.	The page scrolls back to the top.	Pass
LW_HP_015	Verify that the "End of the Sale" section is visible on the homepage	1.Open the homepage. 2.Scroll to the "End of the Sale" section. 3.Check if the section is displayed.		The "End of the Sale" section should be visible on the page.	The "End of the Sale" section is visible on the page.	Pass
LW_HP_016	Verify that the countdown timer in the "End of the Sale" section works correctly.	1.Open the homepage or sale page. 2.Scroll to the "End of the Sale" section. 3.Observe the countdown timer for a few minutes.		The countdown timer should decrease by one second every second and display the correct time remaining.	No counter timer is observed	Fail
LW_HP_017	Verify that the sale end date and time displayed in the "End of the Sale" section are correct.	1.Open the homepage or sale page. 2.Scroll to the "End of the Sale" section. 3.Check the displayed sale end date and time	Sale ends on 31-12-2025 at 23: 59	There is not displayed sale end date and time.	No sale end date and time is mentioned in the sale section.	Fail
LW_HP_018	Verify that sold-out items are visible on the homepage.	1.Open the homepage. 2.Scroll to the product sections 3.Check if sold-out items are displayed.		Sold-out items should be visible on the homepage with a "Sold Out" label or indicator.	Sold-out items visible on the homepage with a "Sold Out" label or indicator.	Pass
LW_HP_019	Verify that the "View More" button is visible when there are more items to load.	1.Open the homepage or product listing page. 2.Scroll to the bottom of the product section. 3.Check if the "View More" button is displayed		The "View More" button should be visible when there are more items to load.	The "View More" button is visible when there are more items to load.	Pass

	LW_HP_020	Verify that the "View More" button disappears after all items are loaded.	1.Open the homepage or product listing page. 2.Click on the "View More" button until all items are loaded. 3.Check if the "View More" button is still visible.		The "View More" button should disappear after all items are loaded.	The "View More" button disappear after all items are loaded.	Pass
	LW_HP_021	Verify that the "Load More" button is visible when there are more items to load.	1.Open the homepage or product listing page. 2.Scroll to the bottom of the product section. 3.Check if the "Load More" button is displayed		The "Load More" button should be visible when there are more items to load.	The "Load More" button is visible when there are more items to load.	Pass