

NAME

torsocks — Shell wrapper to simplify the use of the **torsocks(8)** library to transparently torify an application.

SYNOPSIS

torsocks [OPTIONS] [COMMAND [ARG ...]]

DESCRIPTION

torsocks is a wrapper between the **torsocks** library and the application in order to make every Internet communication go through the Tor network.

By default, **torsocks** will assume that it should connect to the Tor SOCKS proxy running at 127.0.0.1 on port 9050 being the defaults of the Tor daemon.

In order to use a configuration file, **torsocks** tries to read the **/etc/tor/torsocks.conf** file or look for the environment variable **TORSOCKS_CONF_FILE** with the location of the file. If that file cannot be read, **torsocks** will use sensible defaults for most Tor installations.

For further information on configuration, see **torsocks.conf(5)**.

OPTIONS

-h, --help

Show summary of possible options and commands.

--shell Create a new shell with LD_PRELOAD including **torsocks(8)**.

--version

Show version.

-u, --user

Set username for the SOCKS5 authentication. Use for circuit isolation in Tor. Note that you MUST have a password set either by the command line, environment variable or configuration file (**torsocks.conf(5)**).

-p, --pass

Set password for the SOCKS5 authentication. Use for circuit isolation in Tor. Note that you MUST have a username set either by the command line, environment variable or configuration file (**torsocks.conf(5)**).

-a, --address

Set Tor address.

-P, --port

Set Tor port.

-i, --isolate

Automatic tor isolation. Set the username and password for the SOCKS5 authentication method to a PID/current time based value automatically. Username and Password MUST NOT be set.

-d, --debug

Activate the debug mode. Output will be written on stderr.

-q, --quiet

Suppress every log messages (even errors).

on | off This option adds or removes **torsocks(8)** from the LD_PRELOAD environment variable for the current shell. If you want to use this option, you HAVE to source **torsocks** from your shell.

Add the **torsocks** library to LD_PRELOAD

```
$ . torsocks on
Remove the torsocks library from LD_PRELOAD
$ . torsocks off
```

show | sh

Show the current value of the LD_PRELOAD environment variable.

ENVIRONMENT VARIABLES

Please see **torsocks(8)** for more detail on possible environment variables.

SEE ALSO

torsocks(8), **torsocks.conf(5)**

CREDITS

torsocks is distributed under the GNU General Public License version 2.

A Web site is available at <https://www.torproject.org> for more information.

You can also find the source code at <https://git.torproject.org>.

Mailing list for help is <tor-talk@lists.torproject.org> and for development use <tor-dev@lists.torproject.org>. You can find the project also on IRC server [irc.oftc.net](https://www.oftc.net) (OFTC) in #tor and #tor-dev.

AUTHOR

torsocks was originally written by Robert Hogan and has been rewritten by David Goulet <dgoulet@torproject.org> in 2013.