





Select: servers-new

License Administration Tool

Servers License View Help

3DEXPERIENCE | License Administration Tool

Server Definitions Administration Usage Per Feature Usage Per User Authorizations Statistics Server Logs Monitoring Geolocation

Status	Computer Name	Computer ID	Version	Build Date	Operating System	Comment
	172.28.36.252	SCG-435C1CF9DD7614EB	not connected			
	172.27.40.254	LKK-41DE1C4A9249A800	not connected			
	M062	ZFG-42001C41389FA730	not connected			
	172.23.38.131	KZB-41E710481CA04F8F	not connected			

License Server Connection Parameters

License Server name: 172.20.33.143

Administration port: 4084

☐ Use a proxy server



Proxy name:

Proxy port:





OK Cancel Connect

Define server you want to see.
Don't change the port.

Servers License View Help

  **3DEXPERIENCE | License Administration Tool**


Server Definitions Administration Usage Per Feature Usage Per User Authorizations Statistics Server Logs Monitoring Geolocation

Status	Computer Name	Computer ID	Version	Build Date	Operating System
	172.28.36.252	SCG-435C1CF9DD7614EB	not connected		
	172.27.40.254	LKK-41DE1C4A9249A800	not connected		
	M062	ZFG-42001C41389FA730	6.418.3	25.2.2016 15:15:11	Windows 7
	172.23.38.131	KZB-41E710481CA04F8F	not connected		

Right click the server on the list and choose "connect restricted"

Go to "usage per feature sheet and select active server

Servers License View Help

 3DEXPERIENCE | License Administration Tool

Server Definitions Administration **Usage Per Feature** Usage Per User Authorizations Statistics Server Logs Monitoring Geolocation

☐ 172.28.36.252 ☐ 172.27.40.254 ☒ **M062** ☐ 172.23.38.131

Editor	Feature	Commercial Type	In Use	Count
Dassault Systemes V5	CAC	STD	3	7
Dassault Systemes V5	CAI	STD	1	7
Dassault Systemes V5	CBD	STD	1	2
Dassault Systemes V5	EDR	STD	0	15
Dassault Systemes V5	ELB	STD	1	1
Dassault Systemes V5	FDN	STD	0	15
Dassault Systemes V5	MD1	STD	1	4
Dassault Systemes V5	MD2-EHIEWR	STD	0	1
Dassault Systemes V5	MD2-EHIEWRST1	STD	1	1
Dassault Systemes V5	XM1	STD	1	1

In the list you can see:

- license name
- Number of licenses in use
- How many licenses are available on server

Detailed License Usage												
License Usage for Feature CAC from Editor Dassault Systemes V5												
Server	License Type	User	Host	Granted Since	Last Used At	Active Process	Granted At	Max Release Date	Expiration Date	Max Release Number	Internal ID	
M062	ConcurrentUser	EDVBU	LT138 (41E710481CA04F8F-ac172683.4)/172.23.38.131	7.1.2019 7:5...	7.1.2019 13...	C:\Program Fil...	7.1.2019 7:51:00	31.1.2019 1:59:00	31.1.2019 1:5...	0	EDVBU@PANEVEZYS.S	
M062	ConcurrentUser	AIVMY	LT229 (42AF1CCC6A1161F6-ac172424.1)/172.23.36.36	7.1.2019 12:...	7.1.2019 13...	C:\Program Fil...	7.1.2019 12:18:30	31.1.2019 1:59:00	31.1.2019 1:5...	0	AIVMY@PANEVEZYS.S	
M062	ConcurrentUser	Adham.Kira	A750 (424C185B768BC320-ac1e242e.1)/172.30.36.46	7.1.2019 12:...	7.1.2019 13...	C:\Program Fil...	7.1.2019 12:23:36	31.1.2019 1:59:00	31.1.2019 1:5...	0	ADHAM.KIRA@AJ_TEH	

Double click license on the list and you can see who are using them currently.