

LAB ASSIGNMENT-6

Lab 6: NAT Configuration

Experiment Overview:

In this experiment, you will configure Network Address Translation (NAT) on a router using Cisco Packet Tracer. NAT is used to translate private IP addresses within a local network to a public IP address for accessing the internet. This experiment will demonstrate the setup and configuration of NAT to allow internal network devices to communicate with external networks.

Procedure:

Network Design:

- Router1 connected to the ISP Router.
- PC0 connected to Router1.
- PC1 connected to Router1.

Step 1: Configure Network Addresses

1. Determine IP address scheme:

- Inside network (LAN): 192.168.10.0/24
- Outside network (ISP): 200.0.0.0/30

Step 2: Configuring Router1

1. Select Router1 and open CLI.

2. Press ENTER to start configuring Router1.

3. Activate privileged mode:

- Type enable

4. Access the configuration menu:

- Type config t (configure terminal)

5. Configure interfaces of Router1:

- FastEthernet0/0 (connected to LAN):

- Type interface FastEthernet0/0
- Configure with the IP address 192.168.10.1 and Subnet mask 255.255.255.0

- Serial0/0/0 (connected to ISP Router):

- Type interface Serial0/0/0
- Configure with the IP address 200.0.0.1 and Subnet mask 255.255.255.252

6. Activate interfaces:

- Type no shutdown

Step 3: Configuring ISP Router

1. Select the ISP Router and open CLI.
2. Press ENTER to start configuring the ISP Router.

3. Activate privileged mode:

- Type enable

4. Access the configuration menu:

- Type config t (configure terminal)

5. Configure interfaces of the ISP Router:

- Serial0/0/0 (connected to Router1):

- Type interface Serial0/0/0
- Configure with the IP address 200.0.0.2 and Subnet mask 255.255.255.252

6. Activate interfaces:

- Type no shutdown

ISP Router Command Line Interface:

Step 4: Configuring PCs

1. Assign IP addresses to each PC:

○ PC0:

■ Go to the desktop, select IP Configuration, and assign the following:

■ IP address: 192.168.10.2

■ Subnet Mask: 255.255.255.0

■ Default Gateway: 192.168.10.1

○ PC1:

■ Go to the desktop, select IP Configuration, and assign the following:

■ IP address: 192.168.10.3

■ Subnet Mask: 255.255.255.0

■ Default Gateway: 192.168.10.1

Step 5: Configuring NAT on Router1

1. Define the inside and outside interfaces:

○ Access Router1 CLI and type the following commands:

■ interface FastEthernet0/0

■ ip nat inside

■ exit

■ interface Serial0/0/0

■ ip nat outside

■ exit

2. Configure a standard access list to permit the internal network:

○ access-list 1 permit 192.168.10.0 0.0.0.255

3. Configure NAT overload (PAT) for the internal network:

○ ip nat inside source list 1 interface Serial0/0/0 overload

Router1 NAT Configuration Commands:

Step 6: Verify NAT Configuration

1. Test the connectivity by pinging from PC0 to the ISP Router:

- Open the command prompt on PC0.
- Type ping 200.0.0.2 and observe the response.

2. Check NAT translation table on Router1:

- On Router1 CLI, type show ip nat translations to see the NAT entries.

Step 7: Verify External Connectivity

1. Test external connectivity by pinging a public IP (simulated):

- On PC0, type ping 8.8.8.8 (replace with an actual reachable IP in Packet Tracer).
- On PC1, type ping 8.8.8.8.

Configuration Tables

Simulation of Designed Network Topology

Sending a PDU from PC0 to an External Network

1. Open the simulation mode in Packet Tracer.

2. Send a PDU from PC0 to a simulated external IP (e.g., 8.8.8.8):

- Observe the packet traveling from PC0 to Router1, NAT translation occurring, then to the ISP Router and the external network.

Acknowledgment from External Network to PC0

1. Observe the acknowledgment packet:

- Ensure that the acknowledgment packet travels back from the external network to PC0, confirming successful NAT configuration and communication.

Cisco Packet Tracer

File Edit Options View Tools Extensions Window Help

Logical Physical x 677, y 224

STATIC NAT CONFIGURATION

NAT ROUTER

2911 Router0

2911 NAT Switch

192.168.20.0/24

PC-PT PC3

PC-PT PC1

200.100.50.0/30

Router0

IOS Command Line Interface

```
Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#ip nat inside source static 192.168.20.10 200.100.50.1
Router(config)#
Router(config)#
Router(config)#interface GigabitEthernet0/1
Router(config-if)#ip nat inside
Router(config-if)#
Router(config-if)#
Router(config-if)#exit
Router(config)#
Router(config)#interface GigabitEthernet0/0
Router(config-if)#ip nat outside
Router(config-if)#exit
Router(config)#do wr
Building configuration...
[OK]
Router(config)#end
Router#
$SYS-$-CONFIG_1: Configured from console by console

Router#sh ip nat translations
Pro Inside global Inside local Outside local Outside global
--- 200.100.50.1 192.168.20.10 --- ---

Router#
Router#sh ip nat translations
Pro Inside global Inside local Outside local Outside global
icmp 200.100.50.117 192.168.20.117 8.8.8.8:17 8.8.8.8:17
icmp 200.100.50.118 192.168.20.118 8.8.8.8:18 8.8.8.8:18
icmp 200.100.50.119 192.168.20.119 8.8.8.8:19 8.8.8.8:19
icmp 200.100.50.120 192.168.20.120 8.8.8.8:20 8.8.8.8:20
icmp 200.100.50.121 192.168.20.121 8.8.8.8:21 8.8.8.8:21
icmp 200.100.50.122 192.168.20.122 8.8.8.8:22 8.8.8.8:22
icmp 200.100.50.123 192.168.20.123 8.8.8.8:23 8.8.8.8:23
icmp 200.100.50.124 192.168.20.124 8.8.8.8:24 8.8.8.8:24
icmp 200.100.50.125 192.168.20.125 8.8.8.8:25 8.8.8.8:25
icmp 200.100.50.126 192.168.20.126 8.8.8.8:26 8.8.8.8:26
--- 200.100.50.1 192.168.20.10 --- ---

Router#
```

Copy Paste

Time: 00:46:19

Copper Cross-Over

Toggle PDU List Window

Realtime Simulation

Cisco Packet Tracer

File Edit Options View Tools Extensions Window Help

Logical Physical x 680, y 210

STATIC NAT CONFIGURATION

NAT ROUTER

2911 Router0

2911 NAT Switch

192.168.20.0/24

PC-PT PC3

PC-PT PC1

200.100.50.0/30

2911 ISP

8.8.8.0/24

Server-PT GOOGLE WEB SERVER

Time: 00:46:50

Copper Cross-Over

Scenario 0

Fire Last Status Source Destination Type Color Time(sec) Periodic Num Edit Delete

Realtime Simulation