

Ultimate Member: Registration Activation Email

<https://www.youtube.com/watch?v=AuAPvSmo3CQ>

<https://www.youtube.com/watch?v=so33OViB4R0>

1. Create new role

Ultimate Member > User Roles > New > Registration status : Require email activation

2. Set default role upon registering

Ultimate member > Settings > Appearance > Registration forms > Registration Default Role : above

3. Enable Registration Activation Email

Ultimate member > Settings > Email > Account Activation Email > Tick

4. If no mail server present, then use Google's mail server by using WP Mail SMTP plugin

The screenshot shows the WP Mail SMTP plugin settings page. The left sidebar contains the WordPress dashboard menu with 'Settings' highlighted. The main content area is divided into sections:

- Mailer:** Displays five mailer options: php, Google, Mailgun, SendGrid, and Other SMTP. 'Other SMTP' is selected and highlighted with an orange box.
- Return Path:** A checkbox labeled 'Set the return-path to match the From Email' is checked. Below it, a note states: 'Return Path indicates where non-delivery receipts - or bounce messages - are to be sent. If unchecked bounce messages may be lost.'
- Other SMTP:** A heading followed by the instruction: 'Use the SMTP details provided by your hosting provider or email service.' Below this is a link to 'SMTP documentation'.
- SMTP Host:** A text input field containing 'smtp.gmail.com'.
- Encryption:** Three radio buttons: 'None', 'SSL', and 'TLS'. 'TLS' is selected. A note below states: 'For most servers TLS is the recommended option. If your SMTP provider offers both SSL and TLS options, we recommend using TLS.'
- SMTP Port:** A text input field containing '587'.
- Authentication:** A toggle switch labeled 'ON'.
- SMTP Username:** A text input field containing 'steppe.ego@gmail.com'.
- SMTP Password:** A text input field with masked characters (dots).

<https://www.a2hosting.com/kb/installable-applications/optimization-and-configuration/wordpress2/sending-e-mail-in-wordpress#Installing-the-WP-Mail-SMTP-plugin>

<https://www.youtube.com/watch?v=bT6o5dKAQcE>

<https://wordpress.org/plugins/wp-mail-smtp/>

5. Ready your Gmail account:

1. Go to the "Settings", e.g. click on the "Gears" icon and select "Settings".
2. Click on "Forwarding and POP/IMAP".
3. Enable "IMAP Access" and/or "POP Download"
4. See: <https://support.google.com/accounts/answer/6010255?hl=en> for details. The page contains a link to enable "Less secure apps" in MyAccount.
5. You can also enable "Less secure apps" (third-party mail clients) from: "MyAccount" > "Sign-in & security" > "Connected apps & sites" > "Allow less secure apps"

<https://www.arclab.com/en/kb/email/how-to-enable-imap-pop3-smtp-gmail-account.html>