



# INFORMATION REQUIRED FOR THE **MT5** INSTALLATION

# Information required for the MT5 Installation

---

## Server Requirements

1. Access to the server where your data and Clients documents will be stored.

Server's minimal suggested parameters:

- OS: Windows server 2016
  - CPU: 2 cores
  - RAM: 4GB
  - DISK: 100GB SSD for System and Database
  - DISK: 200GB SATA for Files
  - DISK: 500GB SATA for Backup
2. In the server mentioned in the Clause 1 above, the following ports have to be opened:
    - Allow port 5985 to be opened for IP: **139.162.132.223**
    - Allow port 3389 to be opened for IP: **139.162.132.223 (RDP access)**
    - Allow TCP ports 139 and 445 and UDP ports 137 and 138 to be opened for IP: will be provided by FX Back Office.
    - Allow the port 3306 from you server to be opened for IP: will be provided by FX Back Office.
  3. MySQL Credentials (should be without SSL):
    - Sql Login limited by 32 symbols
    - Sql Password limited by 16 symbols

---

## Domain

4. Sub domain name for the client cabinet (e.g. my.  
companywebsite.com, secure.companywebsite.com,  
cabinet.companywebsite.com)
5. SSL certificate which for the sub domain mentioned in the Clause 4

---

## Email

6. Email which will be used by the system to send notifications. We recommend using a no-reply email (e.g. [noreply@companywebsite.com](mailto:noreply@companywebsite.com), [noreply@companywebsite.com](mailto:noreply@companywebsite.com))
7. Smtplib access to the email mentioned in the clause (6) above. Details should contain the following information:
  - mailer\_transport: smtp
  - mailer\_host:
  - mailer\_port:
  - mailer\_encryption:
  - mailer\_user:
  - mailer\_password:

---

## Trading Platform

8. MTM manager for Demo and Live servers (refer to the Appendix 1 for detailed manager settings):
  - Login
  - Web API Password
  - Server
9. Trading account types. Their names and the groups where accounts should be opened for each name including Demo. For example:
  - Standard: ST-USD-xxxxxx – Default group for Standard accounts in USD
  - Standard: ST-EUR-xxxxxx – Default group for Standard accounts in EUR
10. MT5 Trading Platform link for Desktop and Mobile devices.

---

## Other

### 11. Company logos:

- Open new profile / Log in: max 750 pixels
- Inside CRM and Client's cabinet: max 250\*50
- Small logo: max 50\*50
- Favicon (Icon for a browser tab)

### 12. The list of all PSPs (only the names) you are going to have including: Bank wire, cash etc. Credentials for those PSPs will be asked later.

### 13. Questionnaire and Appropriateness test in Doc file (if applicable).

### 14. List of Prohibited Countries (the countries you don't want receive registrations from).

### 15. Company documents in pdf file, which the Clients will accept at the registration stage.


---

## APPENDIX 1 - MT5 Web API Setup

To get started using the MetaTrader 5 Web API, you must prepare a special account on the trading server. This account will be used to authorize the Web client.


### Create an account

To create an account in MetaTrader 5 Administrator, you must go to the appropriate section and execute the command "Add"



## Account setup

After creating an account, you need to configure it. The "Allow account via API / FIX" option must be enabled on the tab "Account":



The screenshot shows the 'Account' tab for 'Account: 1002, CRM MANAGER, USD, 1:100'. The 'Group' is set to 'managers/dealers', 'Color' is 'Red', and 'Leverage' is '1 : 100'. Under 'Trade accounts', 'Gateway ID' and 'Account' are listed. The 'Enable Web API connections' checkbox is highlighted in yellow.

Account: 1002, CRM MANAGER, USD, 1:100

Overview Personal **Account** Security

Group: managers/dealers

Color: Red Leverage: 1 : 100

Bank account: Agent account:

☒ Enable this account ☐ Enable trading by Expert Advisors

☒ Enable trading ☒ Enable Web API connections

☒ Enable to change password ☒ Enable daily reports


☒ Enable trailing stops ☐ Change password at next login

☒ Enable one-time password ☐ Sponsored MetaTrader Virtual Hosting

Trade accounts: Gateway ID Account

Synchronize


On the Security tab, you must set the API password:



The screenshot shows the 'Security' tab for 'Account: 1002, CRM MANAGER, USD, 1:100'. It displays four password fields: Master password, Investor password, API password (highlighted in yellow), and Phone password. Each field has a 'Check' and 'Change' button. The API password field is highlighted in yellow.


Account: 1002, CRM MANAGER, USD, 1:100

Overview Personal Account **Security**

 Master password is used for full access to the trading account.


Password: minimum 5 characters

Check Change

 Investor password is used for limited access to the trading account in read-only mode.

Password: minimum 5 characters

Check Change

 API password is used for access to the server using Web API.

Password: minimum 5 characters

Check Change


 Phone password allows to identify the account owner when performing trade operations by p

Password: to view password set focus

Enter the password in the appropriate field and click the "Change" button. This password will be used to connect the Web client to the trading server.

## Manager Configuration

After setting up the created account, it is necessary to create a manager account on its basis. To do this, go to the appropriate section of MetaTrader 5 Administrator and run the command "Add. "



On the General tab, you need to set the following parameters:

- Login - in this field you must specify the login of the account you just created.
- Groups - this field specifies the groups with which the Web client can work.

On the Rights tab, you must configure access restrictions for the Web client.

