


Configuring Resnet 40 on Windows Vista


Note: Only computers running [Windows Vista Service Pack 1](#) or higher can connect using these instructions.

If you don't have the latest Windows updates installed on your computer, you may need to connect [manually](#).

1. To start configuring your wireless, click **Start » Connect To**.
2. A box should open displaying all available wireless networks. Select "resnet 40" and then **Connect**.




3. Select **Enter/select additional log on information**.



4. To authenticate, enter the following information:
 - User Name: **Missouri State Private ID**
 - Password: **Missouri State Password**
 - Logon domain: **SGF**

Enter Credentials



User name: PrivateID


Password: ••••••••

Logon domain: SGF


☐ Save this user name and password for future use

OK Cancel


5. Select **Enter/select additional log on information** again.



6. Select **OK** to accept the server certificate.




7. You should now be connected to the "resnet 40" network. If this method does not work try connecting [manually](http://resnet.missouristate.edu/help/wireless/resnet40-vista.php).




Setting up Resnet 40 Manually

1. At the "Connect to a network screen select "Set up a connection or network"



2. Click "Manually connect to a wireless network" then click "Next"



3. Enter "resnet 40" into Network Name. Security type should be set to "WPA2-Enterprise" and Encryption type should be "AES." Then click "Next"

Manually connect to a wireless network

Enter information for the wireless network you want to add

Network name:

Security type:

Encryption type:


Security Key/Passphrase: ☐ Display characters

☒ Start this connection automatically


☐ Connect even if the network is not broadcasting

Warning: If you select this option, your computer's privacy might be at risk.


4. Click "Change Connection Settings."




5. Click on the security tab, then click "Settings."




6. Uncheck "Validate server certificate" then click "Configure..."




7. Uncheck "Automatically use my Windows login name or password." Then click "OK" on each of the two windows.



8. Windows now needs credentials to complete the connection. Click on the network icon to access the "Enter Credentials" prompt.



9. Enter your PrivateID, password, and SGF into the User name, password, and login domain respectively. If you enter credentials incorrectly it will prompt you again.



You should now be connected to Resnet 40!