



# ONCUE PROJECTOR

## Installation Guide



Thank you for choosing OnCue Projector! Below is a first-time guide to install OnCue Projector.

## Requirements

### Hardware Requirements

HDD: Minimum 130 megabytes of free space

RAM: Minimum 300 megabytes of available memory

Display: Minimum of two displays in an extended configuration

### Software Requirements

Operating System: Windows 7 and later

Microsoft PowerPoint - for PowerPoint functionality

Windows 10 Universal C Runtime *[Only needed for Windows versions prior to Windows 10]*

## Windows 10 CRT Installation

Users running versions prior to Windows 10 will need to install the Windows 10 Universal C Runtime.

### Method 1: Windows Update

The Universal C Runtime is available through Windows Update [KB3118401] in the Recommended stream.

### Method 2: Manual Install

x86 Systems - <https://go.microsoft.com/fwlink/?LinkId=746571>

x64 Systems - <https://go.microsoft.com/fwlink/?LinkId=746572>

## Configuring Computer Displays

Open the Screen Resolution settings in the Control Panel (desk.cpl) and ensure that at least one monitor is configured to be an extended display

#### Change the appearance of your displays



Display: 2. Dell P2214H(Digital) ▼

Resolution: 1920 × 1080 (Recommended) ▼

Orientation: Landscape ▼

Multiple displays: **Extend desktop to this display** ▼

This is currently your main display.

[Advanced settings](#)

[Make text and other items larger or smaller](#)

[What display settings should I choose?](#)



# OnCue Installation


If you do not have a copy of OnCue, it is available at <http://bearbear12345.github.io/OnCue>

1. Run the *OnCue Projector Setup.exe* installer




OnCue Projector Setup

2. Change the Installation Directory if wanted, then press *Next >*




3. Select the *Create a desktop shortcut* checkbox if you want a shortcut to OnCue to be placed on the desktop. Then press *Next >*







4. Confirm the installation options, then press *Install*



5. Allow the installation to proceed



6. Installation has completed. Select the *Launch OnCue Projector* checkbox if you would like to start OnCue. Then press *Finish*






## Installation Support

Please ensure that your computer meets the minimum requirements for OnCue Projector.

### I am receiving an error that I have no write permissions

Run the installer as an elevated/administrative user.

This can be performed by running the installer while logged on as a user with administrator privileges on the target machine, or by right-clicking the installer and selecting *Run as administrator*



### I am receiving an error that there is no free disk space

Please ensure that there is at least 130MB available on the target machine.

## Further Support

Prior to contacting support, please refer to the **Troubleshooting Guide**.

Direct all technical questions to [featherbear@navhaxs.au.eu.org](mailto:featherbear@navhaxs.au.eu.org).

Read more at <http://bearbear12345.github.io/OnCue>