

Object SSA for BH.usage()V

BB0 (en)



BB1

0 nonreference field get instrctn: 2 = getstatic < Application,Ljava/lang/System, err, <Application,Ljava/io/PrintStream> >
2 invokevirtual < Application, Ljava/io/PrintStream, println(Ljava/lang/String;)V > v2,v3.#usage: java BH -b <size> [-s <steps>] [-p] [-m] [-h] @5 exception:v4



BB2

3 nonreference field get instrctn: 5 = getstatic < Application, Ljava/lang/System, err, <Application,Ljava/io/PrintStream> >
5 invokevirtual < Application, Ljava/io/PrintStream, println(Ljava/lang/String;)V > v5,v6.# -b the number of bodies @13 exception:v7



BB3

6 nonreference field get instrctn: 8 = getstatic < Application, Ljava/lang/System, err, <Application,Ljava/io/PrintStream> >
8 invokevirtual < Application, Ljava/io/PrintStream, println(Ljava/lang/String;)V > v8,v9.# -s the max. number of time steps (default=10) @21 exception:v10



BB4

9 nonreference field get instrctn: 11 = getstatic < Application, Ljava/lang/System, err, <Application,Ljava/io/PrintStream> >
11 invokevirtual < Application, Ljava/io/PrintStream, println(Ljava/lang/String;)V > v11,v12.# -p (print detailed results) @29 exception:v13



BB5

12 nonreference field get instrctn: 14 = getstatic < Application, Ljava/lang/System, err, <Application,Ljava/io/PrintStream> >
14 invokevirtual < Application, Ljava/io/PrintStream, println(Ljava/lang/String;)V > v14,v15.# -m (print information messages @37 exception:v16



BB6

15 nonreference field get instrctn: 17 = getstatic < Application, Ljava/lang/System, err, <Application,Ljava/io/PrintStream> >
17 invokevirtual < Application, Ljava/io/PrintStream, println(Ljava/lang/String;)V > v17,v18.# -h (this message) @45 exception:v19



BB7

19 invokestatic < Application, Ljava/lang/System, exit(I)V > v20:#0 @49 exception:v21



BB8

20 return



BB9 (ex)