

**NAME**

ipmi\_watchdog – IPMI watchdog

**DESCRIPTION**

The kernel module **ipmi\_watchdog** is used on systems that provide hardware watchdog functionality through an IPMI board. F.e. the Lenovo Integrated Management Module is such a board. In difference to other watchdog modules, the ipmi\_watchdog needs a running daemon.

**EXAMPLES**

\* prepare IPMI watchdog, 1st try

```
# chkconfig ipmi on
```

```
# vi /etc/sysconfig/bootloader
INITRD_MODULES="... ipmi_watchdog"
```

```
# vi /etc/modprobe.d/ipmi_watchdog
options ipmi_watchdog nowayout=0 timeout=30 action=reset_power
blacklist iTCO_wdt
blacklist iTCO_vendor_support
```

```
# shutdown -r now
```

\* prepare IPMI watchdog, 2nd try

```
# chkconfig ipmi on
```

```
# vi /etc/sysconfig/ipmi
IPMI_WATCHDOG=yes
IPMI_WATCHDOG_OPTIONS="nowayout=0 action=reset_power timeout=30"
```

\* show

```
# rcipmi status
```

```
# ipmitool mc watchdog get
```

```
# modinfo ipmi_watchdog
```

```
# ls -l /dev/watchdog
```

**FILES**

/dev/watchdog

the watchdog device node.

/lib/modules/<kernel-version>/kernel/drivers/char/ipmi/ipmi\_watchdog.ko  
the IPMI watchdog module.

/etc/init.d/ipmi

the IPMI service start script.

/etc/sysconfig/ipmi

the IPMI related configuration.

/etc/modprobe.d/ipmi\_watchdog  
the kernel module configuration.

/etc/sysconfig/kernel  
the related initrd configuration.

## BUGS

Feedback is welcome. To report bugs for a SUSE product component, please use <https://www.suse.com/support/report-a-bug/>.

## SEE ALSO

**sbd**(8), **stonith\_sbd**(7), **cs\_add\_watchdog\_to\_initrd**(8), **lsinitrd**(8), **ipmitool**(1), **modinfo**(8),  
/usr/src/linux/Documentation/watchdog/watchdog-api.txt ,  
[https://www.suse.com/documentation/sle\\_ha/book\\_sleha/data/sec\\_ha\\_storage\\_protect\\_fencing.html](https://www.suse.com/documentation/sle_ha/book_sleha/data/sec_ha_storage_protect_fencing.html) ,  
<https://www.suse.com/support/kb/doc.php?id=7016880> ,  
<https://www.suse.com/support/kb/doc.php?id=7008216> ,  
[http://download.lenovo.com/ibmdl/pub/pc/pccbbs/thinkservers/imm\\_userguide.pdf](http://download.lenovo.com/ibmdl/pub/pc/pccbbs/thinkservers/imm_userguide.pdf) ,  
[ftp://ftp.software.ibm.com/systems/support/system\\_x\\_pdf/88y7599.pdf](ftp://ftp.software.ibm.com/systems/support/system_x_pdf/88y7599.pdf)

## AUTHORS

S.Erdenberger, L.Pinne

## COPYRIGHT

(c) 2016 SUSE Linux GmbH, Germany.

ipmi\_watchdog comes with ABSOLUTELY NO WARRANTY.

For details see the GNU General Public License at <http://www.gnu.org/licenses/gpl.html>