

Atom插件

Nuclide

facebook开发的插件，提供了ide的功能。目前还没有什么研究它的功能，目前觉得Add Project Folder最有用，可以把几个开发目录放到一个视图里，这样就不需要打开多个Atom。

remote-ftp

sftp插件，需要在项目根目录增加.ftpconfig配置文件，配置简单，实现简单上传文件功能，无成功提示，更无远程文件比较功能。

```

{
  "protocol": "sftp",
  "host": "192.168.145.37", // string - Hostname or IP address of the server.
Default: 'localhost'
  "port": 22, // integer - Port number of the server. Default: 22
  "user": "", // string - Username for authentication. Default: (none)
  "pass": "", // string - Password for password-based user authentication.
Default: (none)
  "promptForPass": false, // boolean - Set to true for enable
password/passphrase dialog. This will prevent from using cleartext
password/passphrase in this config. Default: false
  "remote": "/export/wxsq/html", // try to use absolute paths starting with /
  "agent": "", // string - Path to ssh-agent's UNIX socket for ssh-agent-based
user authentication. Linux/Mac users can set "env" as a value to use env
SSH_AUTH_SOCK variable. Windows users: set to 'pageant' for authenticating with
Pageant or (actual) path to a cygwin "UNIX socket." Default: (none)
  "privatekey": "", // string - Absolute path to the private key file (in
OpenSSH format). Default: (none)
  "passphrase": "", // string - For an encrypted private key, this is the
passphrase used to decrypt it. Default: (none)
  "hosthash": "", // string - 'md5' or 'sha1'. The host's key is hashed using
this method and passed to the hostVerifier function. Default: (none)
  "ignorehost": true,
  "connTimeout": 10000, // integer - How long (in milliseconds) to wait for the
SSH handshake to complete. Default: 10000
  "keepalive": 10000, // integer - How often (in milliseconds) to send SSH-
level keepalive packets to the server (in a similar way as OpenSSH's
ServerAliveInterval config option). Set to 0 to disable. Default: 10000
  "keyboardInteractive": false, // boolean - Set to true for enable verifyCode
dialog. Keyboard interaction authentication mechanism. For example using Google
Authentication (Multi factor)
  "keyboardInteractiveForPass": false, // boolean - Set to true for enable
keyboard interaction and use pass options for password. No open dialog.
  "watch": [ // array - Paths to files, directories, or glob patterns that are
watched and when edited outside of the atom editor are uploaded. Default : []
    "./dist/stylesheets/main.css", // reference from the root of the project.
    "./dist/stylesheets/",
    "./dist/stylesheets/*.css"
  ],

```

```
"watchTimeout":500, // integer - The duration ( in milliseconds ) from when
the file was last changed for the upload to begin.
"filePermissions":"0644" // string - Permissions for uploaded files. WARNING:
if this option is set, previously set permissions on the remote are overwritten!
}
```

markdown

- Markdown-img-paste

可以直接粘贴截图。图片可以选择截图保存在本地，通过相对路径引用。也可以选择截图保存到服务器。如果是上传到服务器，图片会自动保存到sm.ms服务器。保存到七牛云就不推荐，还需要填写七牛云的账号信息。注意粘贴图片的快捷键control+shift+v（mac下），并非ctrl + v 设置如下。

Settings

☒ Only in markdown grammar to enable the plugin

☒ Use sm.ms for image link

☐ Use qiniu for image link

☐ Save images in assets folder

<https://atom.io/packages/markdown-img-paste>

- markdown-pdf

转换markdownw格式文本为pdf文件，没有快捷键，稍微麻烦一点，看说明markdown-themeable-pdf更好用一点，但是一直安装不上。