

# Projet 1

## Fichier pjsip.conf

```
[simpletrans-udp]
```

```
type=transport
```

```
protocol=udp
```

```
bind=0.0.0.0
```

```
[ENDPOINT](!) #Template endpoint
```

```
type=endpoint
```

```
transport=simpletrans-udp
```

```
disallow=all
```

```
allow=ulaw
```

```
allow=gsm
```

```
[AUTH](!) #Template Authentication
```

```
type=auth
```

```
auth_type=userpass
```

```
[AOR](!) #Template Aor
```

```
type=aor
```

```
max_contacts=1
```

```
,=====TELEPHONES ADMINISTRATION=====
```

```
;=====1001
```

[1001](ENDPOINT)

context=ADMIN

auth=1001

aors=1001

[1001](AUTH)

username=1001

password=motpass

[1001](AOR)

contact=sip:1001@192.168.1.20:5060

;=====1002

[1002](ENDPOINT)

context=ADMIN

auth=1002

aors=1002

[1002](AUTH)

username=1002

password=motpass

[1002](AOR)

contact=sip:1002@192.168.1.20:5060

;=====1003

[1003](ENDPOINT)

context=ADMIN

auth=1003

aors=1003

[1003](AUTH)

username=1003

password=motpass

[1003](AOR)

contact=sip:1003@192.168.1.20:5060

;=====1004

[1004](ENDPOINT)

context=ADMIN

auth=1004

aors=1004

[1004](AUTH)

username=1004

password=motpass

[1004](AOR)

contact=sip:1004@192.168.1.20:5060

,=====TELEPHONES DEVELOPPEMENT=====

;=====301

[301](ENDPOINT)

context=DEV

auth=301

aors=301

[301](AUTH)

username=301

password=motpass

[301](AOR)

contact=sip:301@192.168.1.20:5060

;=====302

[302](ENDPOINT)

context=DEV

auth=302

aors=302

[302](AUTH)

username=302

password=motpass

[302](AOR)

contact=sip:302@192.168.1.20:5060

;=====303

[303](ENDPOINT)

context=DEV

auth=303

aors=303

[303](AUTH)

username=303

password=motpass

[303](AOR)

contact=sip:303@192.168.1.20:5060

;=====304

[304](ENDPOINT)

context=DEV

auth=304

aors=304

[304](AUTH)

username=304

password=motpass

[304](AOR)

contact=sip:304@192.168.1.20:5060

;=====305

[305](ENDPOINT)

context=DEV

auth=305

aors=305

[305](AUTH)

username=305

Password=motpass

[305](AOR)

contact=sip:305@192.168.1.20:5060

;=====306

[306](ENDPOINT)

context=DEV

auth=306

aors=306

[306](AUTH)

username=306

password=motpass

[306](AOR)

contact=sip:306@192.168.1.20:5060

,=====TELEPHONES SECURITE=====

;=====7001

[7001](ENDPOINT)

context=SECU

auth=7001

aors=7001

[7001](AUTH)

username=7001

password=motpass

[7001](AOR)

contact=sip:7001@192.168.1.20:5060

;=====7002

[7002](ENDPOINT)

context=SECU

auth=7002

aors=7002

[7002](AUTH)

username=7002

password=motpass

[7002](AOR)

contact=sip:7002@192.168.1.20:5060

;=====7003

[7003](ENDPOINT)

context=SECU

auth=7003

aors=7003

[7003](AUTH)

username=7003

password=motpass

[7003](AOR)

contact=sip:7003@192.168.1.20:5060