

# REUSE ALV PF Status

REUSE\_ALV\_POPUP\_TO\_SELECT\_PF\_STATUS, SAP sisteminde bulunan bir ALV fonksiyonudur. Bu fonksiyon, bir ALV Listesi'nin kullanıcı arayüzünde, ekran düzeni ve işlevsellik için bir PF Status (Process Flow Status) belirlemek için kullanılır.

PF Status, bir SAP ekranında kullanıcının mevcut işlemin durumunu gösteren bir gösterge çubuğu veya menüdür. REUSE\_ALV\_POPUP\_TO\_SELECT\_PF\_STATUS, ALV Listesi'nde kullanılan standart PF Status belirlemek yerine, özel bir PF Status tanımlamanıza olanak tanır.

Bu fonksiyon, bir PF Status'u tanımlamanız ve özelleştirmeniz için bir dizi seçenek sağlar. Örneğin, ekran düzeni ve işlevselliği için butonlar, menüler, simgeler ve diğer öğeleri belirleyebilirsiniz.

Bu fonksiyonun kullanımı, bir ALV Listesi'nin kullanıcı arayüzünün özelleştirilmesini gerektiren durumlarda çok yararlıdır. Örneğin, kullanıcının bir ALV Listesi'nde seçim yapması veya verileri düzenlemesi gerektiğinde,

REUSE\_ALV\_POPUP\_TO\_SELECT\_PF\_STATUS fonksiyonu kullanılabilir.

PF\_STATUS\_SET adında bir form oluşturduktan sonra bu form adını reuse alv içerisinde tanımlıyoruz.

```
*&-----
FORM display_alv .
  gs_event-name = slis_ev_top_of_page.
  gs_event-form = 'TOP_OF_PAGE'.
  APPEND gs_event TO gt_events.
  gs_event-name = slis_ev_end_of_list.
  gs_event-form = 'END_OF_LIST'.
  APPEND gs_event TO gt_events.

  CALL FUNCTION 'REUSE_ALV_GRID_DISPLAY'
    EXPORTING
      I_INTERFACE_CHECK = ' '
      I_BYPASSING_BUFFER = ' '
      I_BUFFER_ACTIVE = ' '
      I_CALLBACK_PROGRAM = sy-repid
      I_CALLBACK_PF_STATUS_SET = 'PF STATUS SET'
      I_CALLBACK_USER_COMMAND = ' '
      I_CALLBACK_TOP_OF_PAGE = 'TOP_OF_PAGE'
```

Method tanımlamalarını gerçekleştiriyoruz;


```
*&-----
FORM pf_status_set USING p_extab TYPE slis_t_extab .
  set PF-STATUS ' '.
ENDFORM.
```

```
FORM pf_status_set USING p_extab TYPE slis_t_extab .
```

```
    set PF-STATUS '0200'.
```

```
ENDFORM.
```

Eski derslerde olduğu gibi, şimdi de bir GUI Status oluşturuyoruz. Fakat bu sefer farklı olacak bir durum mevcut o da STATUS kopyalama olarak geçmektedir.




Aynı zamanda bu tanımladığımız 0100'lu GUI Status'u form içerisinde tanımlıyoruz.

```
FORM pf_status_set USING p_extab TYPE slis_t_extab .  
    set PF-STATUS '0100'.  
ENDFORM.
```




Birinci yol;



The screenshot shows the SAP ABAP Unit Browser interface. The left pane displays the object hierarchy under 'ATC Re'. The 'SALV' object is selected, and a context menu is open with the 'Copy...' option highlighted. The right pane shows the description of the 'SALV' object, which is 'SAP List Viewer'.

```
8 * User-defined Include-fi
9 *****
10 * INCLUDE LSALVF...
11 * INCLUDE LSALVO...
12 * INCLUDE LSALVI...
13
14 INCLUDE LSALVF01.
15 INCLUDE LSALVF02.
```

Ve nereye kopyalanacağını da çıkan ekranda belirledikten sonra;





The screenshot shows the SAP ABAP Unit Browser interface. The left pane displays the object hierarchy under 'Program'. The 'ZB\_REUSE' object is selected, and a context menu is open with the 'Copy...' option highlighted. The right pane shows the description of the 'ZB\_REUSE' object, which is 'reuse eğitimleri'.

```
Object Name      Description
-----
ZB_REUSE        reuse eğitimleri
  Types
  Fields
  Events
  Subroutines
  GUI Status
    0100          0100
                  Standard for General Lis
    0200
  Includes
    ZB_REUSE_FRM  Include ZB_REUSE_FRM
    ZB_REUSE_TOP  Include ZB_REUSE_TOP
```

0200 id verdigimiz status ZB\_REUSE programına gelmiş oldu.





Enhancement Info System  
ABAP Unit Browser  
ATC Result Browser

Program  
ZB\_REUSE

Object Name Description

ZB_REUSE	reuse egitimleri
Events	
Includes	
Fields	
Types	
Subroutines	
GUI Status	
0100	0100
0200	Standard for General Lis
0300	Standard for General Lis

```
11 START-O
12
13 PERFORM
14 PERFORM
15 PERFORM
16 PERFORM
17 *gt_lis
18 *alma g
19 * SELE
20
21
22 *SELECT
23
24
25
26
27
28
29
30 FROM
31 INNE
32 ON s
33 AND
34 WHER
35 AND
36 INTO
```

Üzerine 'mesaj bas' isminde bir buton eklemek;

Function Code Delete subobject

User Interface ZB\_REUSE Active

Menu Bar Standard User Interface STANDARD

Application Toolbar Standard Maximum Interaction

Items 1 - 7

&ETA	&EB9	&ALL	&SAL	&OUP
&UMC	&SUM	&XPA	&OMP	
&AQW	%PC	%SL	&ABC	
&AVE		&LFO	&NFO Select	
&CRR	&CRE	&msg		

Enter Function Text

Function &MSG

There is no text assigned to this function

Create a Function Text

Choose Text Type

☒ Static Text

☐ Dynamic Text

Standard Maximum Interaction