

Contd from solace cli command.....

Define message-spool


enable

config

message-spool message-vpn change-message-vpn

create queue queuecli02

Max-spool-usage 100




```
mr-connection-ekiwk28m759.messaging.solace.cloud - PuTTY
developer-production-69xlr5fp56g-solace-primary-0> enable
developer-production-69xlr5fp56g-solace-primary-0# config
developer-production-69xlr5fp56g-solace-primary-0 (configure)# message-spool mess
age-vpn change-message-vpn
developer-production-69xlr5fp56g-solace-primary-0 (configure/message-spool)# crea
te queue queuecli02
developer-production-69xlr5fp56g-solace-primary-0 (configure/message-spool/queue)
# message-spool usage 50

Invalid command input
  message-spool usage 50
  ^
  -> unknown command, or command not available in current mode
developer-production-69xlr5fp56g-solace-primary-0 (configure/message-spool/queue)
# message-spool-usage 50

Invalid command input
  message-spool-usage 50
  ^
  -> unknown command, or command not available in current mode
developer-production-69xlr5fp56g-solace-primary-0 (configure/message-spool/queue)
# max-spool-usage 100
developer-production-69xlr5fp56g-solace-primary-0 (configure/message-spool/queue)
#
```

permission all consume

no shut



```
message-spool-usage 50
^
-> unknown command, or command not available in current mode
developer-production-69xlr5fp56g-solace-primary-0 (configure/message-spool/queue)
# max-spool-usage 100
developer-production-69xlr5fp56g-solace-primary-0 (configure/message-spool/queue)
# permission all consume
developer-production-69xlr5fp56g-solace-primary-0 (configure/message-spool/queue)
# no shut
developer-production-69xlr5fp56g-solace-primary-0 (configure/message-spool/queue)
#
```

show queue *

show queue queuccli02 detail

```
Flags Legend:
I - Ingress Admin State (U=Up, D=Down)
E - Egress Admin State (U=Up, D=Down)
A - Access-Type (E=Exclusive, N=Non-Exclusive)
S - Selector (Y=Yes, N=No)
D - Durability (D=Durable, N=Non-Durable)
P - Priority (Y=Yes, N=No)

Queue Name           Messages      Spool
Message VPN         Spooled      Usage (MB)    HWM (MB)  Bind Status
-----
queue01
change-message-vpn      3         0.00         0.00      0 U U E N D N


queue02
change-message-vpn      0         0.00         0.00      0 U U E N D N

queuecli01
change-message-vpn      0         0.00         0.00      0 U U E N D N

queuecli02
change-message-vpn      0         0.00         0.00      0 U U E N D N
---Press any key to continue, or `q' to quit---
```

```
Name                  : queuecli02
Message VPN           : change-message-vpn
Durability             : Durable
Id                    : 8
Admin Ingress         : Up
Admin Egress          : Up
Access Type           : Exclusive
Partition Count       : 0
Owner                 :
Created by mgmt       : Yes
All Others Permission  : Consume (1100)
Quota (MB)            : 100
Respect Message Priority : No
Respect TTL           : No
Max TTL (Seconds)     : 0 (Disabled)
Well Known            : Yes
Reject Msg to Sender on Discard : Yes
Including When Shutdown : No
Bind Time Forwarding Mode : Store-And-Forward
Current Messages Spooled : 0
Current Spool Usage (MB) : 0.0000
High Water Mark (MB)  : 0.0000
---Press any key to continue, or `q' to quit---
```

Session restart→ getting into queuecli02
enable
config
message-spool message-vpn change-message-vpn
queue queuecli02
subscription topic hellocli02 (to create a topic in subscription)



```
mr-connection-ekiwk28m759.messaging.solace.cloud - PuTTY
Current Spool Usage (MB)          : 0.0000
High Water Mark (MB)             : 0.0000
---Press any key to continue, or `q` to quit---
Command aborted.
developer-production-69xlr5fp56g-solace-primary-0> enabl
developer-production-69xlr5fp56g-solace-primary-0# enable

Invalid command input
  enable
    ^
    -> unknown command, or command not available in current mode
developer-production-69xlr5fp56g-solace-primary-0# config
developer-production-69xlr5fp56g-solace-primary-0(configure)# message-spool mess
age-vpn change-messae-vpn
ERROR: Cannot enter mode for message-vpn change-messae-vpn: not found.
ERROR: Cannot enter message-spool mode: not found.
developer-production-69xlr5fp56g-solace-primary-0(configure)# message-spool mess
age-vpn change-message-vpn
developer-production-69xlr5fp56g-solace-primary-0(configure/message-spool)# queu
e queuecli02
developer-production-69xlr5fp56g-solace-primary-0(configure/message-spool/queue)
# subscription topic hellocli02
developer-production-69xlr5fp56g-solace-primary-0(configure/message-spool/queue)
#
```